
Amazon Elastic Compute Cloud

CLI Reference

API Version 2013-02-01



Amazon Elastic Compute Cloud: CLI Reference

Copyright © 2013 Amazon Web Services, Inc. and/or its affiliates. All rights reserved.

The following are trademarks of Amazon Web Services, Inc.: Amazon, Amazon Web Services Design, AWS, Amazon CloudFront, Cloudfront, Amazon DevPay, DynamoDB, ElastiCache, Amazon EC2, Amazon Elastic Compute Cloud, Amazon Glacier, Kindle, Kindle Fire, AWS Marketplace Design, Mechanical Turk, Amazon Redshift, Amazon Route 53, Amazon S3, Amazon VPC. In addition, Amazon.com graphics, logos, page headers, button icons, scripts, and service names are trademarks, or trade dress of Amazon in the U.S. and/or other countries. Amazon's trademarks and trade dress may not be used in connection with any product or service that is not Amazon's, in any manner that is likely to cause confusion among customers, or in any manner that disparages or discredits Amazon.

All other trademarks not owned by Amazon are the property of their respective owners, who may or may not be affiliated with, connected to, or sponsored by Amazon.

Welcome	1
List of Commands by Function	2
Commands (CLI Tools)	8
ec2-allocate-address	12
ec2-assign-private-ip-addresses	16
ec2-associate-address	20
ec2-associate-dhcp-options	25
ec2-associate-route-table	29
ec2-attach-internet-gateway	33
ec2-attach-network-interface	37
ec2-attach-volume	41
ec2-attach-vpn-gateway	45
ec2-authorize	49
ec2-bundle-instance	56
ec2-cancel-bundle-task	61
ec2-cancel-conversion-task	64
ec2-cancel-export-task	68
ec2-cancel-reserved-instances-listing	71
ec2-cancel-spot-instance-requests	75
ec2-confirm-product-instance	79
ec2-copy-image	82
ec2-copy-snapshot	85
ec2-create-customer-gateway	89
ec2-create-dhcp-options	93
ec2-create-group	97
ec2-create-image	102
ec2-create-instance-export-task	107
ec2-create-internet-gateway	111
ec2-create-keypair	114
ec2-create-network-acl	118
ec2-create-network-acl-entry	121
ec2-create-network-interface	126
ec2-create-placement-group	131
ec2-create-reserved-instances-listing	134
ec2-create-route	139
ec2-create-route-table	143
ec2-create-snapshot	146
ec2-create-spot-datafeed-subscription	150
ec2-create-subnet	154
ec2-create-tags	158
ec2-create-volume	162
ec2-create-vpc	167
ec2-create-vpn-connection	171
ec2-create-vpn-gateway	176
ec2-create-vpn-connection-route	180
ec2-delete-customer-gateway	183
ec2-delete-dhcp-options	186
ec2-delete-disk-image	189
ec2-delete-group	192
ec2-delete-internet-gateway	196
ec2-delete-keypair	199
ec2-delete-network-acl	202
ec2-delete-network-acl-entry	205
ec2-delete-network-interface	209
ec2-delete-placement-group	212
ec2-delete-route	215
ec2-delete-route-table	218
ec2-delete-snapshot	221

ec2-delete-spot-datafeed-subscription	224
ec2-delete-subnet	227
ec2-delete-tags	230
ec2-delete-volume	234
ec2-delete-vpc	237
ec2-delete-vpn-connection	240
ec2-delete-vpn-connection-route	243
ec2-delete-vpn-gateway	246
ec2-deregister	249
ec2-describe-account-attributes	252
ec2-describe-addresses	256
ec2-describe-availability-zones	262
ec2-describe-bundle-tasks	267
ec2-describe-conversion-tasks	272
ec2-describe-customer-gateways	276
ec2-describe-dhcp-options	281
ec2-describe-export-tasks	286
ec2-describe-group	289
ec2-describe-image-attribute	295
ec2-describe-images	299
ec2-describe-instance-attribute	308
ec2-describe-instance-status	313
ec2-describe-instances	320
ec2-describe-internet-gateways	333
ec2-describe-keypairs	338
ec2-describe-network-acls	342
ec2-describe-network-interface-attribute	348
ec2-describe-network-interfaces	352
ec2-describe-placement-groups	359
ec2-describe-regions	363
ec2-describe-reserved-instances	367
ec2-describe-reserved-instances-listings	373
ec2-describe-reserved-instances-offerings	378
ec2-describe-route-tables	386
ec2-describe-snapshot-attribute	391
ec2-describe-snapshots	395
ec2-describe-spot-datafeed-subscription	401
ec2-describe-spot-instance-requests	404
ec2-describe-spot-price-history	412
ec2-describe-subnets	418
ec2-describe-tags	423
ec2-describe-volume-attribute	428
ec2-describe-volume-status	432
ec2-describe-volumes	438
ec2-describe-vpc-attribute	444
ec2-describe-vpcs	448
ec2-describe-vpn-connections	453
ec2-describe-vpn-gateways	459
ec2-detach-internet-gateway	464
ec2-detach-network-interface	467
ec2-detach-volume	471
ec2-detach-vpn-gateway	475
ec2-disable-vgw-route-propagation	479
ec2-disassociate-address	482
ec2-disassociate-route-table	486
ec2-enable-volume-io	490
ec2-enable-vgw-route-propagation	493
ec2-fingerprint-key	496

ec2-get-console-output	499
ec2-get-password	503
ec2-import-instance	507
ec2-import-keypair	514
ec2-import-volume	518
ec2-migrate-image	524
ec2-modify-image-attribute	530
ec2-modify-instance-attribute	535
ec2-modify-network-interface-attribute	541
ec2-modify-snapshot-attribute	545
ec2-modify-volume-attribute	549
ec2-modify-vpc-attribute	553
ec2-monitor-instances	556
ec2-purchase-reserved-instances-offering	559
ec2-reboot-instances	563
ec2-register	566
ec2-release-address	572
ec2-replace-network-acl-association	576
ec2-replace-network-acl-entry	580
ec2-replace-route	584
ec2-replace-route-table-association	588
ec2-report-instance-status	592
ec2-request-spot-instances	597
ec2-reset-image-attribute	608
ec2-reset-instance-attribute	611
ec2-reset-network-interface-attribute	615
ec2-reset-snapshot-attribute	618
ec2-resume-import	622
ec2-revoke	627
ec2-run-instances	633
ec2-start-instances	646
ec2-stop-instances	650
ec2-terminate-instances	654
ec2-unassign-private-ip-addresses	657
ec2-unmonitor-instances	660
ec2-upload-disk-image	663
ec2-version	667
Common Options	669
Commands (AMI Tools)	672
ec2-bundle-image	673
ec2-bundle-vol	677
ec2-delete-bundle	682
ec2-download-bundle	685
ec2-migrate-bundle	688
ec2-migrate-manifest	692
ec2-unbundle	695
ec2-upload-bundle	697
Common Options	699

Welcome

This is the *Amazon Elastic Compute Cloud Command Line Reference*. It provides descriptions, syntax, and usage examples for each of the commands for Amazon EC2 and Amazon Virtual Private Cloud (Amazon VPC). The commands wrap the Amazon EC2 API actions.

How Do I?	Relevant Topics
Download the command line tools	Amazon EC2 CLI Tools Amazon EC2 AMI Tools
Prepare to use the command line tools	Setting Up the Command Line Interface Tools (in the <i>Amazon Elastic Compute Cloud User Guide</i>)
Get the alphabetical list of commands	Commands (CLI Tools) (p. 8) Commands (AMI Tools) (p. 672)
Get the list of the common options for the commands	Common Options for CLI Tools (p. 669) Common Options for AMI Tools (p. 699)
Get descriptions of the error codes	Error Codes (in the <i>Amazon Elastic Compute Cloud API Reference</i>)
Get the list of regions and endpoints	Regions and Endpoints

Related Topics

- [Amazon EC2 product page](#)
- [Amazon Elastic Compute Cloud User Guide](#)
- [Amazon Virtual Private Cloud User Guide](#)
- [Amazon Elastic Compute Cloud API Reference](#)

List of Commands by Function

Account Attributes

- [ec2-describe-account-attributes](#) (p. 252)

Amazon DevPay

- [ec2-confirm-product-instance](#) (p. 79)

AMIs

- [ec2-copy-image](#) (p. 82)
- [ec2-create-image](#) (p. 102)
- [ec2-deregister](#) (p. 249)
- [ec2-describe-image-attribute](#) (p. 295)
- [ec2-describe-images](#) (p. 299)
- [ec2-migrate-image](#) (p. 524)
- [ec2-modify-image-attribute](#) (p. 530)
- [ec2-register](#) (p. 566)
- [ec2-reset-image-attribute](#) (p. 608)

AMI Bundling (API Tools)

- [ec2-bundle-image](#) (p. 673)
- [ec2-bundle-vol](#) (p. 677)
- [ec2-delete-bundle](#) (p. 682)
- [ec2-download-bundle](#) (p. 685)
- [ec2-migrate-bundle](#) (p. 688)
- [ec2-migrate-manifest](#) (p. 692)
- [ec2-unbundle](#) (p. 695)

- [ec2-upload-bundle](#) (p. 697)

Bundle Tasks

- [ec2-bundle-instance](#) (p. 56)
- [ec2-cancel-bundle-task](#) (p. 61)
- [ec2-describe-bundle-tasks](#) (p. 267)

Customer Gateways (Amazon VPC)

- [ec2-create-customer-gateway](#) (p. 89)
- [ec2-delete-customer-gateway](#) (p. 183)
- [ec2-describe-customer-gateways](#) (p. 276)

DHCP Options (Amazon VPC)

- [ec2-associate-dhcp-options](#) (p. 25)
- [ec2-create-dhcp-options](#) (p. 93)
- [ec2-delete-dhcp-options](#) (p. 186)
- [ec2-describe-dhcp-options](#) (p. 281)

Elastic Block Store

- [ec2-attach-volume](#) (p. 41)
- [ec2-copy-snapshot](#) (p. 85)
- [ec2-create-snapshot](#) (p. 146)
- [ec2-create-volume](#) (p. 162)
- [ec2-delete-disk-image](#) (p. 189)
- [ec2-delete-snapshot](#) (p. 221)
- [ec2-delete-volume](#) (p. 234)
- [ec2-describe-snapshot-attribute](#) (p. 391)
- [ec2-describe-snapshots](#) (p. 395)
- [ec2-describe-volume-attribute](#) (p. 428)
- [ec2-describe-volumes](#) (p. 438)
- [ec2-describe-volume-status](#) (p. 432)
- [ec2-detach-volume](#) (p. 471)
- [ec2-enable-volume-io](#) (p. 490)
- [ec2-import-volume](#) (p. 518)
- [ec2-modify-snapshot-attribute](#) (p. 545)
- [ec2-modify-volume-attribute](#) (p. 549)
- [ec2-reset-snapshot-attribute](#) (p. 618)

Elastic IP Addresses

- [ec2-allocate-address](#) (p. 12)
- [ec2-associate-address](#) (p. 20)
- [ec2-describe-addresses](#) (p. 256)
- [ec2-disassociate-address](#) (p. 482)
- [ec2-release-address](#) (p. 572)

Elastic Network Interfaces (Amazon VPC)

- [ec2-attach-network-interface](#) (p. 37)
- [ec2-create-network-interface](#) (p. 126)
- [ec2-delete-network-interface](#) (p. 209)
- [ec2-describe-network-interfaces](#) (p. 352)
- [ec2-describe-network-interface-attribute](#) (p. 348)
- [ec2-detach-network-interface](#) (p. 467)
- [ec2-modify-network-interface-attribute](#) (p. 541)
- [ec2-reset-network-interface-attribute](#) (p. 615)

Instances

- [ec2-describe-instance-attribute](#) (p. 308)
- [ec2-describe-instance-status](#) (p. 313)
- [ec2-describe-instances](#) (p. 320)
- [ec2-get-console-output](#) (p. 499)
- [ec2-get-password](#) (p. 503)
- [ec2-import-instance](#) (p. 507)
- [ec2-modify-instance-attribute](#) (p. 535)
- [ec2-reboot-instances](#) (p. 563)
- [ec2-reset-instance-attribute](#) (p. 611)
- [ec2-run-instances](#) (p. 633)
- [ec2-start-instances](#) (p. 646)
- [ec2-stop-instances](#) (p. 650)
- [ec2-terminate-instances](#) (p. 654)

Internet Gateways (Amazon VPC)

- [ec2-attach-internet-gateway](#) (p. 33)
- [ec2-create-internet-gateway](#) (p. 111)
- [ec2-delete-internet-gateway](#) (p. 196)
- [ec2-describe-internet-gateways](#) (p. 333)
- [ec2-detach-internet-gateway](#) (p. 464)

Key Pairs

- [ec2-create-keypair](#) (p. 114)
- [ec2-delete-keypair](#) (p. 199)
- [ec2-describe-keypairs](#) (p. 338)
- [ec2-fingerprint-key](#) (p. 496)
- [ec2-import-keypair](#) (p. 514)

Monitoring

- [ec2-monitor-instances](#) (p. 556)
- [ec2-unmonitor-instances](#) (p. 660)

Network ACLs (Amazon VPC)

- [ec2-create-network-acl](#) (p. 118)
- [ec2-create-network-acl-entry](#) (p. 121)
- [ec2-delete-network-acl](#) (p. 202)
- [ec2-delete-network-acl-entry](#) (p. 205)
- [ec2-describe-network-acls](#) (p. 342)
- [ec2-replace-network-acl-association](#) (p. 576)
- [ec2-replace-network-acl-entry](#) (p. 580)

Placement Groups

- [ec2-create-placement-group](#) (p. 131)
- [ec2-delete-placement-group](#) (p. 212)
- [ec2-describe-placement-groups](#) (p. 359)

Regions and Availability Zones

- [ec2-describe-availability-zones](#) (p. 262)
- [ec2-describe-regions](#) (p. 363)

Reserved Instances

- [ec2-cancel-reserved-instances-listing](#) (p. 71)
- [ec2-create-reserved-instances-listing](#) (p. 134)
- [ec2-describe-reserved-instances](#) (p. 367)
- [ec2-describe-reserved-instances-listings](#) (p. 373)
- [ec2-describe-reserved-instances-offerings](#) (p. 378)
- [ec2-purchase-reserved-instances-offering](#) (p. 559)

Route Tables (Amazon VPC)

- [ec2-associate-route-table](#) (p. 29)
- [ec2-create-route](#) (p. 139)
- [ec2-create-route-table](#) (p. 143)
- [ec2-delete-route](#) (p. 215)
- [ec2-delete-route-table](#) (p. 218)
- [ec2-describe-route-tables](#) (p. 386)
- [ec2-disassociate-route-table](#) (p. 486)
- [ec2-replace-route](#) (p. 584)
- [ec2-replace-route-table-association](#) (p. 588)

Security Groups

- [ec2-authorize](#) (p. 49)
- [ec2-create-group](#) (p. 97)
- [ec2-delete-group](#) (p. 192)
- [ec2-describe-group](#) (p. 289)
- [ec2-revoke](#) (p. 627)

Spot Instances

- [ec2-cancel-spot-instance-requests](#) (p. 75)
- [ec2-create-spot-datafeed-subscription](#) (p. 150)
- [ec2-delete-spot-datafeed-subscription](#) (p. 224)
- [ec2-describe-spot-datafeed-subscription](#) (p. 401)
- [ec2-describe-spot-instance-requests](#) (p. 404)
- [ec2-describe-spot-price-history](#) (p. 412)
- [ec2-request-spot-instances](#) (p. 597)

Subnets (Amazon VPC)

- [ec2-create-subnet](#) (p. 154)
- [ec2-delete-subnet](#) (p. 227)
- [ec2-describe-subnets](#) (p. 418)

Tags

- [ec2-create-tags](#) (p. 158)
- [ec2-delete-tags](#) (p. 230)
- [ec2-describe-tags](#) (p. 423)

VM Import

- [ec2-cancel-conversion-task](#) (p. 64)
- [ec2-delete-disk-image](#) (p. 189)
- [ec2-describe-conversion-tasks](#) (p. 272)
- [ec2-import-instance](#) (p. 507)
- [ec2-import-volume](#) (p. 518)
- [ec2-resume-import](#) (p. 622)

VM Export

- [ec2-cancel-export-task](#) (p. 68)
- [ec2-create-instance-export-task](#) (p. 107)
- [ec2-describe-export-tasks](#) (p. 286)

VPCs (Amazon VPC)

- [ec2-create-vpc](#) (p. 167)
- [ec2-delete-vpc](#) (p. 237)
- [ec2-describe-vpc-attribute](#) (p. 444)
- [ec2-describe-vpcs](#) (p. 448)
- [ec2-modify-vpc-attribute](#) (p. 553)

VPN Connections (Amazon VPC)

- [ec2-create-vpn-connection](#) (p. 171)
- [ec2-delete-vpn-connection](#) (p. 240)
- [ec2-describe-vpn-connections](#) (p. 453)

Virtual Private Gateways (Amazon VPC)

- [ec2-attach-vpn-gateway](#) (p. 45)
- [ec2-create-vpn-gateway](#) (p. 176)
- [ec2-delete-vpn-gateway](#) (p. 246)
- [ec2-describe-vpn-gateways](#) (p. 459)
- [ec2-detach-vpn-gateway](#) (p. 475)

Commands (CLI Tools)

You install and run the CLI tools to manage your Amazon EC2 resources (such as instances, security groups, and volumes) and your Amazon VPC resources (such as VPCs, subnets, route tables, and Internet gateways).

Topics

- [ec2-allocate-address](#) (p. 12)
- [ec2-assign-private-ip-addresses](#) (p. 16)
- [ec2-associate-address](#) (p. 20)
- [ec2-associate-dhcp-options](#) (p. 25)
- [ec2-associate-route-table](#) (p. 29)
- [ec2-attach-internet-gateway](#) (p. 33)
- [ec2-attach-network-interface](#) (p. 37)
- [ec2-attach-volume](#) (p. 41)
- [ec2-attach-vpn-gateway](#) (p. 45)
- [ec2-authorize](#) (p. 49)
- [ec2-bundle-instance](#) (p. 56)
- [ec2-cancel-bundle-task](#) (p. 61)
- [ec2-cancel-conversion-task](#) (p. 64)
- [ec2-cancel-export-task](#) (p. 68)
- [ec2-cancel-reserved-instances-listing](#) (p. 71)
- [ec2-cancel-spot-instance-requests](#) (p. 75)
- [ec2-confirm-product-instance](#) (p. 79)
- [ec2-copy-image](#) (p. 82)
- [ec2-copy-snapshot](#) (p. 85)
- [ec2-create-customer-gateway](#) (p. 89)
- [ec2-create-dhcp-options](#) (p. 93)
- [ec2-create-group](#) (p. 97)
- [ec2-create-image](#) (p. 102)
- [ec2-create-instance-export-task](#) (p. 107)
- [ec2-create-internet-gateway](#) (p. 111)
- [ec2-create-keypair](#) (p. 114)
- [ec2-create-network-acl](#) (p. 118)

- [ec2-create-network-acl-entry](#) (p. 121)
- [ec2-create-network-interface](#) (p. 126)
- [ec2-create-placement-group](#) (p. 131)
- [ec2-create-reserved-instances-listing](#) (p. 134)
- [ec2-create-route](#) (p. 139)
- [ec2-create-route-table](#) (p. 143)
- [ec2-create-snapshot](#) (p. 146)
- [ec2-create-spot-datafeed-subscription](#) (p. 150)
- [ec2-create-subnet](#) (p. 154)
- [ec2-create-tags](#) (p. 158)
- [ec2-create-volume](#) (p. 162)
- [ec2-create-vpc](#) (p. 167)
- [ec2-create-vpn-connection](#) (p. 171)
- [ec2-create-vpn-gateway](#) (p. 176)
- [ec2-create-vpn-connection-route](#) (p. 180)
- [ec2-delete-customer-gateway](#) (p. 183)
- [ec2-delete-dhcp-options](#) (p. 186)
- [ec2-delete-disk-image](#) (p. 189)
- [ec2-delete-group](#) (p. 192)
- [ec2-delete-internet-gateway](#) (p. 196)
- [ec2-delete-keypair](#) (p. 199)
- [ec2-delete-network-acl](#) (p. 202)
- [ec2-delete-network-acl-entry](#) (p. 205)
- [ec2-delete-network-interface](#) (p. 209)
- [ec2-delete-placement-group](#) (p. 212)
- [ec2-delete-route](#) (p. 215)
- [ec2-delete-route-table](#) (p. 218)
- [ec2-delete-snapshot](#) (p. 221)
- [ec2-delete-spot-datafeed-subscription](#) (p. 224)
- [ec2-delete-subnet](#) (p. 227)
- [ec2-delete-tags](#) (p. 230)
- [ec2-delete-volume](#) (p. 234)
- [ec2-delete-vpc](#) (p. 237)
- [ec2-delete-vpn-connection](#) (p. 240)
- [ec2-delete-vpn-connection-route](#) (p. 243)
- [ec2-delete-vpn-gateway](#) (p. 246)
- [ec2-deregister](#) (p. 249)
- [ec2-describe-account-attributes](#) (p. 252)
- [ec2-describe-addresses](#) (p. 256)
- [ec2-describe-availability-zones](#) (p. 262)
- [ec2-describe-bundle-tasks](#) (p. 267)
- [ec2-describe-conversion-tasks](#) (p. 272)
- [ec2-describe-customer-gateways](#) (p. 276)
- [ec2-describe-dhcp-options](#) (p. 281)
- [ec2-describe-export-tasks](#) (p. 286)
- [ec2-describe-group](#) (p. 289)

- [ec2-describe-image-attribute](#) (p. 295)
- [ec2-describe-images](#) (p. 299)
- [ec2-describe-instance-attribute](#) (p. 308)
- [ec2-describe-instance-status](#) (p. 313)
- [ec2-describe-instances](#) (p. 320)
- [ec2-describe-internet-gateways](#) (p. 333)
- [ec2-describe-keypairs](#) (p. 338)
- [ec2-describe-network-acls](#) (p. 342)
- [ec2-describe-network-interface-attribute](#) (p. 348)
- [ec2-describe-network-interfaces](#) (p. 352)
- [ec2-describe-placement-groups](#) (p. 359)
- [ec2-describe-regions](#) (p. 363)
- [ec2-describe-reserved-instances](#) (p. 367)
- [ec2-describe-reserved-instances-listings](#) (p. 373)
- [ec2-describe-reserved-instances-offerings](#) (p. 378)
- [ec2-describe-route-tables](#) (p. 386)
- [ec2-describe-snapshot-attribute](#) (p. 391)
- [ec2-describe-snapshots](#) (p. 395)
- [ec2-describe-spot-datafeed-subscription](#) (p. 401)
- [ec2-describe-spot-instance-requests](#) (p. 404)
- [ec2-describe-spot-price-history](#) (p. 412)
- [ec2-describe-subnets](#) (p. 418)
- [ec2-describe-tags](#) (p. 423)
- [ec2-describe-volume-attribute](#) (p. 428)
- [ec2-describe-volume-status](#) (p. 432)
- [ec2-describe-volumes](#) (p. 438)
- [ec2-describe-vpc-attribute](#) (p. 444)
- [ec2-describe-vpcs](#) (p. 448)
- [ec2-describe-vpn-connections](#) (p. 453)
- [ec2-describe-vpn-gateways](#) (p. 459)
- [ec2-detach-internet-gateway](#) (p. 464)
- [ec2-detach-network-interface](#) (p. 467)
- [ec2-detach-volume](#) (p. 471)
- [ec2-detach-vpn-gateway](#) (p. 475)
- [ec2-disable-vgw-route-propagation](#) (p. 479)
- [ec2-disassociate-address](#) (p. 482)
- [ec2-disassociate-route-table](#) (p. 486)
- [ec2-enable-volume-io](#) (p. 490)
- [ec2-enable-vgw-route-propagation](#) (p. 493)
- [ec2-fingerprint-key](#) (p. 496)
- [ec2-get-console-output](#) (p. 499)
- [ec2-get-password](#) (p. 503)
- [ec2-import-instance](#) (p. 507)
- [ec2-import-keypair](#) (p. 514)
- [ec2-import-volume](#) (p. 518)
- [ec2-migrate-image](#) (p. 524)

- [ec2-modify-image-attribute](#) (p. 530)
- [ec2-modify-instance-attribute](#) (p. 535)
- [ec2-modify-network-interface-attribute](#) (p. 541)
- [ec2-modify-snapshot-attribute](#) (p. 545)
- [ec2-modify-volume-attribute](#) (p. 549)
- [ec2-modify-vpc-attribute](#) (p. 553)
- [ec2-monitor-instances](#) (p. 556)
- [ec2-purchase-reserved-instances-offering](#) (p. 559)
- [ec2-reboot-instances](#) (p. 563)
- [ec2-register](#) (p. 566)
- [ec2-release-address](#) (p. 572)
- [ec2-replace-network-acl-association](#) (p. 576)
- [ec2-replace-network-acl-entry](#) (p. 580)
- [ec2-replace-route](#) (p. 584)
- [ec2-replace-route-table-association](#) (p. 588)
- [ec2-report-instance-status](#) (p. 592)
- [ec2-request-spot-instances](#) (p. 597)
- [ec2-reset-image-attribute](#) (p. 608)
- [ec2-reset-instance-attribute](#) (p. 611)
- [ec2-reset-network-interface-attribute](#) (p. 615)
- [ec2-reset-snapshot-attribute](#) (p. 618)
- [ec2-resume-import](#) (p. 622)
- [ec2-revoke](#) (p. 627)
- [ec2-run-instances](#) (p. 633)
- [ec2-start-instances](#) (p. 646)
- [ec2-stop-instances](#) (p. 650)
- [ec2-terminate-instances](#) (p. 654)
- [ec2-unassign-private-ip-addresses](#) (p. 657)
- [ec2-unmonitor-instances](#) (p. 660)
- [ec2-upload-disk-image](#) (p. 663)
- [ec2-version](#) (p. 667)
- [Common Options for CLI Tools](#) (p. 669)

ec2-allocate-address

Description

Acquires an Elastic IP address for use with your AWS account.

An Elastic IP address is for use either in the EC2-Classic platform or in a VPC. For more information, see [Elastic IP Addresses](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2allocaddr**.

Syntax

```
ec2-allocate-address [-d domain]
```

Options

Name	Description
-d, --domain <i>domain</i>	Set to <code>vpc</code> to allocate the address for use with instances in a VPC. Type: String Default: The address is for use in EC2-Classic. Valid values: <code>vpc</code> Required: Conditional Condition: Required when allocating the address for use in a VPC. Example: <code>-d vpc</code>

Common Options

Option	Description
--region <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
-U, --url <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The ADDRESS identifier
- The Elastic IP address for use with your account
- Specifies whether this Elastic IP address is for use with instances in EC2-Classic (`standard`) or instances in a VPC.
- [EC2-VPC] The allocation ID (an ID that AWS assigns to represent the allocation of an address for use in a VPC)

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example returns an Elastic IP address for use in EC2-Classic.

```
PROMPT> ec2-allocate-address  
ADDRESS 192.0.2.1      standard
```

Example Request

This example returns an Elastic IP address for use in a VPC.

```
PROMPT> ec2-allocate-address -d vpc  
ADDRESS 198.51.100.1   vpc      eipalloc-5723d13e
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [AllocateAddress](#)

Related Commands

- [ec2-associate-address](#) (p. 20)
- [ec2-describe-addresses](#) (p. 256)
- [ec2-disassociate-address](#) (p. 482)
- [ec2-release-address](#) (p. 572)

ec2-assign-private-ip-addresses

Description

Assigns one or more secondary private IP addresses to the specified network interface. You can specify one or more specific secondary IP addresses, or you can specify the number of secondary IP addresses to be automatically assigned within the subnet's CIDR block range. The number of secondary IP addresses that you can assign to an instance varies by instance type. For information about instance types, see [Available Instance Types](#) in the *Amazon Elastic Compute Cloud User Guide*. For more information about Elastic IP addresses, see [Elastic IP Addresses](#) in the *Amazon Elastic Compute Cloud User Guide*.

This command is only available in EC2-VPC.

The short version of this command is **ec2apip**.

Syntax

```
ec2-assign-private-ip-addresses --network-interface interface_id
{[--secondary-private-ip-address-count count] | [--secondary-private-ip-address
ip_address]}
```

Options

Name	Description
<code>-n, --network-interface <i>interface_id</i></code>	The ID of the network interface. Type: String Default: None Required: Yes Example: <code>-n eni-bc7299d4</code>
<code>--secondary-private-ip-address <i>ip_address</i></code>	Assigns the specified IP address as a secondary private IP address to the network interface. This option can be used multiple times to assign multiple secondary IP addresses. You can do one of the following: <ul style="list-style-type: none">• Use the <code>--secondary-private-ip-address</code> option without a value, and AWS will automatically assign a secondary private IP address within the subnet range.• Use the <code>--secondary-private-ip-address</code> option, and provide a specific IP address that you want to assign. You cannot specify this parameter when also specifying <code>--secondary-private-ip-address-count</code> Type: String Default: None Required: Conditional Example: <code>--secondary-private-ip-address 10.0.2.18</code> <code>--secondary-private-ip-address 10.0.2.28</code>

Name	Description
<code>--secondary-private-ip-address-count</code> <i>count</i>	The number of secondary IP addresses to assign to the network interface. You cannot specify this parameter when also specifying <code>--secondary-private-ip-address</code> . Type: Integer Default: None Required: Conditional Example: <code>--secondary-private-ip-address-count 2</code>
<code>--allow-reassignment</code>	Specifies whether to allow an IP address that is already assigned to another network interface to be reassigned to the specified network interface. Type: Boolean Default: <code>false</code> Required: No

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key</code> <i>AWS_ACCESS_KEY</i>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key</code> <i>AWS_SECRET_KEY</i>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-T, --security-token</code> <code>TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <code>TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <code>TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <code>EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <code>EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

The command returns true if the operation succeeds or an error if the operation does not succeed.

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example assigns two secondary private IP addresses (10.0.0.118 and 10.0.0.119) to the network interface `eni-c08a35a9`.

```
PROMPT> ec2-assign-private-ip-addresses --network-interface eni-c08a35a9
--secondary-private-ip-address 10.0.0.118 --secondary-private-ip-address
10.0.0.119
RETURN true
```

Example Request

This example assigns two secondary private IP addresses to the network interface `eni-c08a35a9`. The IP addresses are automatically assigned from the available IP addresses within the subnet's CIDR block range.

```
PROMPT> ec2-assign-private-ip-addresses --network-interface eni-c08a35a9
--secondary-private-ip-address-count 2
RETURN true
```

Example Request

This example assigns a secondary private IP address of 10.0.0.82 to the network interface `eni-73e05a1`.

```
PROMPT> ec2-assign-private-ip-addresses --network-interface eni-73e05a1
--secondary-private-ip-address 10.0.0.82
RETURN true
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [AssignPrivateIpAddresses](#)

Related Commands

- [ec2-unassign-private-ip-addresses](#) (p. 657)

ec2-associate-address

Description

Associates an Elastic IP address with an instance or a network interface. For more information about Elastic IP addresses, see [Elastic IP Addresses](#) in the *Amazon Elastic Compute Cloud User Guide*.

[EC2-Classic, default VPC] If the Elastic IP address is already associated with a different instance, it is disassociated from that instance and associated with the specified instance.

[EC2-VPC] If you do not specify a private IP address, the Elastic IP address is associated with the primary IP address. If the Elastic IP address is already associated with a different instance or a network interface, you get an error unless you specify the `--allow-reassociation` option.

This is an idempotent operation. If you enter it more than once, Amazon EC2 does not return an error.

The short version of this command is `ec2assocaddr`.

Syntax

```
ec2-associate-address [-i instance_id | -n interface_id] [ip_address | -a allocation_id] [--private-ip-address private_ip_address] [--allow-reassociation]
```

Options

Name	Description
<code>-i, --instance <i>instance_id</i></code>	The ID of the instance. Type: String Default: None Required: Conditional Condition: Required for EC2-Classic. For EC2-VPC, you can specify either an instance ID or a network interface ID, but not both. Example: <code>-i i-43a4412a</code>
<code><i>ip_address</i></code>	The Elastic IP address. Type: String Default: None Required: Conditional Condition: Required for EC2-Classic. Example: <code>192.0.2.1</code>
<code>-a, --allocation-id <i>allocation_id</i></code>	The allocation ID. Type: String Default: None Required: Conditional Condition: Required for EC2-VPC. Example: <code>-a eipalloc-5723d13e</code>

Name	Description
<code>-n, --network-interface interface_id</code>	[EC2-VPC] The network interface. Type: String Default: None Required: Conditional Condition: Specify either an instance ID or a network interface ID, but not both. Example: <code>-n eni-bc7299d4</code>
<code>-p, --private-ip-address private_ip_address</code>	[EC2-VPC] The primary or secondary private IP address to associate with the Elastic IP address. If no private IP address is specified, the Elastic IP address is associated with the primary private IP address. Type: String Default: None Required: No Example: <code>-p 10.0.0.45</code>
<code>--allow-reassociation</code>	[EC2-VPC] Allows an Elastic IP address that is already associated with an instance or a network interface to be re-associated with the specified instance or network interface. Otherwise, the operation fails. Type: Boolean Default: The operation fails if the address is already associated. Required: No Example: <code>--allow-reassociation</code>

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key</code> <code>AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key</code> <code>AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> <code>TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <code>TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <code>TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The ADDRESS identifier
- The Elastic IP address
- The instance or network interface to which the Elastic IP address is associated
- [EC2-VPC] The allocation ID
- [EC2-VPC] If specified, the private IP address associated with the Elastic IP address

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example associates an Elastic IP address with an instance in EC2-Classic.

```
PROMPT> ec2-associate-address 203.0.113.0 -i i-43a4412a
ADDRESS 203.0.113.0 i-43a4412a
```

Example Request

This example associates an Elastic IP address with an instance in a VPC.

```
PROMPT> ec2-associate-address -a eipalloc-5723d13e -i i-4fd2431a
ADDRESS i-43a4412a eipalloc-5723d13e eipassoc-fc5ca095
```

Example Request

This example associates an Elastic IP address with a network interface.

```
PROMPT> ec2-associate-address -a eipalloc-4a4c6c23 -n eni-1001fa78
ADDRESS i-1ae1ae78 eipalloc-4a4c6c23 eipassoc-1841907a
```

Example Request

This example associates an Elastic IP address with a private IP address for the specified instance in a VPC. The `allow-reassociation` option allows the Elastic IP address to be associated with the specified instance even if it's already associated with a different instance or a network interface.

```
PROMPT> ec2-associate-address -a eipalloc-bf66dcd6 -i i-ba6a0dee -p 10.0.0.85
--allow-reassociation

ADDRESS          i-ba6a0dee          eipalloc-bf66dcd6          eipassoc-9c66dcf5
10.0.0.85
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [AssociateAddress](#)

Related Commands

- [ec2-allocate-address](#) (p. 12)
- [ec2-describe-addresses](#) (p. 256)
- [ec2-disassociate-address](#) (p. 482)
- [ec2-release-address](#) (p. 572)

ec2-associate-dhcp-options

Description

Associates a set of DHCP options (that you've previously created) with the specified VPC, or associates no DHCP options with the VPC.

After you associate the options with the VPC, any existing instances and all new instances that you launch in that VPC use the options. You don't need to restart or relaunch the instances. They automatically pick up the changes within a few hours, depending on how frequently the instance renews its DHCP lease. You can explicitly renew the lease using the operating system on the instance.

For more information, see [DHCP Options Sets](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is `ec2assocdopt`.

Syntax

```
ec2-associate-dhcp-options { dhcp_options_id | default } -c vpc_id
```

Options

Name	Description
<i>dhcp_options_id</i>	The ID of the DHCP options set, or <code>default</code> to associate no DHCP options set with the VPC. Type: String Default: None Required: Yes Example: <code>dopt-7a8b9c2d</code>
<code>-c vpc_id</code>	The ID of the VPC. Type: String Default: None Required: Yes Example: <code>-c vpc-1a2b3c4d</code>

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The DHCPOPTIONS identifier
- The ID of the DHCP options (or `default` if no DHCP options are associated with the VPC)
- The ID of the VPC

Amazon EC2 command line tools display errors on `stderr`.

Examples

Example Request

This example associates the DHCP options with ID `dopt-7a8b9c2d` with the VPC with ID `vpc-1a2b3c4d`.

```
PROMPT> ec2-associate-dhcp-options dopt-7a8b9c2d -c vpc-1a2b3c4d
DHCOPTIONS dopt-7a8b9c2d vpc-1a2b3c4d
```

Example Request

This example changes the VPC with ID `vpc-1a2b3c4d` to have no associated DHCP options set.

```
PROMPT> ec2-associate-dhcp-options default -c vpc-1a2b3c4d
DHCOPTIONS default vpc-1a2b3c4d
```


Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [AssociateDhcpOptions](#)

Related Commands

- [ec2-create-dhcp-options](#) (p. 93)
- [ec2-delete-dhcp-options](#) (p. 186)
- [ec2-describe-dhcp-options](#) (p. 281)

ec2-associate-route-table

Description

Associates a subnet with a route table. The subnet and route table must be in the same VPC. This association causes traffic originating from the subnet to be routed according to the routes in the route table. The action returns an association ID, which you need to disassociate the route table from the subnet later. A route table can be associated with multiple subnets.

For more information about route tables, see [Route Tables](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2assocrtb**.

Syntax

ec2-associate-route-table *route_table_id* **-s** *subnet_id*

Options

Name	Description
<i>route_table_id</i>	The ID of the route table. Type: String Default: None Required: Yes Example: rtb-6aa34603
-s <i>subnet_id</i>	The ID of the subnet. Type: String Default: None Required: Yes Example: -s subnet-92a045fb

Common Options

Option	Description
--region <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
-U, --url <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The ASSOCIATION identifier
- The route table association ID (needed to disassociate the route table)
- The route table ID

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example associates the route-table (with ID `rtb-6aa34603`) with the subnet with ID `subnet-92a045fb`.

```
PROMPT> ec2-associate-route-table rtb-6aa34603 -s subnet-92a045fb  
ASSOCIATION  rtbassoc-61a34608  rtb-6aa34603  subnet-92a045fb
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [AssociateRouteTable](#)

Related Commands

- [ec2-create-route-table](#) (p. 143)
- [ec2-delete-route-table](#) (p. 218)
- [ec2-describe-route-tables](#) (p. 386)

- [ec2-disassociate-route-table](#) (p. 486)
- [ec2-replace-route-table-association](#) (p. 588)

ec2-attach-internet-gateway

Description

Attaches an Internet gateway to a VPC, enabling connectivity between the Internet and the VPC. For more information about your VPC and Internet gateway, see the [Amazon Virtual Private Cloud User Guide](#).

Note

For VPCs that existed before the 2011-01-01 API version: Before you can attach an Internet gateway, you must delete the legacy security group. For more information, see "Deleting the Legacy Security Group" in the [Security Groups](#) section of the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2attigw**.

Syntax

`ec2-attach-internet-gateway internet_gateway_id -c vpc_id`

Options

Name	Description
<i>internet_gateway_id</i>	The ID of the Internet gateway to attach. Type: String Default: None Required: Yes Example: igw-c3a643aa
<code>-c, --vpc <i>vpc_id</i></code>	The ID of the VPC. Type: String Default: None Required: Yes Example: -c vpc-d9a045b0

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the EC2_PRIVATE_KEY environment variable. Example: -K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the EC2_CERT environment variable. Example: -C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem

Output

This command returns a table that contains the following information:

- The ATTACHMENT identifier
- The ID of the VPC
- The attachment state (attaching, attached, detached, detaching, error)

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example attaches the Internet gateway with ID igw-eaad4883 to the VPC with ID vpc-11ad4878.

```
PROMPT> ec2-attach-internet-gateway igw-eaad4883 -c vpc-11ad4878
ATTACHMENT      vpc-11ad4878      attaching
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [AttachInternetGateway](#)

Related Commands

- [ec2-create-internet-gateway](#) (p. 111)
- [ec2-delete-internet-gateway](#) (p. 196)
- [ec2-describe-internet-gateways](#) (p. 333)
- [ec2-detach-internet-gateway](#) (p. 464)

ec2-attach-network-interface

Description

Attaches a network interface to an instance.

The short version of this command is **ec2attnic**.

Syntax

```
ec2-attach-network-interface interface_id -i, --instance instance_id -d,  
--device-index device_index
```

Options

Name	Description
<i>interface_id</i>	The ID of the network interface to attach. Type: String Default: None Required: Yes Example: eni-b35da6da
-i, --instance <i>instance_id</i>	The ID of the instance. Type: String Default: None Required: Yes Example: -i i-640a3c17
-d, --device-index <i>device_index</i>	The index of the device for the network interface attachment on the instance. Type: String Default: None Required: Yes Example: -d 1

Common Options

Option	Description
--region <i>REGION</i>	Overrides the region specified by the EC2_URL environment variable and the URL specified by the -U option. Default: The value of the EC2_URL environment variable, or us-east-1 if EC2_URL isn't set. Example: --region eu-west-1

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the EC2_PRIVATE_KEY environment variable. Example: -K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the EC2_CERT environment variable. Example: -C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem

Output

This command returns the ID of the network interface that was attached.

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example attaches the specified network interface to the specified instance.

```
PROMPT> ec2-attach-network-interface eni-b35da6da -i i-640a3c17 -d 1
eni-attach-dd3fdab4
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [AttachNetworkInterface](#)

Related Commands

- [ec2-create-network-interface](#) (p. 126)
- [ec2-delete-network-interface](#) (p. 209)
- [ec2-describe-network-interface-attribute](#) (p. 348)

- [ec2-describe-network-interfaces](#) (p. 352)
- [ec2-detach-network-interface](#) (p. 467)
- [ec2-modify-network-interface-attribute](#) (p. 541)
- [ec2-reset-network-interface-attribute](#) (p. 615)

ec2-attach-volume

Description

Attaches an Amazon EBS volume to a running or stopped instance and exposes it to the instance with the specified device name.

For a list of supported device names, see [Attaching the Volume to an Instance](#). Any device names that aren't reserved for instance store volumes can be used for Amazon EBS volumes. For more information, see [Amazon EC2 Instance Store](#) in the *Amazon Elastic Compute Cloud User Guide*.

Note

If a volume has an AWS Marketplace product code:

- The volume can only be attached to the root device of a stopped instance.
- You must be subscribed to the AWS Marketplace code that is on the volume.
- The configuration (instance type, operating system) of the instance must support that specific AWS Marketplace code. For example, you cannot take a volume from a Windows instance and attach it to a Linux instance.
- AWS Marketplace product codes are copied from the volume to the instance.

For an overview of the AWS Marketplace, see <https://aws.amazon.com/marketplace/help/200900000>. For details on how to use the AWS Marketplace, see [AWS Marketplace](#).

The short version of this command is **ec2attvol**.

Syntax

```
ec2-attach-volume volume_id --instance instance_id --device device
```

Options

Name	Description
<i>volume_id</i>	The ID of the Amazon EBS volume. The volume and instance must be within the same Availability Zone and the instance. Type: String Default: None Required: Yes Example: vol-4d826724
<i>-i, --instance instance_id</i>	The ID of the instance to attach the volume to. The volume and instance must be within the same Availability Zone. Type: String Default: None Required: Yes Example: -i i-6058a509

Name	Description
<code>-d, --device <i>device</i></code>	The device name to expose to the instance. Type: String Default: None Required: Yes Example: <code>-d /dev/sdf</code> (for Linux/UNIX) or <code>-d xvdf</code> (for Windows)

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url <i>URL</i></code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key <i>AWS_ACCESS_KEY</i></code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key <i>AWS_SECRET_KEY</i></code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token <i>TOKEN</i></code> <code><i>AWS_DELEGATION_TOKEN</i></code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout <i>TIMEOUT</i></code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout <i>TIMEOUT</i></code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>

Option	Description
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The ATTACHMENT identifier
- The ID of the volume
- The ID of the instance
- The device name
- The attachment state of the volume
- The time stamp of the last operation on the volume
- Whether or not the volume is set to delete on termination (`true` or `false`)

Amazon EC2 command line tools display errors using stderr.

Examples

Example Request

This example attaches volume `vol-1a2b3c4d` to instance `i-1a2b3c4d` and exposes it as `/dev/sdh`. For information on standard storage locations, see the [Amazon Elastic Compute Cloud User Guide](#).

```
PROMPT> ec2-attach-volume vol-1a2b3c4d -i i-1a2b3c4d -d /dev/sdh  
ATTACHMENT vol-1a2b3c4d i-1a2b3c4d /dev/sdh attaching YYYY-MM-DDTHH:MM:SS+0000
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [AttachVolume](#)

Related Commands

- [ec2-create-volume](#) (p. 162)
- [ec2-delete-volume](#) (p. 234)
- [ec2-describe-volumes](#) (p. 438)
- [ec2-detach-volume](#) (p. 471)

ec2-attach-vpn-gateway

Description

Attaches a virtual private gateway to a VPC. For more information, see [Adding a Hardware Virtual Private Gateway to Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2attvgw**.

Syntax

```
ec2-attach-vpn-gateway vpn_gateway_id -c vpc_id
```

Options

Name	Description
<i>vpn_gateway_id</i>	The ID of the virtual private gateway to attach to the VPC. Type: String Default: None Required: Yes Example: vgw-8db04f81
-c, --vpc <i>vpc_id</i>	The ID of the VPC. Type: String Default: None Required: Yes Example: -c vpc-1a2b3c4d

Common Options

Option	Description
--region <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: --region eu-west-1
-U, --url <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: -U https://ec2.amazonaws.com

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The VGWATTACHMENT identifier
- The ID of the attached VPC
- The state of the attachment (attaching, attached, detaching, detached)

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example attaches the virtual private gateway with ID `vgw-8db04f81` to the VPC with ID `vpc-1a2b3c4d`.

```
PROMPT> ec2-attach-vpn-gateway vgw-8db04f81 -c vpc-1a2b3c4d  
VGWATTACHMENT vpc-1a2b3c4d attaching
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [AttachVpnGateway](#)

Related Commands

- [ec2-create-vpn-gateway](#) (p. 176)
- [ec2-describe-vpn-gateways](#) (p. 459)
- [ec2-detach-vpn-gateway](#) (p. 475)

- [ec2-create-vpc](#) (p. 167)
- [ec2-create-vpn-connection](#) (p. 171)

ec2-authorize

Description

Adds a rule to a security group.

Important

EC2-Classic: You can have up to 100 rules per group.

EC2-VPC: You can have up to 50 rules per group (covering both ingress and egress).

Rule changes are propagated to affected instances as quickly as possible. However, a small delay might occur.

A security group is for use with instances either in the EC2-Classic platform or in a specific VPC. EC2-Classic doesn't support rules for egress traffic. For more information, see [Amazon EC2 Security Groups](#) in the *Amazon Elastic Compute Cloud User Guide* and [Security Groups for Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

EC2-Classic: This command either gives one or more CIDR IP address ranges permission to access a security group for your account, or it gives one or more security groups (called the *source groups*) permission to access a security group for your account. A source group can be for your own AWS account, or another.

EC2-VPC: For ingress rules, this command either gives one or more CIDR IP address ranges permission to access a security group for your VPC, or it gives one or more other security groups (called the *source groups*) permission to access a security group for your VPC. The groups must all be in the same VPC. For egress rules, this command permits instances in the VPC to send traffic to either one or more destination CIDR IP address ranges, or to one or more destination security groups for the same VPC.

The short version of this command is **ec2auth**.

Syntax

```
ec2-authorize group [--egress] [-P protocol] (-p port_range | -t icmp_type_code)
[-u source_or_dest_group_owner ...] [-o source_or_dest_group ...] [-s
source_or_dest_cidr ...]
```

Options

Name	Description
<i>group</i>	<p>[EC2-Classic, default VPC] The name or ID of the security group.</p> <p>[nondefault VPC] The ID of the security group.</p> <p>The group must belong to your AWS account. Type: String Default: None Required: Yes Example: webserv</p>

Name	Description
<code>--egress</code>	<p>[EC2-VPC] Designates the rule as an egress rule (controls traffic leaving the VPC).</p> <p>Default: If this option is not specified, the rule applies to ingress traffic for the specified security group.</p>
<code>-P, --protocol <i>protocol</i></code>	<p>The IP protocol name or number (see Protocol Numbers). Security groups for EC2-Classic can have rules only for TCP, UDP, and ICMP, whereas security groups for EC2-VPC can have rules assigned to any protocol number.</p> <p>When you use ec2-describe-group (p. 289), the protocol value returned is the number. Exception: For TCP, UDP, and ICMP, the value returned is the name (<code>tcp</code>, <code>udp</code>, or <code>icmp</code>).</p> <p>Type: String</p> <p>Valid values for EC2-Classic: <code>tcp</code> <code>udp</code> <code>icmp</code> or the corresponding protocol number (6 17 1).</p> <p>Default for EC2-Classic: Defaults to TCP if source CIDR is specified (or implied by default), or all three protocols (TCP, UDP, and ICMP) if source group is specified (to ensure backwards compatibility).</p> <p>Valid values for EC2-VPC: <code>tcp</code> <code>udp</code> <code>icmp</code> or any protocol number (see Protocol Numbers). Use <code>all</code> to specify all protocols.</p> <p>Required: Conditional</p> <p>Condition: Required for EC2-VPC.</p> <p>Example: <code>-P udp</code></p>
<code>-p <i>port_range</i></code>	<p>For TCP or UDP: The range of ports to allow.</p> <p>Type: String</p> <p>Default: None</p> <p>Valid values: A single integer or a range (min-max). You can specify -1 to mean all ports (for example, port range 0-65535).</p> <p>Required: Conditional</p> <p>Condition: Required if specifying <code>tcp</code> or <code>udp</code> (or the equivalent number) for the protocol.</p> <p>Example: <code>-p 80-84</code></p>
<code>-t <i>icmp_type_code</i></code>	<p>For ICMP: The ICMP type and code. Use the format <code>type:code</code>, where both are integers. You can use -1 for the type or code to mean all types or all codes.</p> <p>Type: String</p> <p>Default: None</p> <p>Required: Conditional</p> <p>Condition: Required if specifying <code>icmp</code> (or the equivalent number) for the protocol.</p> <p>Example: <code>-t -1:-1</code></p>

Name	Description
<code>-u, source_or_dest_group_owner</code>	The ID of the AWS account that owns the source security group. If the group is in your own account, set this to your own AWS account ID. Cannot be used when specifying a CIDR IP address. Type: String Default: None Required: Conditional Condition: For EC2-Classical: Required when adding a rule that gives access to one or more source security groups. Example: <code>-u 111122223333</code>
<code>-o source_or_dest_group</code>	The source security group (for ingress rules), or destination security group (for egress rules). You can't use this option when specifying a CIDR IP address with the <code>-s</code> option. [nondefault VPC] You must specify the ID of the group (for example, <code>sg-1a2b3c4d</code>) instead of its name. Type: String Default: None Required: Conditional Condition: Required if giving access to one or more source or destination security groups. Example: <code>-o headoffice</code>
<code>-s, --cidr source_or_dest_cidr</code>	The CIDR range. Cannot be used when specifying a source or destination security group with the <code>-o</code> option. Type: String Default: <code>0.0.0.0/0</code> Constraints: Valid CIDR IP address range. Required: Conditional Condition: Required if giving access to one or more IP address ranges. Example: <code>-s 205.192.8.45/24</code>

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key</code> <code>AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key</code> <code>AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> <code>TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <code>TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <code>TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

A line containing the group information. Some of these fields may be blank.

- The GROUP identifier
- The ID of the security group
- The AWS account ID of the owner of the security group
- The name of the security group
- A description of the security group
- [VPC only] The ID of the VPC the group belongs to

One of each of the following lines for each permission defined by the group:

- The PERMISSION identifier
- The AWS account ID of the owner of the group
- The name of the group granting permission
- The type of rule. Currently, only `ALLOWS` rules are supported
- The protocol to allow (for example, `tcp`, `udp`, etc)
- The start of port range
- The end of port range
- `FROM` for an ingress rule or `TO` for an egress rule
- The source type (for ingress rules) or destination type (for egress rules)
- The source (for ingress rules) or destination (for egress rules)
- [USER only] The name of the source or destination entity
- [USER only] The group ID
- Whether the rule is ingress rule or an egress rule

Amazon EC2 command line tools display errors on `stderr`.

Examples

Example Request

EC2 security groups: This example grants TCP port 80 access from the 192.0.2.0/24 address range to the EC2 security group called `websrv`.

```
PROMPT> ec2-authorize websrv -P tcp -p 80 -s 192.0.2.0/24  
GROUP websrv  
PERMISSION websrv ALLOWS tcp 80 80 FROM CIDR 192.0.2.0/24 ingress
```

Example Request

EC2 security groups: This example grants TCP port 80 access from the EC2 source group called `OtherAccountGroup` (in AWS account 111122223333) to your EC2 security group called `websrv`.

```
PROMPT> ec2-authorize websrv -P tcp -p 80 -u 111122223333 -o OtherAccountGroup  
GROUP websrv  
PERMISSION websrv ALLOWS tcp 80 80 FROM USER 111122223333 NAME OtherAccountGroup  
ingress
```

Example Request

[EC2-VPC] This example grants TCP port 80 access from the 192.0.2.0/24 address range to the security group with ID `sg-1a2b3c4d`.

```
PROMPT> ec2-authorize sg-1a2b3c4d -P tcp -p 80 -s 192.0.2.0/24  
GROUP sg-1a2b3c4d  
PERMISSION ALLOWS tcp 80 80 FROM CIDR 192.0.2.0/24 ingress
```

Example Request

[EC2-VPC] This example grants egress access from the group `sg-1a2b3c4d` to the destination group `sg-2a2b3c4d` on TCP destination port 1433.

```
PROMPT> ec2-authorize --egress sg-1a2b3c4d -P tcp -p 1433 -o sg-2a2b3c4d  
GROUP sg-1a2b3c4d  
PERMISSION ALLOWS tcp 1433 1433 TO USER ID sg-2a2b3c4d egress
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Actions

- [AuthorizeSecurityGroupEgress](#)
- [AuthorizeSecurityGroupIngress](#)

Related Commands

- [ec2-create-group](#) (p. 97)
- [ec2-delete-group](#) (p. 192)
- [ec2-describe-group](#) (p. 289)
- [ec2-revoke](#) (p. 627)

ec2-bundle-instance

Description

Bundles an Amazon instance store-backed Windows instance.

During bundling, only the root device volume (C:) is bundled. Data on other instance store volumes is not preserved.

Note

This procedure is not applicable for Linux/UNIX instances or Windows instances that are backed by Amazon EBS.

The short version of this command is **ec2bundle**.

Syntax

```
ec2-bundle-instance instance_id -b bucket -p prefix -o access_key_id {-c policy
| -s policy_signature | -w owner_secret_access_key} [-x hours] [--location
location] [-B]
```

Options

Name	Description
<i>instance_id</i>	The ID of the instance to bundle. Type: String Default: None Required: Yes Example: i-5e73d509
-b, --bucket <i>bucket</i>	The bucket in which to store the AMI. You can specify a bucket that you already own or a new bucket that Amazon EC2 creates on your behalf. If you specify a bucket that belongs to someone else, Amazon EC2 returns an error. Type: String Default: None Required: Yes Example: -b myawsbucket
-p, --prefix <i>prefix</i>	The prefix for the image component names being stored in Amazon S3. Type: String Default: None Required: Yes Example: -p winami
-o, --owner-akid <i>access_key_id</i>	The Access Key ID of the owner of the Amazon S3 bucket. Type: String Default: None Required: Yes Example: -o AKIAIOSFODNN7EXAMPLE

Name	Description
<p><code>-c, --policy <i>policy</i></code></p>	<p>A Base64-encoded Amazon S3 upload policy that gives Amazon EC2 permission to upload items into Amazon S3 on the user's behalf. If you provide this parameter, you must also provide either a policy signature, or your Secret Access Key, so we can create a policy signature for you (the Secret Access Key is not passed to EC2). If you do not provide this parameter, the <code>--owner-sak</code> is required, and we generate an upload policy and policy signature for you automatically. For more information about upload policies and how to sign them, see the sections about policy construction and signatures in the Amazon Simple Storage Service Developer Guide.</p> <p>Type: String Default: None Required: Conditional Example: <code>-c upload-policy</code></p>
<p><code>-s, --policy-signature <i>policy_signature</i></code></p>	<p>The Base-64 encoded signature for the S3 upload policy. If you provide <code>--policy</code> but not <code>--policy-signature</code>, then <code>--owner-sak</code> is required, and we use it to automatically sign the policy.</p> <p>Type: String Default: None Required: Conditional Example: <code>-s upload-policy</code></p>
<p><code>-w, --owner-sak <i>owner_secret_access_key</i></code></p>	<p>The AWS Secret Access Key for the owner of the Amazon S3 bucket specified in the <code>-b</code> parameter. This parameter is required in either of these cases:</p> <ul style="list-style-type: none"> • If you don't provide the <code>--policy</code> parameter • If you provide the <code>--policy</code> parameter, but don't provide the <code>--policy-signature</code> parameter <p>The command line tools client uses the Secret Access Key to sign a policy for you, but does not send the Secret Access Key to EC2.</p> <p>Type: String Default: None Required: Conditional Example: <code>-w wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p>
<p><code>-x, --expires <i>hours</i></code></p>	<p>The validity period, in hours, for a generated upload policy.</p> <p>Type: String Default: 24 Required: No Example: <code>-x 8</code></p>

Name	Description
<code>--location bucket_location</code>	The location of the destination Amazon S3 bucket. Type: String Default: None Required: No Example: <code>--location my-bucket-location</code>
<code>-B, --no-bucket-setup</code>	Indicates that no Amazon S3 bucket should be created if one doesn't already exist, and that no attempt should be made to fix incorrect permissions. Type: Boolean Default: <code>false</code> Required: No Example: <code>-B</code>

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-T, --security-token</code> <code>TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <code>TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <code>TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <code>EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <code>EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The BUNDLE identifier
- The ID of the bundle
- The ID of the instance
- The bucket name
- The bundle prefix
- The bundle start time
- The bundle update time
- The current state, usually pending

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example bundles an instance.

```
PROMPT> ec2-bundle-instance i-12345678 -b myawsbucket -p winami -o AKIAIOSFOD  
NN7EXAMPLE -w wJalrXUtnFEMI/K7MDENG/bPxrFicYEXAMPLEKEY  
BUNDLE bun-cla540a8 i-12345678 myawsbucket winami 2008-09-15T17:15:20+0000  
pending
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [BundleInstance](#)

Related Commands

- [ec2-cancel-bundle-task](#) (p. 61)
- [ec2-create-image](#) (p. 102)
- [ec2-describe-bundle-tasks](#) (p. 267)

ec2-cancel-bundle-task

Description

Cancels a bundling operation for an instance store-backed Windows instance.

The short version of this command is **ec2cbun**.

Syntax

`ec2-cancel-bundle-task bundle_id`

Options

Name	Description
<i>bundle_id</i>	The ID of the bundle task to cancel. Type: String Default: None Required: Yes Example: bun-cla432a3

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The BUNDLE identifier
- The ID of the bundle
- The ID of the instance
- The bucket name
- The cancel status
- The prefix
- The start time
- The update time
- The status (`cancelling`)

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example cancels the `bun-cla322b9` bundle task.

```
PROMPT> ec2-cancel-bundle-task bun-cla322b9
BUNDLE bun-cla322b9 i-2674d22r myawsbucket winami 2008-09-15T17:15:20+0000 2008-09-15T17:15:20+0000 cancelling
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CancelBundleTask](#)

Related Commands

- [ec2-bundle-instance](#) (p. 56)
- [ec2-describe-bundle-tasks](#) (p. 267)

ec2-cancel-conversion-task

Description

Cancels an active conversion task. The task can be the import of an instance or volume. The command removes all artifacts of the conversion, including a partially uploaded volume or instance. If the conversion is complete or is in the process of transferring the final disk image, the command fails and returns an exception.

For more information, see [Using the Command Line Tools to Import Your Virtual Machine to Amazon EC2](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2cct**.

Syntax

```
ec2-cancel-conversion-task task_id
```

Options

Name	Description
<i>task_id</i>	The conversion task ID of the task to cancel. Type: String Default: None Required: Yes Example: import-i-fh95npoc

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns the status (success or failure) of the deletion.

Amazon EC2 command line tools display errors on stderr.

Example

Example Request

This example deletes the conversion identified by task ID `import-i-fh95npoc`.

```
PROMPT> ec2-cancel-conversion-task import-i-fh95npoc  
CONVERSION-TASK import-i-fh95npoc
```

If the task fails, you receive the following error:

```
Client.DeleteConversionTask Error: Failed to delete conversion task import-i-fh95npoc
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- `CancelConversionTask`

Related Commands

- `ec2-delete-disk-image` (p. 189)
- `ec2-describe-conversion-tasks` (p. 272)

- [ec2-import-instance](#) (p. 507)
- [ec2-import-volume](#) (p. 518)
- [ec2-resume-import](#) (p. 622)

ec2-cancel-export-task

Description

Cancels an active export task. The command removes all artifacts of the export, including any partially created Amazon S3 objects. If the export task is complete or is in the process of transferring the final disk image, the command fails and returns an error.

The short version of this command is **ec2cxt**.

Syntax

`ec2-cancel-export-task` *task_id*

Options

Name	Description
<i>task_id</i>	The ID of the export task to be canceled. This is the ID returned by <code>ec2-create-instance-export-task</code> . Type: String Default: None Required: Yes Example: <code>export-i-fgelt0i7</code>

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key</code> <i>AWS_ACCESS_KEY</i>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key</code> <i>AWS_SECRET_KEY</i>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> TOKEN <i>AWS_DELEGATION_TOKEN</i>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <i>TIMEOUT</i>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns the status (success or failure) of the cancellation.

Amazon EC2 command line tools display errors on stderr.

Example

Example Request

This example deletes the export identified by task ID `export-i-fgelt0i7`.

```
PROMPT> ec2-cancel-export-task export-i-fgelt0i7  
EXPORT-TASK    export-i-fgelt0i7
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CancelExportTask](#)

Related Commands

- [ec2-create-instance-export-task](#) (p. 107)
- [ec2-describe-export-tasks](#) (p. 286)

ec2-cancel-reserved-instances-listing

Description

Cancels the specified Reserved Instance listing in the Reserved Instance Marketplace.

For more information about Reserved Instance Marketplace, see [Reserved Instance Marketplace](#) in the *Amazon Elastic Compute Cloud User Guide*.

Syntax

ec2-cancel-reserved-instances-listing *LISTING*

Options

Name	Description
<i>LISTING</i>	The ID of the Reserved Instance listing to be canceled. Type: String Required: Yes Default: None

Common Options

Option	Description
--region <i>REGION</i>	Overrides the region specified by the EC2_URL environment variable and the URL specified by the -U option. Default: The value of the EC2_URL environment variable, or us-east-1 if EC2_URL isn't set. Example: --region eu-west-1
-U, --url <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the EC2_URL environment variable, or https://ec2.amazonaws.com if EC2_URL isn't set. Example: -U https://ec2.amazonaws.com
-O, --aws-access-key <i>AWS_ACCESS_KEY</i>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the AWS_ACCESS_KEY environment variable. If AWS_ACCESS_KEY isn't set, you must specify this option. Example: -O AKIAIOSFODNN7EXAMPLE Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key</code> <i>AWS_SECRET_KEY</i>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> TOKEN <i>AWS_DELEGATION_TOKEN</i>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <i>TIMEOUT</i>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

The command returns a table that contains the following information:

The listing information

- The LISTING identifier
- Reserved Instance listing ID
- Reserved Instances ID
- Create Date
- Update Date
- Status
- Status Message

One or more rows that contain instance count information

- The INSTANCE-COUNT identifier
- The instance count state
- The instance count

One or more rows that contain price schedule information

- The PRICE-SCHEDULE identifier
- The term
- The price
- Whether or not the schedule is active

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example cancels a Reserved Instance listing in the Reserved Instance Marketplace.

```
PROMPT> ec2-cancel-reserved-instances-listing 095c0e18-c9e6-4692-97e5-653e0example
```

Amazon EC2 returns output similar to the following:

```
PROMPT> ec2-cancel-reserved-instances-listing
Type ReservedInstancesListingId ReservedInstancesId CreateDate UpdateDate Status
  StatusMessage
LISTING 095c0e18-c9e6-4692-97e5-653e0example b847fa93-c736-4eae-bca1-e3147example
  Tue Aug 28 18:21:07 PDT 2012 Tue Aug 28 18:21:07 PDT 2012 cancelled cancelled
INSTANCE-COUNT available 0
INSTANCE-COUNT sold 0
INSTANCE-COUNT cancelled 1
INSTANCE-COUNT pending 0
PRICE-SCHEDULE 5 $1.2 true
PRICE-SCHEDULE 4 $1.2 false
PRICE-SCHEDULE 3 $1.2 false
PRICE-SCHEDULE 2 $1.2 false
PRICE-SCHEDULE 1 $1.2 true
```

Related Operations

- [ec2-describe-reserved-instances-listings](#) (p. 373)
- [ec2-create-reserved-instances-listing](#) (p. 134)
- [ec2-describe-reserved-instances](#) (p. 367)

ec2-cancel-spot-instance-requests

Description

Cancels one or more Spot Instance requests. Spot Instances are instances that Amazon EC2 starts on your behalf when the maximum price that you specify exceeds the current Spot Price. Amazon EC2 periodically sets the Spot Price based on available Spot Instance capacity and current Spot Instance requests. For more information about Spot Instances, see [Spot Instances](#) in the *Amazon Elastic Compute Cloud User Guide*.

Important

Canceling a Spot Instance request does not terminate running Spot Instances associated with the request.

The short version of this command is **ec2csir**.

Syntax

```
ec2-cancel-spot-instance-requests request_id [request_id...]
```

Options

Name	Description
<i>request_id</i>	The Spot Instance request ID. Type: String Default: None Required: Yes Example: sir-8456a32b

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The SPOTINSTANCEREQUEST identifier
- The Spot Instance request ID
- The current state

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example cancels a Spot Instance request.

```
PROMPT> ec2-cancel-spot-instance-requests sir-1a2b3c4d sir-2a2b3c4d  
SPOTINSTANCEREQUEST sir-1a2b3c4d cancelled  
SPOTINSTANCEREQUEST sir-2a2b3c4d cancelled
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CancelSpotInstanceRequests](#)

Related Commands

- [ec2-describe-spot-instance-requests](#) (p. 404)
- [ec2-describe-spot-price-history](#) (p. 412)

- [ec2-request-spot-instances](#) (p. 597)

ec2-confirm-product-instance

Description

Determines whether a product code is associated with an instance. This command can only be run by the owner of the product code. It is useful when a product code owner needs to verify whether an EC2 user's instance is eligible for support.

The short version of this command is **ec2cpi**.

Syntax

`ec2-confirm-product-instance product_code -i instance_id`

Options

Name	Description
<code>product_code</code>	The product code to confirm. This must be an Amazon DevPay product code that you own. Type: String Default: None Required: Yes Example: 774F4FF8
<code>-i instance_id</code>	The instance to confirm. Type: String Default: None Required: Yes Example: -i i-10a64379

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The product code
- The instance ID
- A Boolean value indicating whether the product code is attached to the instance
- The instance owner's account ID (if the product code is attached)

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example determines whether the product code is associated with the instance.

```
PROMPT> ec2-confirm-product-instance 774F4FF8 -i i-10a64379
774F4FF8 i-10a64379 true 111122223333
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ConfirmProductInstance](#)

Related Commands

- [ec2-describe-instances](#) (p. 320)
- [ec2-run-instances](#) (p. 633)

ec2-copy-image

Description

Initiates the copy of an AMI from the specified source region to the region in which the command is executed.

The short version of this command is **ec2cpimg**.

Syntax

At a command prompt, switch to the destination region, and then type the following:

```
ec2-copy-image -r source_region -s source_ami_id [-n ami_name] [-d ami_description] [-c token]
```

Options

Name	Description
-r, --source-region <i>source_region</i>	The name of the AWS region that contains the AMI to be copied. Type: String Default: None Required: Yes Example: us-west-2
-s, --source-ami-id <i>source_ami_id</i>	The ID of the AMI to copy. Type: String Default: None Required: Yes Example: ami-4fa54026
-n, --name <i>ami_name</i>	The name of the new AMI in the destination region. Type: String Default: Same name as the AMI being copied. Required: No Example: My-Standard-AMI
-d, --description <i>ami_description</i>	The description to set on the new AMI in the destination region. Type: String Default: Same description as the AMI being copied. Constraints: Up to 255 characters. Required: No Example: -d "This is the new version of My-Standard-AMI"

Name	Description
<code>-c, --client-token token</code>	Unique, case-sensitive identifier you provide to ensure idempotency of the request. For more information, see How to Ensure Idempotency in the <i>Amazon Elastic Compute Cloud User Guide</i> . Type: String Default: None Constraints: Up to 255 characters Required: No Example: 550e8400-e29b-41d4-a716-446655440000

Tip

You can use the common option `--region` to specify the region against which the command is executed. For AMI Copy, this will be the destination region.

Examples

Example Request

This example copies the AMI `ami-4d3c2b1a` in region `us-west-2`, giving the new AMI the name `My-Standard-AMI`:

```
PROMPT> ec2-copy-image -r us-west-2 -i ami-4d3c2b1a -n "My-Standard-AMI" -d  
"This is a copy of ami-4fa54026 --My-standard-AMI-- from us-west-2" -c 550e8400-  
e29b-41d4-a716-46655440001  
IMAGE ami-1a2b3c4d
```

Example Request

This example copies the AMI `ami-4d3c2b1a` in region `us-east-1` to `ap-northeast-1`, giving the new AMI the name `My-Standard-AMI`:

```
PROMPT> ec2-copy-image -r us-east-1 --region ap-northeast-1 -i ami-4d3c2b1a -n  
"My-Standard-AMI" -d "This is a copy of ami-4fa54026 --My-Standard-AMI-- from  
us-east-1" -c 550e8400-e29b-41d4-a716-46655440000  
IMAGE ami-1a2b3c4d
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CopyImage](#)

Related Commands

- [ec2-describe-images](#) (p. 299)
- [ec2-deregister](#) (p. 249)

ec2-copy-snapshot

Description

Copies a point-in-time snapshot of an Amazon Elastic Block Store (Amazon EBS) volume and stores it in Amazon Simple Storage Service (Amazon S3). You can copy the snapshot within the same region or from one region to another. You can use the snapshot to create new Amazon EBS volumes or Amazon Machine Images (AMI).

The short version of this command is **ec2cpsnap**.

Syntax

```
ec2-copy-snapshot -r source_region -s source_snapshot_id [-d description]
```

Options

Name	Description
<code>-r, --source-region</code> <i>source_region</i>	The name of the AWS region that contains the snapshot to be copied. Type: String Default: None Required: Yes Example: us-west-1
<code>-s, --source-snapshot-id</code> <i>source_snapshot_id</i>	The ID of the Amazon EBS snapshot to copy. Type: String Default: None Required: Yes Example: snap-4d826724
<code>-d, --description</code> <i>description</i>	The description to set on the destination Amazon EBS snapshot. Type: String Default: The source's snapshot description or "[Copied from SOURCE_REGION]" if source snapshot doesn't have a description. Constraints: Up to 255 characters. Required: No Example: -d "Copy of user data from us-west-1"

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.

Option	Description
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The SNAPSHOT identifier
- The ID of the new snapshot

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example copies snapshot `snap-1a2b3c4d`.

```
PROMPT> ec2-copy-snapshot -r us-west-1 -s snap-1a2b3c4d --description "Copy of
user data from us-west-1"
SNAPSHOT snap-2a2b3c4d
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CopySnapshot](#)

Related Commands

- [ec2-create-snapshot](#) (p. 146)
- [ec2-delete-snapshot](#) (p. 221)
- [ec2-describe-snapshots](#) (p. 395)

ec2-create-customer-gateway

Description

Provides information to AWS about your VPN customer gateway device. The customer gateway is the appliance at your end of the VPN connection (compared to the virtual private gateway, which is the device at the AWS side of the VPN connection)

You must provide the Internet-routable IP address of the customer gateway's external interface. The IP address must be static and can't be behind a device performing network address translation (NAT).

You must also provide the device's Border Gateway Protocol (BGP) Autonomous System Number (ASN). You can use an existing ASN assigned to your network. If you don't have an ASN already, you can use a private ASN (in the 64512 - 65534 range).

Note

Amazon EC2 supports all 2-byte ASN numbers in the range of 1 - 65534, with the exception of 7224, which is reserved in US East, and 9059, which is reserved in EU West.

For more information about ASNs, see the [Wikipedia article](#).

For more information about VPN customer gateways, see [Adding a Hardware Virtual Private Gateway to Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2addcgw**.

Syntax

```
ec2-create-customer-gateway -t type -i ip_address -b bgp_asn
```

Options

Name	Description
-t <i>type</i>	The type of VPN connection this customer gateway supports. Type: String Default: None Valid values: ipsec.1 Required: Yes Example: -t ipsec.1
-i <i>ip_address</i>	The Internet-routable IP address for the customer gateway's outside interface. The address must be static. Type: String Default: None Required: Yes Example: -i 12.1.2.3

Name	Description
<code>-b <i>bgp_asn</i></code>	The customer gateway's Border Gateway Protocol (BGP) Autonomous System Number (ASN). Type: Integer Default: None Required: Yes Example: <code>-b 65534</code>

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url <i>URL</i></code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key <i>AWS_ACCESS_KEY</i></code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key <i>AWS_SECRET_KEY</i></code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token <i>TOKEN</i></code> <code><i>AWS_DELEGATION_TOKEN</i></code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout <i>TIMEOUT</i></code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout <i>TIMEOUT</i></code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>

Option	Description
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The CUSTOMERGATEWAY identifier
- The customer gateway ID, which uniquely identifies the customer gateway
- The current state of the customer gateway (pending, available, deleting, deleted)
- The type of VPN connection the customer gateway supports
- The Internet-routable IP address for the customer gateway's outside interface
- The customer gateway's BGP ASN

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example passes information to AWS about the customer gateway with IP address 12.1.2.3 and ASN 65534.

```
PROMPT> ec2-create-customer-gateway -t ipsec.1 -i 12.1.2.3 -b 65534  
CUSTOMERGATEWAY cgw-b4dc3961 pending ipsec.1 12.1.2.3 65534
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateCustomerGateway](#)

Related Commands

- [ec2-delete-customer-gateway](#) (p. 183)
- [ec2-describe-customer-gateways](#) (p. 276)

ec2-create-dhcp-options

Description

Creates a set of DHCP options for your VPC. After creating the new set, you must associate it with the VPC, causing all existing and new instances that you launch in the VPC to use the new set of DHCP options. The following table lists the individual DHCP options you can specify. For more information about the options, see [RFC 2132](#).

DHCP Option Name	Description
domain-name-servers	The IP addresses of up to four domain name servers, or . The default DHCP option set specifies .
domain-name	If you're using in US East (Northern Virginia) Region, specify <code>compute-1.amazonaws.com</code> . If you're using in another region, specify <code>region.compute.amazonaws.com</code> . Otherwise, specify a domain name (for example, <code>MyCompany.com</code>).
ntp-servers	The IP addresses of up to four Network Time Protocol (NTP) servers.
netbios-name-servers	The IP addresses of up to four NetBIOS name servers.
netbios-node-type	The NetBIOS node type (1, 2, 4, or 8). We recommend that you specify 2 (broadcast and multicast are not currently supported). For more information about these node types, see RFC 2132 .

Important

Your VPC automatically starts out with a set of DHCP options that includes only a DNS server that we provide (AmazonProvidedDNS). If you create a new set of options, and if your VPC has an Internet gateway, make sure to set the `domain-name-servers` option either to AmazonProvidedDNS or to a domain name server of your choice.

For more information about DHCP options, see [Using DHCP Options with Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is `ec2adddopt`.

Syntax

```
ec2-create-dhcp-options name=value[,value...] [ name=value[,value...] ... ]
```

Options

Name	Description
<code>name=value,value</code>	<p>The DHCP option (including the option's name and its value). You can specify more than one option in the request, and more than one value per option. If you're using the command line tools on a Windows system, you might need to use quotation marks (for example, "name=value,value").</p> <p>Type: String Default: None Required: Yes Example: "domain-name-servers=10.2.5.1,10.2.5.2"</p>

Common Options

Option	Description
<code>--region REGION</code>	<p>Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option.</p> <p>Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set.</p> <p>Example: <code>--region eu-west-1</code></p>
<code>-U, --url URL</code>	<p>The uniform resource locator (URL) of the Amazon EC2 web service entry point.</p> <p>Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set.</p> <p>Example: <code>-U https://ec2.amazonaws.com</code></p>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>

Option	Description
<code>--connection-timeout</code> <i>TIMEOUT</i>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The DHCPOPTIONS identifier

- The DHCP options ID
- The OPTION identifier
- Each option and its corresponding value in the set of options

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates a new set of DHCP options with a domain name mydomain.com and two DNS servers (10.2.5.1 and 10.2.5.2).

```
PROMPT> ec2-create-dhcp-options "domain-name=mydomain.com" "domain-name-servers=10.2.5.1,10.2.5.2"
DHCPOPTIONS dopt-7a8b9c2d
OPTION domain-name mydomain.com
OPTION domain-name-servers 10.2.5.1,10.2.5.2
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateDhcpOptions](#)

Related Commands

- [ec2-associate-dhcp-options](#) (p. 25)
- [ec2-delete-dhcp-options](#) (p. 186)
- [ec2-describe-dhcp-options](#) (p. 281)

ec2-create-group

Description

Creates a security group.

Important

EC2-Classic: You can create up to 500 security groups.

EC2-VPC: You can create up to 100 security groups per VPC.

A security group is for use with instances either in the EC2-Classic platform or in a specific VPC. For more information, see [Amazon EC2 Security Groups](#) in the *Amazon Elastic Compute Cloud User Guide* and [Security Groups for Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

When you create a security group, you specify a friendly name of your choice. You can have a security group for EC2-Classic with the same name as a security group for a VPC. However, you can't have two security groups for EC2-Classic with the same name or two security groups for a VPC with the same name.

You have a default security group for EC2-Classic and a default security group for your VPC. If you don't specify a security group when you launch an instance, the instance is launched into the appropriate default security group. A default security group includes a default rule that grants instances unrestricted network access to each other.

You can add or remove rules from your security groups using the `ec2-authorize` and `ec2-revoke` commands.

The short version of this command is `ec2addgrp`.

Syntax

```
ec2-create-group group_name -d description [-c vpc_id]
```

Options

Name	Description
<i>group_name</i>	The name of the security group. Type: String Default: None Constraints: Up to 255 characters in length Constraints for EC2-Classic: ASCII characters Constraints for EC2-VPC: a-z, A-Z, 0-9, spaces, and . _ - : / () # , @ [] + = & ; { } ! \$ * Required: Yes Example: webserv

Name	Description
<code>-d, --description <i>description</i></code>	A description for the security group. This is informational only. Type: String Default: None Constraints: Up to 255 characters in length Constraints for EC2-Classic: ASCII characters Constraints for EC2-VPC: a-z, A-Z, 0-9, spaces, and <code>._-:/()#,@[]+=&:{}!\$*</code> Required: Yes Example: <code>-d "Web Servers"</code>
<code>-c, --vpc <i>vpc_id</i></code>	[EC2-VPC] The ID of the VPC. Type: String Default: None Required: Conditional Condition: Required for EC2-VPC Example: <code>-c vpc-1a2b3c4d</code>

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url <i>URL</i></code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key <i>AWS_ACCESS_KEY</i></code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key</code> <i>AWS_SECRET_KEY</i>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> TOKEN <i>AWS_DELEGATION_TOKEN</i>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <i>TIMEOUT</i>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXI1BH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The GROUP identifier
- The AWS-assigned ID for the group
- The group name
- The group description

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates the `webserv` security group for EC2-Classic.

```
PROMPT> ec2-create-group webserv -d "Web Servers"  
GROUP sg-1a2b3c4d webserv Web Servers
```

Example Request

This example creates the `MyVPCGroup` security group for the VPC with the ID `vpc-3325caf2`.

```
PROMPT> ec2-create-group MyVPCGroup -d 'Group in my VPC' -c vpc-3325caf2  
GROUP sg-0a42d66a MyVPCGroup Group in my VPC
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateSecurityGroup](#)

Related Commands

- [ec2-authorize](#) (p. 49)

- [ec2-delete-group](#) (p. 192)
- [ec2-describe-group](#) (p. 289)
- [ec2-revoke](#) (p. 627)
- [ec2-run-instances](#) (p. 633)

ec2-create-image

Description

Creates an Amazon EBS-backed AMI from a running or stopped instance. For more information about Amazon EBS-backed AMIs, see [Storage for the Root Device](#).

Note

If you customized your instance with instance store volumes or Amazon EBS volumes in addition to the root device volume, the new AMI contains block device mapping information for those volumes. When you launch an instance from this new AMI, the instance automatically launches with those additional volumes.

The short version of this command is **ec2cim**.

Syntax

```
ec2-create-image instance_id --name name [--description description]  
[--no-reboot] [-b, --blockdevicemapping mapping]
```

Options

Name	Description
<i>instance_id</i>	The ID of the instance. Type: String Default: None Required: Yes Example: i-10a64379
-n, --name <i>name</i>	A name for the new image. Type: String Default: None Constraints: 3-128 alphanumeric characters, parenthesis (), commas (,), slashes (/), dashes (-), or underscores(_). Allows spaces if the name is enclosed in quotation marks. Required: Yes Example: -n "Standard Web Server"
-d, --description <i>description</i>	A description for the new image. Type: String Default: None Constraints: Up to 255 characters Required: No Example: -d Fedora_v11

Name	Description
<p><code>--no-reboot</code></p>	<p>When this option is absent, Amazon EC2 attempts to cleanly shut down the instance before image creation and reboots the instance. When this option is used, Amazon EC2 doesn't shut down the instance before creating the image; therefore, file system integrity on the created image can't be guaranteed.</p> <p>Type: Boolean Default: <code>false</code> Required: No Example: <code>--no-reboot</code></p>
<p><code>-b, --block-device-mapping <i>mapping</i></code></p>	<p>The block device mapping for the instance. This argument is passed in the form of <code><devicename>=<blockdevice></code>. The <i>devicename</i> is the device name of the physical device on the instance to map. The <i>blockdevice</i> can be one of the following values:</p> <ul style="list-style-type: none"> <code>none</code> - Suppresses an existing mapping of the device from the AMI used to launch the instance. For example: <code>"/dev/sdc=none"</code>. <code>ephemeral[0..3]</code> - An instance store volume to be mapped to the device. For example: <code>"/dev/sdc=ephemeral0"</code>. <code>[<i>snapshot-id</i>]:[<i>volume-size</i>]:[<i>true</i> <i>false</i>]:[<i>standard</i> <i>io1</i>]:[<i>iops</i>]</code> - An EBS volume to be mapped to the device. [<i>snapshot-id</i>] To create a volume from a snapshot, specify the snapshot ID. [<i>volume-size</i>] To create an empty EBS volume, omit the snapshot ID and specify a volume size instead. For example: <code>"/dev/sdh=:20"</code>. [<i>delete-on-termination</i>] To prevent the volume from being deleted on termination of the instance, specify <code>false</code>. The default is <code>true</code>. [<i>volume-type</i>] To create a Provisioned IOPS volume, specify <code>io1</code>. The default volume type is <code>standard</code>. If the volume type is <code>io1</code>, you can also provision the number of IOPS that the volume supports. For example, <code>"/dev/sdh=snap-7eb96d16::false:io1:500"</code>. <p>You can specify multiple <i>blockdevicemapping</i> arguments in one call.</p> <p>For more detailed information about block device mapping, see Block Device Mapping in the <i>Amazon Elastic Compute Cloud User Guide</i>.</p> <p>Type: String Default: None Required: No Example: <code>-b "/dev/sdc=snap-7eb96d16:100:false:io1:500"</code></p> <p>Note On Windows, the <i>mapping</i> argument must be enclosed in double quotes, as shown in the example.</p>

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.

Option	Description
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The IMAGE identifier
- The ID of the newly registered AMI

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates an AMI from the `i-10a64379` instance.

```
PROMPT> ec2-create-image i-10a64379 --name "Standard Web Server" --description
"Standard web server AMI"
IMAGE ami-4fa54026
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateImage](#)

Related Commands

- [ec2-describe-instances](#) (p. 320)
- [ec2-run-instances](#) (p. 633)
- [ec2-terminate-instances](#) (p. 654)

ec2-create-instance-export-task

Description

Exports a running or stopped instance to an Amazon S3 bucket. For information about the supported operating systems, image formats, and known limitations for the types of instances you can export, see [Exporting EC2 Instances](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2addixt**.

Syntax

```
ec2-create-instance-export-task instance_id -e target_environment -f
disk_image_format [-c container_format] -b S3_bucket [-p S3_prefix] [-d
description]
```

Options

Name	Description
<i>instance_id</i>	The ID of the instance to export. Required: Yes
-e, --target-environment <i>target_environment</i>	The target environment. VMware supports VMware 4 and 5. Citrix target Xen 6. Type: String Valid values: VMware Citrix Required: Yes
-f, --disk-image-format <i>disk_image_format</i>	The disk image file format used to represent the exported disk. Type: String Valid values: VMDK VHD Default: If -e = VMware, then -f = VMDK; otherwise VHD Required: No
-c, --container-format <i>container_format</i>	The container format used to combine disk images with metadata (such as OVF). If absent, only the disk image will be exported. Type: String Valid values: OVA Default: If -e = VMware, then -c = OVA; otherwise empty Required: No
-b, --bucket <i>S3_bucket</i>	The name of the destination Amazon S3 bucket where the file will be exported. The destination bucket must grant WRITE and READ_ACL permissions to the vm-import-export@amazon.com AWS account. Type: String Required: Yes

Name	Description
<code>-p, --prefix S3_prefix</code>	The prefix for the Amazon S3 key (object name) used for the exported file. Maximum length is 1000 bytes of UTF-8 character encoding. The final key is composed from this prefix (if supplied), the export-task-id, and other relevant parameters. Type: String Required: No Example: <code>my-export-, incoming/vm-export/</code>
<code>-d, --description description</code>	A free-form comment that is returned verbatim during subsequent calls to <code>ec2-describe-export-tasks</code> . Maximum length is 255 bytes. Type: String Required: No

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
-T, --security-token TOKEN AWS_DELEGATION_TOKEN	The AWS delegation token. Default: The value of the environment variable (if set).
--connection-timeout TIMEOUT	The connection timeout, in seconds. Example: --connection-timeout 30
--request-timeout TIMEOUT	The request timeout, in seconds. Example: --request-timeout 45
-v, --verbose	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
-H, --headers	Includes column headers in the command output.
--show-empty-fields	Shows empty columns as (nil).
--hide-tags	Omits tags for tagged resources.
--debug	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
-?, --help, -h	Displays usage information for the command.
-	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key EC2-PRIVATE-KEY	The private key to use when constructing requests to Amazon EC2. Default: The value of the EC2_PRIVATE_KEY environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
-C, --cert EC2-CERT	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the EC2_CERT environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The EXPORTTASK identifier.
- The export task ID.

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates a task to export an instance.

```
PROMPT> ec2-create-instance-export-task i-38e485d8 -e vmware -f vmdk -c ova -b
myexportbucket
EXPORTTASK      export-i-fgelt0i7      active      i-38e485d8      vmware      vmdk
myexportbucket  export-i-fgelt0i7.vmdk
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateInstanceExportTask](#)

Related Commands

- [ec2-cancel-export-task](#) (p. 68)
- [ec2-describe-export-tasks](#) (p. 286)

ec2-create-internet-gateway

Description

Creates a new Internet gateway for use with a VPC. After creating the Internet gateway, you attach it to a VPC using `ec2-attach-internet-gateway`. For more information about your VPC and Internet gateway, see the [Amazon Virtual Private Cloud User Guide](#).

The short version of this command is `ec2addigw`.

Syntax

`ec2-create-internet-gateway`

Options

This command does not have any options.

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJa1rXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-T, --security-token TOKEN</code> <i>AWS_DELEGATION_TOKEN</i>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The INTERNETGATEWAY identifier
- The ID of the Internet gateway

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates an Internet gateway.

```
PROMPT> ec2-create-internet-gateway  
INTERNETGATEWAY igw-c0a643a9
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateInternetGateway](#)

Related Commands

- [ec2-attach-internet-gateway](#) (p. 33)
- [ec2-delete-internet-gateway](#) (p. 196)
- [ec2-describe-internet-gateways](#) (p. 333)
- [ec2-detach-internet-gateway](#) (p. 464)

ec2-create-keypair

Description

Creates a new 2048-bit RSA key pair with the specified name. The public key is stored by Amazon EC2 and the private key is displayed on the console. The private key is returned as an unencrypted PEM encoded PKCS#8 private key. If a key with the specified name already exists, Amazon EC2 returns an error.

You can have up to five thousand key pairs per region.

Tip

The key pair returned to you works only in the region you're using when you create the key pair. To create a key pair that works in all regions, use [ec2-import-keypair](#) (p. 514).

The short version of this command is **ec2addkey**.

Syntax

```
ec2-create-keypair key
```

Options

Name	Description
<i>key</i>	A unique name for the key pair. Type: String Default: None Constraints: Accepts alphanumeric characters, spaces, dashes, and underscores. Required: Yes Example: mysecretkey

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The KEYPAIR identifier
- The name of the key pair
- The private key fingerprint
- The private key contents

You must save the private key contents, including the `----- BEGIN RSA PRIVATE KEY -----` and `-----END RSA PRIVATE KEY-----` lines, in a local file. This file should be kept in a safe place. This file is required to decrypt any information encrypted with the public key. For more information, see [Getting an SSH Key Pair](#) in the *Amazon Elastic Compute Cloud User Guide*.

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates a key pair named `gsg-keypair`.

```
PROMPT> ec2-create-keypair gsg-keypair
KEYPAIR gsg-keypair 1f:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00
----- BEGIN RSA PRIVATE KEY -----
MIICi TCCAfICCQD6m7oRw0uXOjANBgqhkiG9w0BAQUFADCBiDELMAkGAlUEBhMC
VVMxCzAJBgNVBAGTAldBMRawDgYDVRQQHEwdTZWF0dGx1MQ8wDQYDVQQKEwZBbWF6
b24xVDAsBgNVBAStC0lBTSDb25zb2xlMRlWEAYDVRQQDEwUjZSN0Q2lSYYWmXzAd
BgkqhkiG9w0BCQEWEG5vb25lQGFTYXp6bi5jb20wHhcnMTENDI1MjA0NTIxWhcN
MTIwNDIOMjA0NTIxWjCBiDELMAkGAlUEBhMCVVMxCzAJBgNVBAGTAldBMRawDgYD
VQQHEwdTZWF0dGx1MQ8wDQYDVQQKEwZBbWF6b24xVDAsBgNVBAStC0lBTSDb25z
b2xlMRlWEAYDVRQQDEwUjZSN0Q2lSYYWmXzAdBgkqhkiG9w0BCQEWEG5vb25lQGFT
YXp6bi5jb20wgZ8wDQYJKoZIhvcNAQEBBQADgY0AMIGJAOGBAMaK0dn+a4GmWIWJ
21uUSfwfEvySWtC2XADZ4nB+BLygVIk60Cp1wsZ3G93vUEIO3IyNoH/f0wYK8m9T
rDHudUZg3qX4waLG5M43q7Wgc/MbQITxOUsQv7c7ugFFDzQGBzZswY6786m86gpE
Ibb30hjZncvQAaRHhd1QWIMm2nrAgMBAAEwDQYJKoZIhvcNAQEFBQADgYEAtCu4
nUhVVxYUntned9+h8Mg9q6q+auNKyExzyLwaxlAoo7TJHidbtS4J5iNmZgXL0Fkb
FFBjvSfpJIlJ00zbhNYS5f6GuoEDmFJl0ZxBHjJnyp378OD8uTs7fLvJx79LjSTb
```

```
NYiytVbZPQUQ5Yaxu2jXnimvw3rrszlaEXAMPLE=  
-----END RSA PRIVATE KEY-----
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateKeyPair](#)

Related Commands

- [ec2-delete-keypair](#) (p. 199)
- [ec2-describe-keypairs](#) (p. 338)
- [ec2-run-instances](#) (p. 633)

ec2-create-network-acl

Description

Creates a network ACL in a VPC. Network ACLs provide an optional layer of security (on top of security groups) for the instances in your VPC. For more information about network ACLs, see [Network ACLs](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2addnacl**.

Syntax

`ec2-create-network-acl` *vpc_id*

Options

Name	Description
<i>vpc_id</i>	The ID of the VPC for the network ACL. Type: String Default: None Required: Yes Example: vpc-9ea045f7

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U</code> , <code>--url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O</code> , <code>--aws-access-key</code> <i>AWS_ACCESS_KEY</i>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXI1BH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The NETWORKACL identifier
- The ACL ID
- The ID of the VPC that the route table was created in
- The ENTRY elements created by default

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates a new network ACL in the VPC with ID `vpc-11ad4878`. Notice that the response includes a default entry for egress, and another for ingress, each with a very high rule number (32767). These are the last entries that we process to decide whether traffic is allowed into our out of an associated subnet. If the traffic doesn't match any rules with a lower rule number, then these default entries ultimately deny the traffic. The -1 means all protocols and ports.

```
PROMPT> ec2-create-network-acl vpc-11ad4878
NETWORKACL acl-5fb85d36 vpc-11ad4878
ENTRY egress 32767 deny 0.0.0.0/0 all
ENTRY ingress 32767 deny 0.0.0.0/0 all
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateNetworkAcl](#)

Related Commands

- [ec2-delete-network-acl](#) (p. 202)
- [ec2-describe-network-acls](#) (p. 342)
- [ec2-replace-network-acl-association](#) (p. 576)

ec2-create-network-acl-entry

Description

Creates an entry (a rule) in a network ACL with the specified rule number. Each network ACL has a set of numbered ingress rules and a separate set of numbered egress rules. When determining whether a packet should be allowed in or out of a subnet, we process the entries in the ACL according to the rule numbers, in ascending order. Each network ACL has a set of ingress rules and a separate set of egress rules.

Tip

We recommend that you leave room between the rule numbers (for example, 100, 110, 120, etc.), and not number them one right after the other (for example, 101, 102, 103, etc.). This makes it easier to add a new rule between existing ones without having to renumber the rules.

After you add an entry, you can't modify it; you must either replace it or create a new entry and delete the old one.

For more information about network ACLs, see [Network ACLs](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2addnae**.

Syntax

```
ec2-create-network-acl-entry acl_id -n rule_number [--egress] -P protocol -r cidr [-p port_range] [-t icmp_type_code] { --allow | --deny }
```

Options

Name	Description
<i>acl_id</i>	The ID of the ACL for the entry. Type: String Default: None Required: Yes Example: acl-5fb85d36
-n, --rule-number <i>rule_number</i>	The rule number to assign to the entry (for example, 100). ACL entries are processed in ascending order by rule number. Type: Number Default: None Constraints: Positive integer from 1 to 32766 Required: Yes Example: -n 100
--egress	Indicates that the rule be applied to traffic leaving the subnet. Default: If not specified, the rule applies to ingress traffic into the subnet. Required: No

Name	Description
<code>-P, --protocol protocol</code>	The IP protocol. You can specify <code>all</code> or <code>-1</code> to mean all protocols. Type: String Valid values: <code>all</code> <code>-1</code> <code>tcp</code> <code>udp</code> <code>icmp</code> or any protocol number (for a list, see Protocol Numbers). Required: Yes Example: <code>-P 6</code>
<code>-r, --cidr cidr</code>	The CIDR range to allow or deny, in CIDR notation. Type: String Default: None Required: Yes Example: <code>-r 172.16.0.0/24</code>
<code>-p, --port-range port_range</code>	For TCP or UDP: The range of ports to allow. Type: String Default: None Valid values: A single integer or a range (min-max). You can specify <code>-1</code> to mean all ports (for example, port range 0-65535). Required: Conditional Condition: Required if specifying <code>tcp</code> or <code>udp</code> (or the equivalent number) for the protocol. Example: <code>-p 80-84</code>
<code>-t, --icmp-type-code icmp_type_code</code>	For ICMP: The ICMP type and code using format <code>type:code</code> , where both are integers. You can use <code>-1</code> for the type or code to mean all types or all codes Type: String Default: None Required: Conditional Condition: Required if specifying <code>icmp</code> (or the equivalent number) for the protocol. Example: <code>-t -1:-1</code>
<code>--allow</code>	Specifies that any traffic matching the rule is allowed. Required: Conditional Condition: You must specify either <code>--allow</code> or <code>--deny</code> , but not both options.
<code>--deny</code>	Specifies that any traffic matching the rule is denied. Required: Conditional Condition: You must specify either <code>--allow</code> or <code>--deny</code> , but not both.

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.

Option	Description
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The ENTRY identifier

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates an entry with rule number 100 in the network ACL with ID `acl-2cb85d45`. The rule allows ingress traffic from anywhere (0.0.0.0/0) on UDP port 53 into the subnet.

```
PROMPT> ec2-create-network-acl-entry acl-2cb85d45 -n 100 -r 0.0.0.0/0 -P udp -
p 53 --allow
ENTRY  ingress 100      allow  0.0.0.0/0      udp      53
      53
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateNetworkAclEntry](#)

Related Commands

- [ec2-delete-network-acl-entry](#) (p. 205)
- [ec2-describe-network-acls](#) (p. 342)
- [ec2-replace-network-acl-entry](#) (p. 580)

ec2-create-network-interface

Description

Creates a network interface in the specified subnet. This command is supported only in EC2-VPC.

The short version of this command is **ec2addnic**.

Syntax

```
ec2-create-network-interface -d, --description description [--private-ip-address ip_address] [--secondary-private-ip-address ip_address] [--secondary-private-ip-address-count address_count] [-g, --group security_group_id]
```

Options

Name	Description
<code>-d, --description <i>description</i></code>	Set the description of the network interface. Type: String Default: None Required: No Example: -d "My ENI"
<code>--private-ip-address <i>ip_address</i></code>	The primary private IP address of the network interface. If an IP address is not specified, one will be auto-assigned to the interface. Type: String Default: None Required: No Example: --private-ip-address 10.0.2.17

Name	Description
<code>--secondary-private-ip-address</code> <i>ip_address</i>	<p>Assigns the specified IP address as a secondary private IP address to the network interface or instance. This option can be used multiple times to assign multiple secondary IP addresses.</p> <p>You can do one of the following:</p> <ul style="list-style-type: none"> • Use the <code>--secondary-private-ip-address</code> option without a value and AWS will automatically assign a secondary private IP address within the subnet range. • Use the <code>--secondary-private-ip-address</code> option and provide a specific IP address that you want to assign. <p>You cannot specify this parameter when also specifying <code>--secondary-private-ip-address-count</code>.</p> <p>Type: String Default: None Required: No Example: <code>--secondary-private-ip-address 10.0.2.18</code> <code>-secondary-private-ip-address 10.0.2.28</code></p>
<code>--secondary-private-ip-address-count</code> <i>address_count</i>	<p>The number of secondary IP addresses to assign to the network interface. You cannot specify this parameter when also specifying <code>--secondary-private-ip-address</code>.</p> <p>Type: Integer Default: None Required: No Example: <code>--secondary-private-ip-address-count 2</code></p>
<code>-g, --group</code> <i>security_group_id</i>	<p>A security group to add to the network interface. You can use this option multiple times to add multiple groups.</p> <p>Type: String Default: None. If no security group is specified, the interface will become a member of the default security group. Required: No Example: <code>-g sg-bba1bcd7 -g sg-6d495601</code></p>

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	<p>Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option.</p> <p>Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code></p>

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the EC2_PRIVATE_KEY environment variable. Example: -K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the EC2_CERT environment variable. Example: -C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem

Output

This command returns the ENI ID for the network interface that was created, along with the subnet ID, VPC ID, Availability Zone, private IP addresses, and security group membership.

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates a network interface address in the specified subnet.

```
PROMPT> ec2-create-network-interface -d "My ENI" -g sg-bbalbcd7 --private-ip-
address 10.0.2.17 subnet-fd04ff94
NETWORKINTERFACE   eni-3b9f6552   My ENI subnet-fd04ff94 vpc-e604ff8f   us-
east-1b   089818748305   false   pending 02:1a:80:41:52:9c   10.0.2.17   true

GROUP   sg-bbalbcd7   default
PRIVATEIPADDRESS 10.0.2.17
```

Example Request

This example creates a network interface address with a primary private IP address of 10.0.0.117, and two secondary private IP addresses: one secondary private IP address of 10.0.0.118 and another secondary private IP address that will be automatically assigned.

```
PROMPT> ec2-create-network-interface -d "My ENI" -g sg-b1b508d8 --private-ip-
address 10.0.0.117 --secondary-private-ip-address 10.0.0.118 subnet-b1b508d8
NETWORKINTERFACE   eni-f907b890   My ENI   subnet-b1b508d8 vpc-a2b508cb   ap-
southeast-1a 013274050172   false   pending 02:75:42:60:6c:05
10.0.0.117   true
```

```
GROUP    sg-82b3a1ee    default
PRIVATEIPADDRESS  10.0.0.117
PRIVATEIPADDRESS  10.0.0.118
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateNetworkInterface](#)

Related Commands

- [ec2-attach-network-interface](#) (p. 37)
- [ec2-delete-network-interface](#) (p. 209)
- [ec2-describe-network-interface-attribute](#) (p. 348)
- [ec2-describe-network-interfaces](#) (p. 352)
- [ec2-detach-network-interface](#) (p. 467)
- [ec2-modify-network-interface-attribute](#) (p. 541)
- [ec2-reset-network-interface-attribute](#) (p. 615)

ec2-create-placement-group

Description

Creates a placement group that you launch cluster instances into. You must give the group a name unique within the scope of your account. For more information about placement groups and cluster instances, see [Using Cluster Instances](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2addpgrp**.

Syntax

`ec2-create-placement-group placement_group -s strategy`

Options

Name	Description
<i>placement_group</i>	A name for the placement group. Type: String Default: None Required: Yes Example: XYZ-cluster
<code>-s <i>strategy</i></code>	The placement strategy. Type: String Valid values: cluster Default: cluster Required: Yes Example: -s cluster

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url <i>URL</i></code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The PLACEMENTGROUP identifier
- The placement group name
- The placement group strategy
- The state of the placement group

Examples

Example Request

This example creates the `XYZ-cluster` group.

```
PROMPT> ec2-create-placement-group XYZ-cluster -s cluster  
PLACEMENTGROUP XYZ-cluster cluster available
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreatePlacementGroup](#)

Related Commands

- [ec2-delete-placement-group](#) (p. 212)
- [ec2-describe-placement-groups](#) (p. 359)

ec2-create-reserved-instances-listing

Description

Creates a new listing for Amazon EC2 Reserved Instances that will be sold in the Reserved Instance Marketplace. You can submit one Reserved Instance listing at a time.

The Reserved Instance Marketplace matches sellers who want to resell Reserved Instance capacity that they no longer need with buyers who want to purchase additional capacity. Reserved Instances bought from third-party sellers through the Reserved Instance Marketplace work like any other Reserved Instances.

If you want to sell your Reserved Instances, you must first register as a Seller in the Reserved Instance Marketplace. After completing the registration process, you can create a Reserved Instance Marketplace listing of some or all of your Reserved Instances, and specify the upfront price you want to receive for them. Your Reserved Instance listings then become available for purchase.

For more information about Reserved Instance Marketplace, see [Reserved Instance Marketplace](#) in the *Amazon Elastic Compute Cloud User Guide*.

Syntax

```
ec2-create-reserved-instances-listing --reserved-instance RESERVED-INSTANCE  
--instance-count INSTANCE-COUNT [--client-token TOKEN] MONTH:PRICE  
[MONTH:PRICE[...]]
```

Options

Name	Description
<code>--reserved-instance</code> <i>RESERVED-INSTANCE</i>	The ID of the active Reserved Instance with which the instance you want to list is associated. Type: String Default: None Required: Yes
<code>--instance-count</code> <i>INSTANCE-COUNT</i>	The number of instances that are a part of a Reserved Instance account that will be listed in the Reserved Instance Marketplace. This number should be less or equal to the instance count associated with the Reserved Instance ID specified in this command. Type: Integer Default: Total number of Reserved Instances active for the account Required: Yes
<i>MONTH:PRICE</i>	The price and schedule entry, using the format MONTH:PRICE, where MONTH is the number of months and PRICE is the numerical part of the price you want for the specified months of the term. For example, 14:12.34 means you want to sell 14 months at the price of \$12.34. Type: String Default: None Required: Yes

Name	Description
<code>--client-token</code> <i>TOKEN</i>	<p>Unique, case-sensitive identifier you provide to ensure idempotency of your listings. This helps avoid duplicate listings. For more information, see Ensuring Idempotency in the <i>Amazon Elastic Compute Cloud User Guide</i>.</p> <p>Type: String Default: None Required: No</p>

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	<p>Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option.</p> <p>Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set.</p> <p>Example: <code>--region eu-west-1</code></p>
<code>-U, --url</code> <i>URL</i>	<p>The uniform resource locator (URL) of the Amazon EC2 web service entry point.</p> <p>Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set.</p> <p>Example: <code>-U https://ec2.amazonaws.com</code></p>
<code>-O, --aws-access-key</code> <i>AWS_ACCESS_KEY</i>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key</code> <i>AWS_SECRET_KEY</i>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token</code> <i>TOKEN</i> <i>AWS_DELEGATION_TOKEN</i>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout</code> <i>TIMEOUT</i>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>

Option	Description
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

The command returns a table that contains the following information:

The listing information

- The LISTING identifier
- Reserved Instance listing ID
- Reserved Instances ID

- Create Date
- Update Date
- Status
- Status Message

One or more rows that contain instance count information

- The INSTANCE-COUNT identifier
- The instance count state
- The instance count

One or more rows that contain price schedule information

- The PRICE-SCHEDULE identifier
- The term
- The price
- Whether or not the schedule is active

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates a Reserved Instance Marketplace listing from the existing Reserved Instance named *b847fa93-c736-4eae-bca1-e3147example*, which has 5 months remaining in its term. In this example, we set the upfront price at \$1.20.

The command looks like this:

```
PROMPT> ec2-create-reserved-instances-listing --reserved-instance b847fa93-c736-4eae-bca1-3147example --instance-count 1 05:01.20
```

Amazon EC2 returns output similar to the following:

```
PROMPT>Type ReservedInstancesListingId ReservedInstancesId CreateDate UpdateDate
Status StatusMessage
LISTING 095c0e18-c9e6-4692-97e5-653e0example b847fa93-c736-4eae-bca1-e3147example
Tue Aug 28 18:21:07 PDT 2012 Tue Aug 28 18:21:07 PDT 2012 active active
INSTANCE-COUNT available 1
INSTANCE-COUNT sold 0
INSTANCE-COUNT cancelled 0
INSTANCE-COUNT pending 0
PRICE-SCHEDULE 5 $1.2 true
PRICE-SCHEDULE 4 $1.2 false
PRICE-SCHEDULE 3 $1.2 false
PRICE-SCHEDULE 2 $1.2 false
PRICE-SCHEDULE 1 $1.2 true
```

Related Operations

- [ec2-cancel-reserved-instances-listing](#) (p. 71)
- [ec2-describe-reserved-instances-listings](#) (p. 373)

ec2-create-route

Description

Creates a route in a route table within a VPC. The route's target can be either a gateway attached to the VPC or a NAT instance in the VPC.

When determining how to route traffic, we use the route with the most specific match. For example, let's say the traffic is destined for 192.0.2.3, and the route table includes the following two routes:

- 192.0.2.0/24 (goes to some target A)
- 192.0.2.0/28 (goes to some target B)

Both routes apply to the traffic destined for 192.0.2.3. However, the second route in the list covers a smaller number of IP addresses and is therefore more specific, so we use that route to determine where to target the traffic.

For more information about route tables, see [Route Tables](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2addrtr**.

Syntax

```
ec2-create-route route_table_id -r cidr {-g gateway_id | -i instance_id | -n interface_id}
```

Options

Name	Description
<i>route_table_id</i>	The ID of the route table for the route. Type: String Default: None Required: Yes Example: rtb-5da34634
<code>-r, --cidr <i>cidr</i></code>	The CIDR address block used for the destination match. Routing decisions are based on the most specific match. Type: String Default: None Required: Yes Example: -r 0.0.0.0/0
<code>-g, --gateway <i>gateway_id</i></code>	The ID of a gateway in your VPC. Type: String Default: None Required: Conditional Condition: You must provide one of the following: a gateway ID, instance ID, or a network interface ID. Example: -g igw-68a34601

Name	Description
<code>-i, --instance <i>instance_id</i></code>	The ID of a NAT instance in your VPC. Type: String Default: None Required: Conditional Condition: You must provide one of the following: a gateway ID, instance ID, or a network interface ID. Example: <code>-i i-a7c871e3</code>
<code>-n, --network-interface <i>interface_id</i></code>	The network interface associated with the route. Type: String Default: None Required: Conditional Condition: You must provide one of the following: a gateway ID, instance ID, or a network interface. Example: <code>-n eni-5b729933</code>

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url <i>URL</i></code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key <i>AWS_ACCESS_KEY</i></code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key <i>AWS_SECRET_KEY</i></code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-T, --security-token TOKEN</code> <i>AWS_DELEGATION_TOKEN</i>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The ROUTE identifier
- The Internet gateway ID

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates a route in the route table with ID `rtb-e4ad488d`. The route matches all traffic (`0.0.0.0/0`) and routes it to the Internet gateway with ID `igw-eaad4883`.

```
PROMPT> ec2-create-route rtb-e4ad488d -r 0.0.0.0/0 -g igw-eaad4883  
ROUTE    igw-eaad4883    0.0.0.0/0
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateRoute](#)

Related Commands

- [ec2-delete-route](#) (p. 215)
- [ec2-describe-route-tables](#) (p. 386)
- [ec2-replace-route](#) (p. 584)

ec2-create-route-table

Description

Creates a route table within a VPC. After you create a new route table, you can add routes and associate the table with a subnet. For more information about route tables, see [Route Tables](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2addrtb**.

Syntax

`ec2-create-route-table` *vpc_id*

Options

Name	Description
<i>vpc_id</i>	The ID of the VPC for the route table. Type: String Default: None Required: Yes Example: vpc-9ea045f7

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key</code> <i>AWS_ACCESS_KEY</i>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXI1BH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The ROUTETABLE identifier
- The route table ID
- The ID of the VPC
- Information about the local route included in every new route table

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates a new route table within the VPC with the ID `vpc-9ea045f7`.

```
PROMPT> ec2-create-route-table vpc-9ea045f7  
ROUTETABLE rtb-6aa34603 vpc-9ea045f7  
ROUTE local active 172.16.0.0/16
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateRouteTable](#)

Related Commands

- [ec2-associate-route-table](#) (p. 29)
- [ec2-create-route](#) (p. 139)
- [ec2-delete-route-table](#) (p. 218)
- [ec2-describe-route-tables](#) (p. 386)
- [ec2-disassociate-route-table](#) (p. 486)
- [ec2-replace-route-table-association](#) (p. 588)

ec2-create-snapshot

Description

Creates a snapshot of an Amazon EBS volume and stores it in Amazon S3. You can use snapshots for backups, to make copies of instance store volumes, and to save data before shutting down an instance. For more information about Amazon EBS, see [Amazon Elastic Block Store](#) in the *Amazon Elastic Compute Cloud User Guide*.

When a snapshot is created, any AWS Marketplace product codes from the volume are propagated to the snapshot.

You can take a snapshot of an attached volume that is in use. However, snapshots only capture data that has been written to your Amazon EBS volume at the time the snapshot command is issued. This may exclude any data that has been cached by any applications or the operating system. If you can pause any file writes to the volume long enough to take a snapshot, your snapshot should be complete. However, if you cannot pause all file writes to the volume, you need to unmount the volume from within the instance, issue the snapshot command, and then remount the volume to ensure a consistent and complete snapshot.

To create a snapshot for Amazon EBS volumes that serve as root devices, you should stop the instance before taking the snapshot.

To unmount the volume in Linux/UNIX

- Enter the following command from the command line.

```
umount -d device_name
```

For example:

```
# umount -d /dev/sdh
```

To unmount the volume in Windows

1. In Disk Management, right-click the volume to unmount, and select **Change Drive Letter and Path**.
2. Select the mount point to remove and click **Remove**.

The short version of this command is **ec2addsnap**.

Syntax

```
ec2-create-snapshot volume_id [-d description]
```

Options

Name	Description
<code>volume_id</code>	The ID of the Amazon EBS volume to take a snapshot of. Type: String Default: None Required: Yes Example: vol-4d826724
<code>-d, --description description</code>	The description of the Amazon EBS snapshot. Type: String Default: None Constraints: Up to 255 characters Required: No Example: -d "Daily backup"

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
-T, --security-token TOKEN <i>AWS_DELEGATION_TOKEN</i>	The AWS delegation token. Default: The value of the environment variable (if set).
--connection-timeout <i>TIMEOUT</i>	The connection timeout, in seconds. Example: --connection-timeout 30
--request-timeout <i>TIMEOUT</i>	The request timeout, in seconds. Example: --request-timeout 45
-v, --verbose	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
-H, --headers	Includes column headers in the command output.
--show-empty-fields	Shows empty columns as (nil).
--hide-tags	Omits tags for tagged resources.
--debug	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
-?, --help, -h	Displays usage information for the command.
-	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The SNAPSHOT identifier
- The ID of the snapshot
- The ID of the volume
- The state of the snapshot (`pending`, `completed`, `error`)
- The time stamp when the snapshot initiated
- The percentage of completion
- The ID of the snapshot owner
- The size of the volume
- The description of the snapshot

Amazon EC2 command line tools display errors on `stderr`.

Examples

Example Request

This example creates a snapshot of volume `vol-1a2b3c4d`.

```
PROMPT> ec2-create-snapshot vol-1a2b3c4d --description "Daily Backup"  
SNAPSHOT snap-1a2b3c4d vol-1a2b3c4d pending YYYY-MM-DDTHH:MM:SS+0000  
111122223333 30 Daily Backup
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateSnapshot](#)

Related Commands

- [ec2-delete-snapshot](#) (p. 221)
- [ec2-describe-snapshots](#) (p. 395)

ec2-create-spot-datafeed-subscription

Description

Creates the data feed for Spot Instances, enabling you to view Spot Instance usage logs. You can create one data feed per account. For more information about Spot Instances, see [Spot Instances](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2addsds**.

Syntax

```
ec2-create-spot-datafeed-subscription --bucket bucket [--prefix prefix]
```

Options

Name	Description
<code>-b, --bucket <i>bucket</i></code>	The Amazon S3 bucket in which to store the Spot Instance datafeed. Type: String Default: None Constraints: Must be a valid bucket associated with your account. Required: Yes Example: <code>-b myawsbucket</code>
<code>-p, --prefix <i>bucket</i></code>	A prefix for the datafeed files. Type: String Default: None Required: No Example: <code>-p spotdata_</code>

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url <i>URL</i></code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The SPOTDATAFEEDSUBSCRIPTION identifier
- The AWS account ID of the owner
- The Amazon S3 bucket where the data feed is located
- The prefix for the data feed files
- The state (*Active* | *Inactive*)

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates the data feed for the account.

```
PROMPT> ec2-create-spot-datafeed-subscription -b myawsbucket -p spotdata_
SPOTDATAFEEDSUBSCRIPTION 111122223333 myawsbucket spotdata_ Active
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateSpotDatafeedSubscription](#)

Related Commands

- [ec2-delete-spot-datafeed-subscription](#) (p. 224)

- [ec2-describe-spot-datafeed-subscription](#) (p. 401)

ec2-create-subnet

Description

Creates a subnet in an existing VPC. You can create up to 20 subnets in a VPC. If you add more than one subnet to a VPC, they're set up in a star topology with a logical router in the middle. If you need more than 20 subnets, you can request more by going to [Request to Increase Amazon VPC Limits](#).

When you create each subnet, you provide the ID of the VPC and the CIDR block you want for the subnet. After you create a subnet, you can't change its CIDR block. The subnet's CIDR block can be the same as the VPC's CIDR block (assuming you want only a single subnet in the VPC), or a subset of the VPC's CIDR block. If you create more than one subnet in a VPC, the subnets' CIDR blocks must not overlap. The smallest subnet (and VPC) you can create uses a /28 netmask (16 IP addresses), and the largest uses a /16 netmask (65,536 IP addresses).

Important

AWS reserves both the first four and the last IP address in each subnet's CIDR block. They're not available for use.

If you launch an instance in a VPC using an Amazon EBS-backed AMI, the IP address doesn't change if you stop and restart the instance (unlike a similar instance launched outside a VPC, which gets a new IP address when restarted). It's therefore possible to have a subnet with no running instances (they're all stopped), but no remaining IP addresses available. For more information about Amazon EBS-backed AMIs, see [AMI Basics](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2addsubnet**.

Syntax

```
ec2-create-subnet -c vpc_id -i cidr [ -z zone ]
```

Options

Name	Description
-c <i>vpc_id</i>	The ID of the VPC for the subnet. Type: String Default: None Required: Yes Example: -c vpc-1a2b3c4d
-i <i>cidr</i>	The CIDR block for the subnet to cover. Type: String Default: None Required: Yes Example: -i 10.0.1.0/24
-z <i>zone</i>	The Availability Zone for the subnet. Type: String Default: AWS selects a zone for you (recommended). Required: No Example: -z us-east-1a

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.

Option	Description
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The SUBNET identifier
- The subnet ID
- The current state of the subnet (pending or available)
- The ID of the VPC the subnet is in
- The CIDR block assigned to the subnet
- The number of IP addresses in the subnet that are available
- The Availability Zone the subnet is in

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates a subnet with CIDR block 10.0.1.0/24 in the VPC with ID `vpc-1a2b3c4d`.

```
PROMPT> ec2-create-subnet -c vpc-1a2b3c4d -i 10.0.1.0/24  
SUBNET subnet-9d4a7b6c pending vpc-1a2b3c4d 10.0.1.0/24 251 us-east-  
1a
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateSubnet](#)

Related Commands

- [ec2-delete-subnet](#) (p. 227)
- [ec2-describe-subnets](#) (p. 418)

ec2-create-tags

Description

Adds or overwrites one or more tags for the specified resource or resources. Each resource can have a maximum of 10 tags. Each tag consists of a key and optional value. Tag keys must be unique per resource.

For more information about tags, see [Tagging Your Resources](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2addtag**.

Syntax

```
ec2-create-tags resource_id [resource_id ...] --tag key[=value] [--tag key[=value] ...]
```

Options

Name	Description
<i>resource_id</i>	The AWS-assigned ID of the resource you want to tag. You can specify multiple resources to assign the tags to. Type: String Default: None Required: Yes Example: ami-1a2b3c4d
--tag <i>key</i> or <i>key=value</i>	The key and optional value of the tag, separated by an equals sign (=). If you don't include a value, we set the value to an empty string. If you're using the command line tools on a Windows system, you might need to use quotation marks (for example, "key=value"). Type: String Default: None Constraints: Maximum tag key length is 128 characters. Maximum tag value length is 256 characters. Tag keys and values are case sensitive and accept Unicode characters. Required: Yes Example: --tag "stack=Production"

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.

Option	Description
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The TAG identifier
- The resource type identifier
- The resource ID
- The tag key
- The tag value

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example adds (or overwrites) two tags for an AMI and an instance. One of the tags is just a key (`webserver`), with no value. The other consists of a key (`stack`) and value (`Production`). We set the value of the `webserver` tag to an empty string.

```
PROMPT> ec2-create-tags ami-1a2b3c4d i-7d3e5a2f --tag webservers --tag  
"stack=Production"  
TAG image ami-1a2b3c4d webservers  
TAG image ami-1a2b3c4d stack Production  
TAG instance i-7d3e5a2f webservers  
TAG instance i-7d3e5a2f stack Production
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateTags](#)

Related Commands

- [ec2-delete-tags](#) (p. 230)
- [ec2-describe-tags](#) (p. 423)

ec2-create-volume

Description

Creates an Amazon EBS volume that can be attached to any instance in the same Availability Zone. Any AWS Marketplace product codes from the snapshot are propagated to the volume. For more information about Amazon EBS, see [Amazon Elastic Block Store](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2addvol**.

Syntax

```
ec2-create-volume [--size size | --snapshot snapshot_id [--size size]]
--availability-zone zone [--type type [--iops iops]]
```

Options

Name	Description
<code>-s, --size <i>size</i></code>	The size of the volume, in GiBs. Type: String Valid values: 1-1024 Valid values: If the volume type is <code>io1</code> , the minimum size of the volume is 10 GiB. Default: If you're creating the volume from a snapshot and don't specify a volume size, the default is the snapshot size. Condition: Required unless you're creating the volume from a snapshot. Required: Conditional Example: <code>-s 80</code>
<code>--snapshot <i>snapshot_id</i></code>	The snapshot from which to create the new volume. Type: String Default: None Required: Conditional Condition: Required if you are creating a volume from a snapshot. Example: <code>--snapshot snap-78a54011</code>
<code>-z, --availability-zone <i>zone</i></code>	The Availability Zone in which to create the new volume. Type: String Default: None Required: Yes Example: <code>-z us-east-1a</code>

Name	Description
<code>-t, --type type</code>	The volume type. Type: String Valid values: <code>standard</code> <code>io1</code> Default: <code>standard</code> Required: No Example: <code>-t io1</code>
<code>-i, --iops iops</code>	The number of I/O operations per second (IOPS) that the volume supports. Type: Integer Valid values: Range is 100 to 4000. Default: None Required: Conditional Condition: Required when the volume type is <code>io1</code> ; not used with <code>standard</code> volumes. Example: <code>-iops 500</code>

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key EC2_PRIVATE_KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The VOLUME identifier
- The ID of the volume
- The size of the volume, in GiBs
- The snapshot from which the volume was created, if applicable
- The Availability Zone in which the volume was created
- The volume state (`creating`, `available`, `in-use`, `deleting`, `error`)
- The time stamp when volume creation was initiated
- The EBS volume type
- The I/O operations per second (IOPS) of a provisioned IOPS volume

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates a new 20 GiB volume in Availability Zone `us-east-1a`.

```
PROMPT> ec2-create-volume --size 20 --availability-zone us-east-1a  
VOLUME vol-1a2b3c4d 20 us-east-1a creating YYYY-MM-DDTHH:MM:SS+0000 standard
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateVolume](#)

Related Commands

- [ec2-attach-volume](#) (p. 41)
- [ec2-delete-volume](#) (p. 234)
- [ec2-describe-availability-zones](#) (p. 262)

- [ec2-describe-volumes](#) (p. 438)
- [ec2-detach-volume](#) (p. 471)

ec2-create-vpc

Description

Creates a VPC with the CIDR block you specify. The smallest VPC you can create uses a /28 netmask (16 IP addresses), and the largest uses a /16 netmask (65,536 IP addresses). To help you decide how big to make your VPC, see [Your VPC and Subnets](#) in the *Amazon Virtual Private Cloud User Guide*.

By default, each instance you launch in the VPC has the default DHCP options that includes only a default DNS server that we provide (AmazonProvidedDNS). For more information about DHCP options, see [Using DHCP Options with Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2addvpc**.

Syntax

`ec2-create-vpc cidr [tenancy]`

Options

Name	Description
<i>cidr</i>	The CIDR block for the VPC. Type: String Default: None Required: Yes Example: 10.0.0.0/16
<i>tenancy</i>	The supported tenancy of instances launched into the VPC. A value of <code>default</code> means instances can be launched with any tenancy; a value of <code>dedicated</code> means all instances launched into the VPC will be launched as dedicated tenancy instances regardless of the tenancy assigned to the instance at launch. Setting the instance's tenancy attribute to <code>dedicated</code> specifies that your instance will run on single-tenant hardware. Type: String Default: <code>default</code> Valid values: <code>default</code> <code>dedicated</code> Required: No

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The VPC identifier
- The ID of the VPC
- The CIDR block of the VPC
- The current state of the VPC (`pending` or `available`)
- The ID of the DHCP options associated with the VPC (or `default` if none)
- The supported tenancy options for instances launched into the VPC (`default` or `dedicated`).

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates a VPC with CIDR block 10.0.0.0/16.

```
PROMPT> ec2-create-vpc 10.0.0.0/16
VPC vpc-1a2b3c4d pending 10.0.0.0/16 dopt-1a2b3c4d default
```

Example Request

This example creates a VPC with the `dedicated` tenancy option.

```
PROMPT> ec2-create-vpc 10.0.0.0/16 --tenancy dedicated
VPC vpc-1a2b3c4d pending 10.0.0.0/16 dopt-1a2b3c4d dedicated
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateVpc](#)

Related Commands

- [ec2-associate-dhcp-options \(p. 25\)](#)
- [ec2-create-dhcp-options \(p. 93\)](#)
- [ec2-delete-vpc \(p. 237\)](#)
- [ec2-describe-vpcs \(p. 448\)](#)

ec2-create-vpn-connection

Description

Creates a VPN connection between an existing virtual private gateway and customer gateway. The only supported connection type is `ipsec.1`.

The response includes information that you need to give to your network administrator to configure your customer gateway. The underlying native format of this information is XML; however, with the **ec2-create-vpn-connection** command, you can transform the information into a different format based on the vendor that makes your customer gateway (for example, Cisco or Juniper). If you use a vendor other than Cisco or Juniper, you can set the `--format` option to `generic`, and the information is formatted in a human readable format for your network administrator. If you want to see the native XML, you can specify `xml` as the value of the `--format` option. If you want to write your own stylesheet, you can use the `--stylesheet` option to specify that stylesheet and receive the output in your own format. Whereas the **ec2-create-vpn-connection** command lets you choose a format for the configuration information, the corresponding API action (`CreateVpnConnection`) returns only the native XML.

If you decide to shut down your VPN connection for any reason and then create a new one, you must reconfigure your customer gateway with the new information returned from this call.

For more information about VPN connections, see [Adding a Hardware Virtual Private Gateway to Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2addvpn**.

Syntax

```
ec2-create-vpn-connection -t type --customer-gateway customer_gateway_id  
--vpn-gateway vpn_gateway_id [--format format] | [--stylesheet your_stylesheet]
```

Options

Name	Description
<code>-t <i>type</i></code>	The type of VPN connection. Type: String Default: None Valid values: <code>ipsec.1</code> Required: Yes Example: <code>-t ipsec.1</code>
<code>--customer-gateway <i>customer_gateway_id</i></code>	The ID of the customer gateway. Type: String Default: None Required: Yes Example: <code>--customer-gateway cgw-b4dc3961</code>

Name	Description
<code>--vpn-gateway <i>vpn_gateway_id</i></code>	The ID of the virtual private gateway. Type: String Default: None Required: Yes Example: <code>--vpn-gateway vgw-8db04f81</code>
<code>--format <i>format</i></code>	Includes customer gateway configuration information in the response, in the format specified. The returned information can be formatted for various devices, including a Cisco device (<code>cisco-ios-isr</code>) or Juniper device (<code>juniper-junos-j</code>), in human readable format (<code>generic</code>), or in the native XML format (<code>xml</code>). Type: String Default: None Valid values: <code>cisco-ios-isr juniper-junos-j juniper-screensos-6.2 juniper-screensos-6.1 generic xml</code> Required: No Example: <code>--format cisco-ios-isr</code>
<code>--stylesheet <i>your_stylesheet</i></code>	Includes customer gateway configuration information in the response, formatted according to the custom XSL stylesheet specified. Type: String Default: None Required: No Example: <code>--stylesheet c:\my_stylesheet.xsl</code>
<code>--static-routes-only</code>	Indicates whether or not the VPN connection requires static routes. If you are creating a VPN connection for a device that does not support BGP, you must specify this value as true. Type: Boolean Default: <code>false</code> Required: No

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url <i>URL</i></code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The VPNCONNECTION identifier
- The VPN connection ID
- The current state of the VPN connection (pending, available, deleting, deleted)
- The type of VPN connection
- The customer gateway ID
- The virtual private gateway ID
- The configuration information for the customer gateway

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates a VPN connection between the virtual private gateway with ID `vgw-8db04f81` and the customer gateway with ID `cgw-b4dc3961`. The example specifies that the configuration information be formatted as needed for a Cisco customer gateway. Because it's a long set of information, we haven't displayed it here in the response. To see an example of the information returned, see the [Amazon Virtual Private Cloud Network Administrator Guide](#).

```
PROMPT> ec2-create-vpn-connection -t ipsec.1 --customer-gateway cgw-b4dc3961 -  
-vpn-gateway  
vgw-8db04f81 --format cisco-ios-isr  
VPNCONNECTION vpn-44a8938f pending ipsec.1 cgw-b4dc3961 vgw-8db04f81  
<Long customer gateway configuration data...>
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateVpnConnection](#)

Related Commands

- [ec2-attach-vpn-gateway](#) (p. 45)
- [ec2-create-subnet](#) (p. 154)
- [ec2-create-vpc](#) (p. 167)
- [ec2-delete-vpn-connection](#) (p. 240)
- [ec2-describe-vpn-connections](#) (p. 453)

ec2-create-vpn-gateway

Description

Creates a virtual private gateway. A virtual private gateway is the VPC-side endpoint for your VPN connection. You can create a virtual private gateway before creating the VPC itself.

For more information about virtual private gateways, see [Adding a Hardware Virtual Private Gateway to Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2addvgw**.

Syntax

```
ec2-create-vpn-gateway -t type
```

Options

Name	Description
-t <i>type</i>	The type of VPN connection this virtual private gateway supports. Type: String Default: None Valid values: ipsec.1 Required: Yes Example: -t ipsec.1

Common Options

Option	Description
--region <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: --region eu-west-1
-U, --url <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: -U https://ec2.amazonaws.com

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The VPNGATEWAY identifier
- The virtual private gateway ID
- The current state of the virtual private gateway (`pending`, `available`, `deleting`, `deleted`)
- The type of VPN connection the virtual private gateway supports
- The Availability Zone for the virtual private gateway
- Information about VPCs attached to the virtual private gateway (there are none attached when you first create a virtual private gateway)

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates a virtual private gateway.

```
PROMPT> ec2-create-vpn-gateway -t ipsec.1  
VPNGATEWAY vgw-8db04f81 pending ipsec.1
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateVpnGateway](#)

Related Commands

- [ec2-attach-vpn-gateway](#) (p. 45)
- [ec2-delete-vpn-gateway](#) (p. 246)
- [ec2-describe-vpn-gateways](#) (p. 459)
- [ec2-detach-vpn-gateway](#) (p. 475)

ec2-create-vpn-connection-route

Description

Creates a new static route associated with a VPN connection between an existing virtual private gateway and a VPN customer gateway. The static route allows traffic to be routed from the virtual private gateway to the VPN customer gateway.

This command is only available in EC2-VPC.

The short version of this command is **ec2cvcr**.

Syntax

```
ec2-create-vpn-connection-route --vpn-connection vpn_connection_id --cidr cidr_block
```

Options

Name	Description
<code>--vpn-connection <i>vpn_connection_id</i></code>	The ID of the VPN connection. Type: String Default: None Required: Yes
<code>--cidr <i>cidr_block</i></code>	The CIDR block associated with the local subnet of the customer data center. Type: String Default: None Required: Yes

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url <i>URL</i></code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

The command returns true if the operation succeeds or an error if the operation does not succeed.

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates a static route to the VPN connection for the VPN connection ID `vpn-83ad48ea` to the destination CIDR block `11.12.0.0/16`

```
PROMPT> ec2-create-vpn-connection-route --cidr "11.12.0.0/16" --vpn-connection  
vpn-83ad48ea  
RETURN true
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [CreateVpnConnectionRoute](#)

ec2-delete-customer-gateway

Description

Deletes a VPN customer gateway. You must delete the VPN connection before deleting the customer gateway.

For more information about VPN customer gateways, see [Adding a Hardware Virtual Private Gateway to Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is `ec2delcgw`.

Syntax

`ec2-delete-customer-gateway` *customer_gateway_id*

Options

Name	Description
<i>customer_gateway_id</i>	The ID of the customer gateway. Type: String Default: None Required: Yes Example: cgw-b4dc3961

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key</code> <i>AWS_ACCESS_KEY</i>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key</code> <code>AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> <code>TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <code>TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <code>TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <code>EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXI1BH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The CUSTOMERGATEWAY identifier
- The customer gateway ID

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example deletes the customer gateway with ID `cgw-b4dc3961`.

```
PROMPT> ec2-delete-customer-gateway cgw-b4dc3961  
CUSTOMERGATEWAY cgw-b4dc3961
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DeleteCustomerGateway](#)

Related Commands

- [ec2-create-customer-gateway](#) (p. 89)
- [ec2-describe-customer-gateways](#) (p. 276)

ec2-delete-dhcp-options

Description

Deletes a set of DHCP options that you specify. The action returns an error if the set of options you specify is currently associated with a VPC. You can disassociate the set of options by associating either a new set of options or the default options with the VPC.

For more information about DHCP options sets, see [Using DHCP Options with Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2deldopt**.

Syntax

```
ec2-delete-dhcp-options dhcp_options_id
```

Options

Name	Description
<i>dhcp_options_id</i>	The ID of the DHCP options. Type: String Default: None Required: Yes Example: dopt-7a8b9c2d

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The DHCP_OPTIONS identifier
- The DHCP options ID

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example deletes the set of DHCP options with ID `dopt-7a8b9c2d`.

```
PROMPT> ec2-delete-dhcp-options dopt-7a8b9c2d  
DHCOPTIONS dopt-7a8b9c2d
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DeleteDhcpOptions](#)

Related Commands

- [ec2-associate-dhcp-options](#) (p. 25)
- [ec2-create-dhcp-options](#) (p. 93)
- [ec2-describe-dhcp-options](#) (p. 281)

ec2-delete-disk-image

Description

Deletes a partially or fully uploaded disk image for conversion from Amazon S3. You can specify either the conversion task ID, or the URL to the import manifest file in Amazon S3. For more information, see [Using the Command Line Tools to Import Your Virtual Machine to Amazon EC2](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2ddi**.

Syntax

```
ec2-delete-disk-image { -t task_id | -u url } -o owner_access_key_id -w
owner_secret_access_key [--ignore-active-task]
```

Options

Name	Description
-t, --task <i>task_id</i>	The Task ID of the conversion task that is no longer active. Type: String Default: None Required: Conditional Condition: Either the task ID or the URL to the manifest is required. Example: -t import-i-fh95npoc
-u, --manifest-url <i>url</i>	The URL for an existing import manifest file. Use this option to delete the uploaded disk image even if one or more active conversion tasks still reference the manifest. Type: String Default: None Required: Conditional Condition: Either the task ID or the URL to the manifest is required. Example: -u http://s3.example.com/mydisk-to-delete.vmdk
-o, --owner-akid <i>owner_access_key_id</i>	The access Key ID of the owner of the bucket containing the uploaded disk image to be deleted. This parameter value is not sent to Amazon EC2. Type: String Default: None Required: Yes Example: -o AKIAIOSFODNN7EXAMPLE

Name	Description
<code>-w, --owner-sak owner_secret_access_key</code>	The AWS Secret Access Key of the owner of the bucket containing the uploaded disk image to be deleted. This parameter value is not sent to Amazon EC2. Type: String Default: None Required: Yes Example: <code>-w wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code>
<code>--ignore-active-task</code>	Delete the uploaded disk image despite having an active task. Using this option may cause active tasks to fail. Use this option at your own risk. Type: String Default: None Required: No Example: <code>--ignore-active-task</code>

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-T, --security-token</code> <code>TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <code>TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <code>TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <code>EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <code>EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- Task ID

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example deletes the `import-i-fh95npoc` disk image.

```
PROMPT> ec2-delete-disk-image -t import-i-fh95npoc -o AKIAIOSFODNN7EXAMPLE -w
wJa1rXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY
DELETE-TASK import-i-fh95npoc
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Commands

- [ec2-cancel-conversion-task](#) (p. 64)
- [ec2-import-instance](#) (p. 507)
- [ec2-import-volume](#) (p. 518)
- [ec2-resume-import](#) (p. 622)

ec2-delete-group

Description

Deletes a security group.

Important

If you attempt to delete a security group that contains instances, or is referenced by another security group, the operation fails with `InvalidGroup.InUse` for EC2-Classic or `DependencyViolation` for EC2-VPC.

A security group is for use with instances either in the EC2-Classic platform or in a specific VPC. For more information, see [Amazon EC2 Security Groups](#) in the *Amazon Elastic Compute Cloud User Guide* and [Security Groups for Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is `ec2delgrp`.

Syntax

```
ec2-delete-group { group_name | group_id }
```

Options

Name	Description
<i>group_name</i>	The name of the security group. Type: String Default: None Required: Conditional Condition: For EC2-Classical, default VPC, you can specify either <i>group_name</i> or <i>group_id</i> . Example: webserv
<i>group_id</i>	The ID of the security group. Type: String Default: None Required: Conditional Condition: Required for nondefault VPC; otherwise, you can specify either <i>group_name</i> or <i>group_id</i> . Example: sg-32fa9d3e

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key</code> <i>AWS_SECRET_KEY</i>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> TOKEN <i>AWS_DELEGATION_TOKEN</i>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <i>TIMEOUT</i>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- Success status (`true` or `false`)

Amazon EC2 command line tools display errors on `stderr`.

Examples

Example Request

This example deletes the security group for EC2-Classical `webserv`.

```
PROMPT> ec2-delete-group webserv
RETURN true
```

Example Request

This example deletes the security group for EC2-VPC with the ID `sg-1a2b3c4d`.

```
PROMPT> ec2-delete-group sg-1a2b3c4d
RETURN true
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DeleteSecurityGroup](#)

Related Commands

- [ec2-authorize](#) (p. 49)
- [ec2-create-group](#) (p. 97)
- [ec2-describe-group](#) (p. 289)
- [ec2-revoke](#) (p. 627)

ec2-delete-internet-gateway

Description

Deletes an Internet gateway from your AWS account. The gateway must not be attached to a VPC. For more information about your VPC and Internet gateway, see the [Amazon Virtual Private Cloud User Guide](#).

The short version of this command is `ec2deligw`.

Syntax

`ec2-delete-internet-gateway` *internet_gateway_id*

Options

Name	Description
<i>internet_gateway_id</i>	The ID of the Internet gateway. Type: String Default: None Required: Yes Example: igw-8db04f81

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U</code> , <code>--url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O</code> , <code>--aws-access-key</code> <i>AWS_ACCESS_KEY</i>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXI1BH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- Success status (`true` or `false`)

Amazon EC2 command line tools display errors on `stderr`.

Examples

Example Request

This example deletes the Internet gateway with ID `igw-eaad4883`.

```
PROMPT> ec2-delete-internet-gateway igw-eaad4883  
RETURN true
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- `DeleteInternetGateway`

Related Commands

- [ec2-attach-internet-gateway](#) (p. 33)
- [ec2-create-internet-gateway](#) (p. 111)
- [ec2-describe-internet-gateways](#) (p. 333)
- [ec2-detach-internet-gateway](#) (p. 464)

ec2-delete-keypair

Description

Deletes the specified key pair, by removing the public key from Amazon EC2. You must own the key pair.

The short version of this command is **ec2delkey**.

Syntax

`ec2-delete-keypair` *key_pair*

Options

Name	Description
<i>key_pair</i>	The name of the key pair. Type: String Default: None Required: Yes Example: primary_keypair

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U</code> , <code>--url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O</code> , <code>--aws-access-key</code> <i>AWS_ACCESS_KEY</i>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key</code> <i>AWS_SECRET_KEY</i>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> TOKEN <i>AWS_DELEGATION_TOKEN</i>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <i>TIMEOUT</i>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXI1BH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The KEYPAIR identifier
- The name of the deleted key pair

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example deletes the `gsg-keypair` key pair.

```
PROMPT> ec2-delete-keypair gsg-keypair  
KEYPAIR gsg-keypair
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DeleteKeyPair](#)

Related Commands

- [ec2-create-keypair](#) (p. 114)
- [ec2-describe-keypairs](#) (p. 338)

ec2-delete-network-acl

Description

Deletes a network ACL from a VPC. The ACL must not be associated with any subnets. You can't delete the default network ACL. For more information about network ACLs, see [Network ACLs](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2delnacl**.

Syntax

`ec2-delete-network-acl acl_id`

Options

Name	Description
<i>acl_id</i>	The ID of the network ACL. Type: String Default: None Required: Yes Example: acl-2cb85d45

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url <i>URL</i></code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key <i>AWS_ACCESS_KEY</i></code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key</code> <code>AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> <code>TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <code>TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <code>TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <code>EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXI1BH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- Success status (`true` or `false`)

Amazon EC2 command line tools display errors on `stderr`.

Examples

Example Request

This example deletes the network ACL with ID `acl-2cb85d45`.

```
PROMPT> ec2-delete-network-acl acl-2cb85d45  
RETURN      true
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- `DeleteNetworkAcl`

Related Commands

- [ec2-create-network-acl](#) (p. 118)
- [ec2-describe-network-acls](#) (p. 342)
- [ec2-replace-network-acl-association](#) (p. 576)

ec2-delete-network-acl-entry

Description

Deletes an ingress or egress entry (rule) from a network ACL. For more information about network ACLs, see [Network ACLs](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2delnae**.

Syntax

```
ec2-delete-network-acl-entry acl_id -n rule_number [--egress]
```

Options

Name	Description
<i>acl_id</i>	The ID of the network ACL. Type: String Default: None Required: Yes Example: acl-5fb85d36
<code>-n, --rule-number</code> <i>rule_number</i>	The rule number for the entry to delete. Type: Number Default: None Required: Yes Example: 100
<code>--egress</code>	Indicates that the rule is an egress rule. Default: If not specified, the rule is an ingress rule. Required: No

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- Success status (`true` or `false`)

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example deletes the ingress entry with rule number 100 from the network ACL with ID `acl-2cb85d45`.

```
PROMPT> ec2-delete-network-acl-entry acl-2cb85d45 -n 100
RETURN true
```

Example Request

This example deletes the egress entry with rule number 200 from the network ACL with ID `acl-2cb85d45`.

```
PROMPT> ec2-delete-network-acl-entry acl-2cb85d45 -n 200 --egress
RETURN true
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DeleteNetworkAclEntry](#)

Related Commands

- [ec2-create-network-acl-entry](#) (p. 121)
- [ec2-describe-network-acls](#) (p. 342)
- [ec2-replace-network-acl-entry](#) (p. 580)

ec2-delete-network-interface

Description

Deletes a network interface. Network interfaces must be detached from an instance before they can be deleted.

The short version of this command is **ec2delnic**.

Syntax

`ec2-delete-network-interface` *interface_id*

Options

Name	Description
<i>interface_id</i>	The network interface ID. Type: String Default: None Required: Yes Example: eni-3a9f6553

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U</code> , <code>--url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O</code> , <code>--aws-access-key</code> <i>AWS_ACCESS_KEY</i>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key EC2_PRIVATE_KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns the ID of the network interface that you deleted.

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example deletes the specified network interface.

```
PROMPT> ec2-delete-network-interface eni-3a9f6553  
NETWORKINTERFACE      eni-3a9f6553
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DeleteNetworkInterface](#)

Related Commands

- [ec2-attach-network-interface](#) (p. 37)
- [ec2-create-network-interface](#) (p. 126)
- [ec2-describe-network-interface-attribute](#) (p. 348)
- [ec2-describe-network-interfaces](#) (p. 352)
- [ec2-detach-network-interface](#) (p. 467)
- [ec2-modify-network-interface-attribute](#) (p. 541)
- [ec2-reset-network-interface-attribute](#) (p. 615)

ec2-delete-placement-group

Description

Deletes a placement group in your account. You must terminate all instances in a placement group before deleting it. For more information about placement groups and cluster instances, see [Using Cluster Instances](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2delgrp**.

`ec2-delete-placement-group` *placement_group*

Options

Name	Description
<i>placement_group</i>	The name of the placement group. Type: String Default: None Required: Yes Example: XYZ-cluster

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key</code> <i>AWS_ACCESS_KEY</i>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key</code> <i>AWS_SECRET_KEY</i>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> TOKEN <i>AWS_DELEGATION_TOKEN</i>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <i>TIMEOUT</i>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXI1BH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns the following information:

- The PLACEMENTGROUP identifier
- The name of the placement group
- The status of the placement group (`deleted`)

Examples

Example Request

This example deletes the XYZ-cluster placement group.

```
PROMPT> ec2-delete-placement-group XYZ-cluster  
PLACEMENTGROUP XYZ-cluster deleted
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DeletePlacementGroup](#)

Related Commands

- [ec2-create-placement-group](#) (p. 131)
- [ec2-describe-placement-groups](#) (p. 359)

ec2-delete-route

Description

Deletes a route from a route table in a VPC. For more information about route tables, see [Route Tables](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2delrt**.

Syntax

```
ec2-delete-route route_table_id -r cidr
```

Options

Name	Description
<i>route_table_id</i>	The ID of the route table. Type: String Default: None Required: Yes Example: rtb-5da34634
-r, --cidr <i>cidr</i>	The CIDR range for the route. The value you specify must match the CIDR for the route exactly. Type: String Default: None Required: Yes Example: 0.0.0.0/0

Common Options

Option	Description
--region <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: --region eu-west-1
-U, --url <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: -U https://ec2.amazonaws.com

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- Success status (`true` or `false`)

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example removes the route with destination CIDR 172.16.1.0/24 from the route table with ID `rtb-e4ad488d`.

```
PROMPT> ec2-delete-route rtb-e4ad488d -r 172.16.1.0/24  
RETURN          true
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DeleteRoute](#)

Related Commands

- [ec2-create-route](#) (p. 139)
- [ec2-describe-route-tables](#) (p. 386)
- [ec2-replace-route](#) (p. 584)

ec2-delete-route-table

Description

Deletes a route table from a VPC. The route table must not be associated with a subnet. You can't delete the main route table. For more information about route tables, see [Route Tables](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is `ec2delrtb`.

Syntax

`ec2-delete-route-table` *route_table_id*

Options

Name	Description
<i>route_table_id</i>	The ID of the route table. Type: String Default: None Required: Yes Example: rtb-7aa34613

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key</code> <i>AWS_ACCESS_KEY</i>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- Success status (`true` or `false`)

Amazon EC2 command line tools display errors on `stderr`.

Examples

Example Request

This example deletes the route table with ID `rtb-7aa34613`.

```
PROMPT> ec2-delete-route-table rtb-7aa34613  
RETURN true
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DeleteRouteTable](#)

Related Commands

- [ec2-associate-route-table](#) (p. 29)
- [ec2-create-route-table](#) (p. 143)
- [ec2-describe-route-tables](#) (p. 386)
- [ec2-disassociate-route-table](#) (p. 486)
- [ec2-replace-route-table-association](#) (p. 588)

ec2-delete-snapshot

Description

Deletes a snapshot of an Amazon EBS volume.

Note

If you make periodic snapshots of a volume, the snapshots are incremental so that only the blocks on the device that have changed since your last snapshot are incrementally saved in the new snapshot. Even though snapshots are saved incrementally, the snapshot deletion process is designed so that you need to retain only the most recent snapshot in order to restore the volume.

The short version of this command is **ec2delsnap**.

Syntax

`ec2-delete-snapshot` *snapshot_id*

Options

Name	Description
<i>snapshot_id</i>	The ID of the Amazon EBS snapshot. Type: String Default: None Required: Yes Example: snap-78a54011

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U</code> , <code>--url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key</code> <code>AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key</code> <code>AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> TOKEN <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> TIMEOUT	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> TIMEOUT	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The SNAPSHOT identifier
- The ID of the snapshot

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example deletes snapshot `snap-1a2b3c4d`.

```
PROMPT> ec2-delete-snapshot snap-1a2b3c4d  
SNAPSHOT snap-1a2b3c4d
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DeleteSnapshot](#)

Related Commands

- [ec2-create-snapshot](#) (p. 146)
- [ec2-describe-snapshots](#) (p. 395)

ec2-delete-spot-datafeed-subscription

Description

Deletes the data feed for Spot Instances. For more information about Spot Instances, see [Spot Instances](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2delsds**.

Syntax

```
ec2-delete-spot-datafeed-subscription
```

Options

This command does not have any options.

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-T, --security-token TOKEN</code> <i>AWS_DELEGATION_TOKEN</i>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns no output.

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example deletes the data feed for the account.

```
PROMPT> ec2-delete-spot-datafeed-subscription  
-
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DeleteSpotDatafeedSubscription](#)

Related Commands

- [ec2-create-spot-datafeed-subscription](#) (p. 150)
- [ec2-describe-spot-datafeed-subscription](#) (p. 401)

ec2-delete-subnet

Description

Deletes a subnet from a VPC. You must terminate all running instances in the subnet before deleting it, otherwise the action returns an error.

The short version of this command is `ec2delsubnet`.

Syntax

`ec2-delete-subnet` *subnet_id*

Options

Name	Description
<i>subnet_id</i>	The ID of the subnet. Type: String Default: None Required: Yes Example: subnet-9d4a7b6c

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U</code> , <code>--url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O</code> , <code>--aws-access-key</code> <i>AWS_ACCESS_KEY</i>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The SUBNET identifier
- The ID of the subnet

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example deletes the subnet with ID `subnet-9d4a7b6c`.

```
PROMPT> ec2-delete-subnet subnet-9d4a7b6c  
SUBNET subnet-9d4a7b6c
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DeleteSubnet](#)

Related Commands

- [ec2-create-subnet](#) (p. 154)
- [ec2-describe-subnets](#) (p. 418)

ec2-delete-tags

Description

Deletes a specific set of tags from a specific set of EC2 resources. This command is designed to follow the `ec2-describe-tags` command. First determine what tags a resource has, then call `ec2-delete-tags` with the resource ID and the specific tags you want to delete.

For more information about tags, see [Tagging Your Resources](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is `ec2deltag`.

Syntax

```
ec2-delete-tags resource_id [resource_id ... ] --tag key[=value] [--tag key[=value] ... ]
```

Options

Name	Description
<i>resource_id</i>	The AWS-assigned identifier of the resource. You can specify more than one resource ID. Type: String Default: None Required: Yes Example: i-1a2b3c4d
--tag <i>key</i> or <i>key=value</i>	The key and optional value of the tag, separated by an equals sign (=). You can specify more than one tag to remove. Type: String Default: None Required: Yes Example: --tag "stack=Production"

Common Options

Option	Description
--region <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: --region eu-west-1

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information for tags that were deleted:

- The TAG identifier
- The resource type identifier
- The resource ID
- The tag key
- The tag value

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example deletes the tags for the AMI with ID `ami-1a2b3c4d`. You first get a list of the tags.

```
PROMPT> ec2-describe-tags --filter "resource-id=ami-1a2b3c4d"
TAG ami-1a2b3c4d image webserver
TAG ami-1a2b3c4d image stack Production
```

Then you delete the tags. Specifying the value for the `stack` tag is optional.

```
PROMPT> ec2-delete-tags ami-1a2b3c4d --tag webserver --tag "stack=Production"
```

If you specify a value for the key, the tag is deleted only if the tag's value matches the one you specified. If you specify the empty string as the value, the tag is deleted only if the tag's value is the empty string. The following example specifies the empty string as the value for the tag to delete (notice the equals sign after `Owner`).

```
PROMPT> ec2-delete-tags snap-4dfg39a --tag "Owner="
```

Example Request

This example deletes the *stack* tag from two particular instances.

```
PROMPT> ec2-delete-tags i-5f4e3d2a i-12345678 --tag stack
```

Example Request

You can specify a tag key without a corresponding tag value if you want to delete the tag regardless of its value. This example deletes all tags for the specified resources that have a key of `Purpose`, regardless of the tag value.

```
PROMPT> ec2-delete-tags i-5f4e3d2a i-4d5h8a9b i-1d3d4fae --tag Purpose
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DeleteTags](#)

Related Commands

- [ec2-create-tags](#) (p. 158)
- [ec2-describe-tags](#) (p. 423)

ec2-delete-volume

Description

Deletes an Amazon EBS volume. The volume must be in the `available` state (not attached to an instance). For more information about Amazon EBS, see [Amazon Elastic Block Store](#) in the *Amazon Elastic Compute Cloud User Guide*.

Note

The volume remains in the `deleting` state for several minutes after you run this command.

The short version of this command is `ec2delvol`.

Syntax

```
ec2-delete-volume volume_id
```

Options

Name	Description
<i>volume_id</i>	The ID of the volume. Type: String Default: None Required: Yes Example: vol-4282672b

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The VOLUME identifier
- The ID of the volume that was deleted

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example deletes volume `vol-1a2b3c4d`.

```
PROMPT> ec2-delete-volume vol-1a2b3c4d  
VOLUME vol-1a2b3c4d
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DeleteVolume](#)

Related Commands

- [ec2-attach-volume](#) (p. 41)
- [ec2-create-volume](#) (p. 162)
- [ec2-describe-volumes](#) (p. 438)
- [ec2-detach-volume](#) (p. 471)

ec2-delete-vpc

Description

Deletes a VPC. You must detach or delete all gateways or other objects that are dependent on the VPC first. For example, you must terminate all running instances, delete all security groups associated with the VPC (except the default), delete all route tables (except the default), and so on.

The short version of this command is **ec2delvpc**.

Syntax

`ec2-delete-vpc` *vpc_id*

Options

Name	Description
<i>vpc_id</i>	The ID of the VPC. Type: String Default: None Required: Yes Example: vpc-1a2b3c4d

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U</code> , <code>--url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O</code> , <code>--aws-access-key</code> <i>AWS_ACCESS_KEY</i>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key</code> <i>AWS_SECRET_KEY</i>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> TOKEN <i>AWS_DELEGATION_TOKEN</i>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <i>TIMEOUT</i>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXI1BH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The VPC identifier
- The ID of the VPC

Amazon EC2 command line tools display errors on `stderr`.

Examples

Example Request

This example deletes the VPC with ID `vpc-1a2b3c4d`.

```
PROMPT> ec2-delete-vpc vpc-1a2b3c4d  
VPC vpc-1a2b3c4d
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DeleteVpc](#)

Related Commands

- [ec2-create-vpc](#) (p. 167)
- [ec2-describe-vpcs](#) (p. 448)

ec2-delete-vpn-connection

Description

Deletes a VPN connection. Use this command to delete a VPC and its associated components. Another reason to use this command is if you believe that the tunnel credentials for your VPN connection have been compromised. In that situation, you can delete the VPN connection and create a new one that has new keys, without needing to delete the VPC or virtual private gateway. If you create a new VPN connection, you must reconfigure the customer gateway using the new configuration information returned with the new VPN connection ID.

If you're deleting the VPC and its associated components, we recommend that you detach the virtual private gateway from the VPC and delete the VPC before deleting the VPN connection.

For more information about VPN connections, see [Adding a Hardware Virtual Private Gateway to Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2delvpn**.

Syntax

```
ec2-delete-vpn-connection vpn_connection_id
```

Options

Name	Description
<i>vpn_connection_id</i>	The ID of the VPN connection. Type: String Default: None Required: Yes Example: vpn-44a8938f

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key</code> <code>AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key</code> <code>AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> <code>TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <code>TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <code>TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The VPNCONNECTION identifier
- The ID of the VPN connection

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example deletes the VPN connection with ID `vpn-44a8938f`.

```
PROMPT> ec2-delete-vpn-connection vpn-44a8938f  
VPNCONNECTION vpn-44a8938f
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DeleteVpnConnection](#)

Related Commands

- [ec2-create-vpn-connection](#) (p. 171)
- [ec2-delete-vpc](#) (p. 237)
- [ec2-describe-vpn-connections](#) (p. 453)
- [ec2-detach-vpn-gateway](#) (p. 475)

ec2-delete-vpn-connection-route

Description

Deletes an existing static route associated with a VPN connection between an existing virtual private gateway and a VPN customer gateway. The static route allows traffic to be routed from the virtual private gateway to the VPN customer gateway.

This command is only available in EC2-VPC.

The short version of this command is **ec2dvcr**.

Syntax

```
ec2-delete-vpn-connection-route --vpn-connection vpn_connection_id --cidr cidr_block
```

Options

Name	Description
<code>--vpn-connection</code> <i>vpn_connection_id</i>	The ID of the VPN connection. Type: String Default: None Required: Yes
<code>--cidr</code> <i>cidr_block</i>	The CIDR block associated with the local subnet of the customer data center. Type: String Default: None Required: Yes

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

The command returns true if the operation succeeds or an error if the operation does not succeed.

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example deletes a static route to the VPN connection for the VPN connection ID `vpn-83ad48ea` to the destination CIDR block `11.12.0.0/16`

```
PROMPT> ec2-delete-vpn-connection-route--cidr "11.12.0.0/16" --vpn-connection  
vpn-83ad48ea  
RETURN true
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DeleteVpnConnectionRoute](#)

ec2-delete-vpn-gateway

Description

Deletes a virtual private gateway. Use this command to delete a VPC and its associated components because you no longer need them. We recommend that before you delete a virtual private gateway, you detach it from the VPC and delete the VPN connection. Note that you don't need to delete the virtual private gateway if you just want to delete and recreate the VPN connection between your VPC and data center.

For more information about virtual private gateways, see [Adding a Hardware Virtual Private Gateway to Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2delvgw**.

Syntax

```
ec2-delete-vpn-gateway vpn_gateway_id
```

Options

Name	Description
<i>vpn_gateway_id</i>	The ID of the virtual private gateway. Type: String Default: None Required: Yes Example: vgw-8db04f81

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The VPNGATEWAY identifier
- The ID of the virtual private gateway

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example deletes the virtual private gateway with ID `vgw-8db04f81`.

```
PROMPT> ec2-delete-vpn-gateway vgw-8db04f81  
VPNGATEWAY vgw-8db04f81
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DeleteVpnGateway](#)

Related Commands

- [ec2-create-vpn-gateway](#) (p. 176)
- [ec2-delete-vpn-connection](#) (p. 240)
- [ec2-describe-vpn-gateways](#) (p. 459)

ec2-deregister

Description

Deregisters the specified AMI. After you deregister an AMI, it can't be used to launch new instances.

Note

This command does not delete the AMI.

The short version of this command is **ec2dereg**.

Syntax

`ec2-deregister` *ami_id*

Options

Name	Description
<i>ami_id</i>	The ID of the AMI. Type: String Default: None Required: Yes Example: ami-4fa54026

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key</code> <i>AWS_ACCESS_KEY</i>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key</code> <code>AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> <code>TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <code>TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <code>TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <code>EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The IMAGE identifier
- The ID of the AMI

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example deregisters the `ami-1a2b3c4d` AMI.

```
PROMPT> ec2-deregister ami-1a2b3c4d  
IMAGE ami-1a2b3c4d
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DeregisterImage](#)

Related Commands

- [ec2-describe-images](#) (p. 299)
- [ec2-register](#) (p. 566)

ec2-describe-account-attributes

Description

Describes the specified attribute of your AWS account.

The short version of this command is **ec2daa**.

Syntax

```
ec2-describe-account-attributes { supported-platforms | default-vpc } [--filter "name=value"] ...]
```

Options

Name	Description
supported-platforms	Specifies whether your account can launch instances into EC2-Classic and EC2-VPC, or only into EC2-VPC. For more information, see Supported Platforms . Required: No
default-vpc	The ID of the default VPC for your account, or <code>none</code> . For more information, see Your Default VPC and Subnets . Required: No

Common Options

Option	Description
--region <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U</code> , --url <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O</code> , --aws-access-key <i>AWS_ACCESS_KEY</i>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key</code> <i>AWS_SECRET_KEY</i>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> TOKEN <i>AWS_DELEGATION_TOKEN</i>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <i>TIMEOUT</i>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXI1BH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The ACCOUNTATTRIBUTE identifier
- The attribute name
- The VALUE identifier
- The attribute value

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

The following command is used to determine the platforms that are supported by the specified account.

```
PROMPT> ec2-describe-account-attributes supported-platforms
```

This example response shows the output for an account that must launch instances into a VPC, such as the default VPC.

```
ACCOUNTATTRIBUTE supported-platforms  
VALUE EC2-VPC
```

This example response shows the output for an account that can launch instances into a VPC or into EC2-Classic.

```
ACCOUNTATTRIBUTE supported-platforms  
VALUE EC2-Classic  
VALUE EC2-VPC
```

Example Request

The following command is used to determine the ID of the default VPC.

```
PROMPT> ec2-describe-account-attributes default-vpc
```

This example response shows the output for an account with a default VPC.

```
ACCOUNTATTRIBUTE default-vpc  
VALUE vpc-1a2b3c4d
```

This example response shows the output for an account without a default VPC.

```
ACCOUNTATTRIBUTE default-vpc  
VALUE none
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeAccountAttributes](#)

ec2-describe-addresses

Description

Describes one or more of your Elastic IP addresses.

An Elastic IP address is for use in either the EC2-Classical platform or in a VPC. For more information, see [Elastic IP Addresses](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2daddr**.

Syntax

```
ec2-describe-addresses [public_ip ... | allocation_id ...] [--filter "name=value"] ...]
```

Options

Name	Description
<i>public_ip</i>	[EC2-Classical] One or more Elastic IP addresses. Type: String Default: Describes all your Elastic IP addresses. Required: No Example: 198.51.100.1
<i>allocation_id</i>	[EC2-VPC] One or more allocation IDs. Type: String Default: Describes all your Elastic IP addresses. Required: No Example: eipalloc-9558a4fc
<code>-F, --filter name=value</code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value string ("name=value"). Type: String Default: Describes all your Elastic IP addresses, or only those you specified. Required: No Example: --filter "instance-id=i-1a2b3c4d"

Supported Filters

You can specify filters so that the response includes information for only certain Elastic IP addresses. For example, you can use a filter to specify that you're interested in addresses that have a specific tag. You can specify multiple values for a filter. The response includes information for an address only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify addresses of a specific value that have a specific tag. The response includes information for an address only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

domain

Indicates whether the address is for use in a VPC.

Type: String

Valid values: `standard` | `vpc`

instance-id

The instance the address is associated with (if any).

Type: String

public-ip

The Elastic IP address.

Type: String

allocation-id

The allocation ID for the address (VPC only).

Type: String

association-id

The association ID for the address (VPC only).

Type: String

network-interface-id

The network interface (if any) that the address is associated with (VPC only).

Type: String

network-interface-owner-id

The owner IID.

Type: String

private-ip-address

The private IP address associated with the Elastic IP address (VPC only).

Type: String

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the EC2_PRIVATE_KEY environment variable. Example: -K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the EC2_CERT environment variable. Example: -C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem

Output

This command returns a table that contains the following information:

- The ADDRESS identifier
- The Elastic IP address
- The ID of the instance to which the IP address is associated, if any
- The domain of the Elastic IP address (standard or vpc)
- [EC2-VPC] The allocation ID
- [EC2-VPC] The association ID
- [EC2-VPC] The private IP address associated with the Elastic IP address

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example describes the Elastic IP address 192.0.2.1, which is assigned to instance i-f15ebb98 in EC2-Classic.

```
PROMPT> ec2-describe-addresses 192.0.2.1
ADDRESS 192.0.2.1 i-f15ebb98 standard
```

Example Request

This example describes the Elastic IP address with allocation ID eipalloc-282d9641, which is assigned to instance i-7a00642 in EC2-VPC.

```
PROMPT> ec2-describe-addresses eipalloc-9258a4fb
Type      Address      Instance      Domain      AllocationId
AssociationId      NetworkInterfaceID
PrivateIP ADDRESS 203.0.113.0 i-7a00642e vpc eipalloc-282d9641
eipassoc-252d964c eni-d83388b1 10.0.0.14 4
```


Example Request

This example describes all your Elastic IP addresses (for both EC2-Classic and your VPCs).

```
PROMPT> ec2-describe-addresses  
ADDRESS 203.0.113.12    i-f15ebb98    standard  
ADDRESS 203.0.113.22    i-9e9da4e9    vpc           eipalloc-9258a4fb    eipassoc-  
0659a56f  
ADDRESS 203.0.113.32    vpc           eipalloc-9558a4fc
```

Example Request

This example describes your Elastic IP addresses for EC2-VPC.

```
PROMPT> ec2-describe-addresses --filter "allocation-id=*" -H  
ec2-describe-addresses -H  
Type          Address          Instance          Domain  AllocationId  
AssociationId  NetworkInterfaceID  
PrivateIP     ADDRESS 203.0.113.10          vpc           eipalloc-1b5fe072  
eipassoc-eb5fe082    eni-0689366f    10.0.1.35  
                ADDRESS 203.0.113.20          i-c844219c    vpc           eipalloc-b463dcdd  
eipassoc-d218a3bb    eni-ea67dc83    10.0.0.174  
                ADDRESS 203.0.113.140        i-ba6a0d      vpc           eipalloc-1266dd7b  
eipassoc-39e15b50    eni-73e05a1a    10.0.0.85  
                ADDRESS 203.0.113.140        i-7a00642    vpc           eipalloc-f38a359a  
eipassoc-1f239876    eni-d83388b1    10.0.0.12  
                ADDRESS 203.0.113.177        i-7a00642e    vpc           eipalloc-282d9641  
eipassoc-252d964c    eni-d83388b1    10.0.0.14
```

Example Request

This example describes Elastic IP addresses associated with a particular private IP address in EC2-VPC.

```
PROMPT> ec2-describe-addresses --filter "private-ip-address=10.0.0.94"  
ADDRESS 203.0.113.155    vpc           eipalloc-fdfc4394    eipassoc-52fa453b  
eni-66fc430f    10.0.0.94
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeAddresses](#)

Related Commands

- [ec2-allocate-address](#) (p. 12)

- [ec2-associate-address](#) (p. 20)
- [ec2-disassociate-address](#) (p. 482)
- [ec2-release-address](#) (p. 572)

ec2-describe-availability-zones

Description

Describes one or more of the Availability Zones that are available to you. The results include zones only for the region you're currently using.

Note

Availability Zones are not the same across accounts. The Availability Zone `us-east-1a` for account A is not necessarily the same as `us-east-1a` for account B. Availability Zone assignments are mapped independently for each account.

The short version of this command is `ec2daz`.

Syntax

```
ec2-describe-availability-zones [zone_name ...] [--filter "name=value" ...]
```

Options

Name	Description
<i>zone_name</i>	One or more Availability Zone names. Type: String Default: Describes all zones in the region. Required: No Example: <code>us-east-1a</code>
<code>-F, --filter <i>name=value</i></code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space (" <code>name=value example</code> "). On a Windows system, use quotation marks even without a space in the value string (" <code>name=value</code> "). Type: String Default: Describes all zones in the region, or only those you specified by name. Required: No Example: <code>--filter "region-name=ap-southeast-1"</code>

Supported Filters

You can specify filters so that the response includes information for only certain Availability Zones. For example, you can use a filter to specify that you're interested in Availability Zones in the `available` state. You can specify multiple values for a filter. The response includes information for an Availability Zone only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify Availability Zones that are in a particular region and are in the `available` state. The response includes information for an Availability Zone only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

message

Information about the Availability Zone.

Type: String

region-name

The region for the Availability Zone (for example, us-east-1).

Type: String

state

The state of the Availability Zone

Type: String

Valid values: available

zone-name

The name of the zone.

Type: String

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key</code> <i>AWS_SECRET_KEY</i>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> TOKEN <i>AWS_DELEGATION_TOKEN</i>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <i>TIMEOUT</i>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXI1BH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information for each Availability Zones retrieved:

- The AVAILABILITYZONE identifier
- The name of the Availability Zone
- The state of the zone
- The region that the Availability Zone belongs to
- Any messages associated with the Availability Zone

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example displays information about Availability Zones that are available to the account. The response includes zones only for the region you're currently using.

```
PROMPT> > ec2-describe-availability-zones  
AVAILABILITYZONE us-east-1a available us-east-1  
AVAILABILITYZONE us-east-1b available us-east-1  
AVAILABILITYZONE us-east-1c available us-east-1
```

Example Request

This example displays information about Availability Zones that are available to the account in the `us-east-1` region.

```
PROMPT> > ec2-describe-availability-zones --region us-east-1  
AVAILABILITYZONE us-east-1a available us-east-1  
AVAILABILITYZONE us-east-1b available us-east-1  
AVAILABILITYZONE us-east-1c available us-east-1  
AVAILABILITYZONE us-east-1d available us-east-1
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeAvailabilityZones](#)

Related Commands

- [ec2-describe-regions](#) (p. 363)
- [ec2-run-instances](#) (p. 633)

ec2-describe-bundle-tasks

Description

Describes one or more of your bundling tasks.

Note

Completed bundle tasks are listed for only a limited time. If your bundle task is no longer in the list, you can still register an AMI from it. Just use the `ec2-register` command with the Amazon S3 bucket name and image manifest name you provided to the bundle task.

The short version of this command is **ec2dbun**.

Syntax

```
ec2-describe-bundle-tasks [bundle ...] [--filter "name=value"] ...]
```

Options

Name	Description
<i>bundle</i>	The IDs of one or more bundle tasks. Type: String Default: Describes all your bundle tasks. Required: No Example: bun-cla432a3
<code>-F, --filter <i>name=value</i></code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space (" <i>name=value example</i> "). On a Windows system, use quotation marks even without a space in the value string (" <i>name=value</i> "). Type: String Default: Describes all your bundle tasks, or only those you specified by ID. Required: No Example: <code>--filter "state=pending"</code>

Supported Filters

You can specify filters so that the response includes information for only certain bundle tasks. For example, you can use a filter to specify that you're interested in the bundle tasks in the `complete` state. You can specify multiple values for a filter. The response includes information for a bundle task only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify bundles that are stored in a specific Amazon S3 bucket and are in the `complete` state. The response includes information for a bundle task only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

bundle-id

The ID of the bundle task.

Type: String

error-code

If the task failed, the error code returned.

Type: String

error-message

If the task failed, the error message returned.

Type: String

instance-id

The ID of the instance that was bundled.

Type: String

progress

The level of task completion, as a percentage (for example, 20%).

Type: String

s3-bucket

The Amazon S3 bucket to store the AMI.

Type: String

s3-prefix

The beginning of the AMI name.

Type: String

start-time

The time the task started (for example, 2008-09-15T17:15:20.000Z).

Type: DateTime

state

The state of the task.

Type: String

Valid values: `pending` | `waiting-for-shutdown` | `bundling` | `storing` | `cancelling` | `complete` | `failed`

update-time

The time of the most recent update for the task (for example, 2008-09-15T17:15:20.000Z).

Type: DateTime

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>

**Amazon Elastic Compute Cloud CLI Reference
Common Options**

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The BUNDLE identifier
- The ID of the bundle
- The ID of the instance
- The bucket name
- The prefix
- The start time
- The update time
- The current state (pending, waiting-for-shutdown, bundling, storing, cancelling, complete, failed)
- The progress as a % if state is bundling

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example describes the status of the `bun-c1a540a8` bundle task.

```
PROMPT> ec2-describe-bundle-tasks bun-c1a540a8
BUNDLE bun-c1a540a8 i-2674d22r myawsbucket winami 2008-09-15T17:15:20.000Z
2008-09-15T17:15:20.000Z bundling 3%
```

Example Request

This example filters the response to include only bundle tasks whose state is either `complete` or `failed`, and in addition are targeted for the Amazon S3 bucket called `myawsbucket`.

```
PROMPT> ec2-describe-bundle-tasks --filter "s3-bucket=myawsbucket" --filter
"state=complete" --filter "state=failed"
BUNDLE bun-1a2b3c4d i-8765abcd myawsbucket linuxami 2008-09-14T08:32:43.000Z
2008-09-14T08:32:43.000Z complete
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeBundleTasks](#)

Related Commands

- [ec2-bundle-instance](#) (p. 56)
- [ec2-cancel-bundle-task](#) (p. 61)

ec2-describe-conversion-tasks

Description

Describes one or more of your conversion tasks. For more information, see [Using the Command Line Tools to Import Your Virtual Machine to Amazon EC2](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2dct**.

Syntax

```
ec2-describe-conversion-tasks [task_id ...] [--show-transfer-details]
```

Options

Name	Description
<i>task_id</i>	The IDs of one or more conversion tasks for the upload. Type: String Default: Describes all your conversion tasks. Required: No Example: import-i-ffvko9js
--show-transfer-details	Any additional details for uploading the disk image. The <code>ec2-upload-disk-image</code> command automatically returns this information. Type: None Default: None Required: No Example: --show-transfer-details

Common Options

Option	Description
--region <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: --region eu-west-1
-U, --url <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: -U https://ec2.amazonaws.com

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns the following information:

- Information about the task, such as the task ID, task type, expiration, status, and number of bytes received
- Information about the image, such as the image size, format, volume ID, and volume size

Amazon EC2 command line tools display errors on stderr.

Example

Example Request

This example shows the status of your import instance task.

```
PROMPT>ec2-describe-conversion-tasks import-i-ffvko9js
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeConversionTasks](#)

Related Commands

- [ec2-cancel-conversion-task](#) (p. 64)
- [ec2-delete-disk-image](#) (p. 189)
- [ec2-import-instance](#) (p. 507)
- [ec2-import-volume](#) (p. 518)

- [ec2-resume-import](#) (p. 622)

ec2-describe-customer-gateways

Description

Describes one or more of your customer gateways.

For more information about VPN customer gateways, see [Adding a Hardware Virtual Private Gateway to Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2dcgw**.

Syntax

```
ec2-describe-customer-gateways [ customer_gateway_id ... ] [--filter "name=value"] ...]
```

Options

Name	Description
<i>customer_gateway_id</i>	One or more customer gateway IDs. Type: String Default: Describes all your customer gateways. Required: No Example: cgw-b4dc3961
-F, --filter name=value	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value string ("name=value"). Type: String Default: Describes all your customer gateways, or only those you specified by ID. Required: No Example: --filter "tag-key=Production"

Supported Filters

You can specify filters so that the response includes information for only certain customer gateways. For example, you can use a filter to specify that you're interested in customer gateways in the `pending` or `available` state. You can specify multiple values for a filter. The response includes information for a customer gateway only if it matches at least one of the of the filter values that you specified.

You can specify multiple filters; for example, specify customer gateways that have a specific IP address for the Internet-routable external interface and are in the `pending` or `available` state. The response includes information for a customer gateway only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?`.

The following are the available filters.

bgp-asn

The customer gateway's Border Gateway Protocol (BGP) Autonomous System Number (ASN).

Type: String

customer-gateway-id

The ID of the customer gateway.

Type: String

ip-address

The IP address of the customer gateway's Internet-routable external interface (for example, 12.1.1.2.3).

Type: String

state

The state of the customer gateway.

Type: String

Valid values: pending | available | deleting | deleted

type

The type of customer gateway. Currently the only supported type is `ipsec.1`.

Type: String

Valid values: ipsec.1

tag-key

The key of a tag assigned to the resource. This filter is independent of the `tag-value` filter. For example, if you use both the filter `tag-key=Purpose` and the filter `tag-value=X`, you get any resources assigned both the tag key `Purpose` (regardless of what the tag's value is), and the tag value `X` (regardless of what the tag's key is). If you want to list only resources where `Purpose` is `X`, see the `tag:key` filter.

For more information about tags, see [Tagging Your Resources](#) in the *Amazon Elastic Compute Cloud User Guide*.

Type: String

tag-value

The value of a tag assigned to the resource. This filter is independent of the `tag-key` filter.

Type: String

tag:key

Filters the response based on a specific tag/value combination.

Example: To list just the resources that have been assigned tag `Purpose=X`, specify:

```
--filter tag:Purpose=X
```

Example: To list just resources that have been assigned tag `Purpose=X` OR `Purpose=Y`, specify:

```
--filter tag:Purpose=X --filter tag:Purpose=Y
```

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the EC2_PRIVATE_KEY environment variable. Example: -K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the EC2_CERT environment variable. Example: -C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem

Output

This command returns a table that contains the following information:

- The CUSTOMERGATEWAY identifier
- The ID of the customer gateway
- The state of the customer gateway (pending, available, deleting, deleted)
- The type of VPN connection the customer gateway supports
- The Internet-routable IP address of the customer gateway's outside interface
- The customer gateway's Border Gateway Protocol (BGP) Autonomous System Number (ASN)
- Any tags assigned to the customer gateway

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example gives a description of the customer gateway with ID cgw-b4dc3961.

```
PROMPT> ec2-describe-customer-gateways cgw-b4dc3961
CUSTOMERGATEWAY cgw-b4dc3961 available ipsec.1 12.1.2.3 65534
```

Example Request

This example uses filters to give a description of any customer gateway you own whose IP address is 12.1.2.3, and whose state is either pending or available.

```
PROMPT> ec2-describe-customer-gateways --filter "ip-address=12.1.2.3" --filter  
"state=pending" --filter "state=available"  
CUSTOMERGATEWAY cgw-b4dc3961 available ipsec.1 12.1.2.3 65534
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeCustomerGateways](#)

Related Commands

- [ec2-create-customer-gateway](#) (p. 89)
- [ec2-delete-customer-gateway](#) (p. 183)

ec2-describe-dhcp-options

Description

Describes one or more of your sets of DHCP options.

For more information about DHCP options sets, see [Using DHCP Options with Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2ddopt**.

Syntax

```
ec2-describe-dhcp-options [ dhcp_options_id ... ] [--filter "name=value"] ...]
```

Options

Name	Description
<i>dhcp_options_id</i>	The IDs of one or more sets of DHCP options. Type: String Default: Describes all your sets of DHCP options. Required: No Example: dopt-7a8b9c2d
-F, --filter <i>name=value</i>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space (" <i>name=value example</i> "). On a Windows system, use quotation marks even without a space in the value string (" <i>name=value</i> "). Type: String Default: Describes all your DHCP options. Required: No Example: --filter "tag-key=Production"

Supported Filters

You can specify filters so that the response includes information for only certain sets of DHCP options. For example, you can use a filter to specify that you're interested in sets of DHCP options with a particular value for the `domain-name` option. You can specify multiple values for a filter. The response includes information for a set of DHCP options only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify sets of DHCP options that have a specific value for the `domain-name` option and a specific tag. The response includes information for a set of DHCP options only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

dhcp-options-id

The ID of a set of DHCP options.

Type: String

key

The key for one of the options (for example, domain-name).

Type: String

value

The value for one of the options.

Type: String

tag-key

The key of a tag assigned to the resource. This filter is independent of the tag-value filter. For example, if you use both the filter "tag-key=Purpose" and the filter "tag-value=X", you get any resources assigned both the tag key Purpose (regardless of what the tag's value is), and the tag value X (regardless of what the tag's key is). If you want to list only resources where Purpose is X, see the tag:key filter.

For more information about tags, see [Tagging Your Resources](#) in the *Amazon Elastic Compute Cloud User Guide*.

Type: String

tag-value

The value of a tag assigned to the resource. This filter is independent of the tag-key filter.

Type: String

tag:key

Filters the response based on a specific tag/value combination.

Example: To list just the resources that have been assigned tag Purpose=X, specify:

```
--filter tag:Purpose=X
```

Example: To list just resources that have been assigned tag Purpose=X OR Purpose=Y, specify:

```
--filter tag:Purpose=X --filter tag:Purpose=Y
```

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the EC2_URL environment variable and the URL specified by the -U option. Default: The value of the EC2_URL environment variable, or us-east-1 if EC2_URL isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the EC2_URL environment variable, or https://ec2.amazonaws.com if EC2_URL isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The DHCPOPTIONS identifier
- The ID of the DHCP options set
- The name and values for each option in the set
- Any tags assigned to the set

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example gives a description of the DHCP options set with ID `dopt-7a8b9c2d`.

```
PROMPT> ec2-describe-dhcp-options dopt-7a8b9c2d
DHCPOPTIONS dopt-7a8b9c2d
OPTION domain-name mydomain.com
OPTION domain-name-servers 10.2.5.1,10.2.5.2
```

Example Request

This example uses filters to give a description of any DHCP options set that includes a `domain-name` option whose value includes the string `example`.

```
PROMPT> ec2-describe-dhcp-options --filter "key=domain-name" --filter
"value=*example*"
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeDhcpOptions](#)

Related Commands

- [ec2-associate-dhcp-options](#) (p. 25)
- [ec2-create-dhcp-options](#) (p. 93)
- [ec2-delete-dhcp-options](#) (p. 186)

ec2-describe-export-tasks

Description

Describes one or more of your export tasks, including the most recent canceled and completed tasks.

The short version of this command is **ec2dxt**.

Syntax

```
ec2-describe-export-tasks [ task_id ... ]
```

Options

Name	Description
<i>task_id</i>	One or more export task IDs. These are returned by <code>ec2-create-instance-export-task</code> . Type: String Default: Describes all your export tasks. Required: No

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key</code> <code>AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> <code>TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <code>TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <code>TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <code>EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns information about the export task including:

- The EXPORTTASK identifier
- The ID of the task
- The status of the task
- The export progress

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example describes the export task with the ID `export-i-fgelt0i7`.

```
PROMPT> ec2-describe-export-tasks export-i-fgelt0i7  
EXPORTTASK    export-i-fgelt0i7    active    i-81428ee7    vmware    vmdk  
myexportbucket    export-i-fgelt0i7.vmdk
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeExportTasks](#)

Related Commands

- [ec2-cancel-export-task](#) (p. 68)
- [ec2-create-instance-export-task](#) (p. 107)

ec2-describe-group

Description

Describes one or more of your security groups.

A security group is for use with instances either in the EC2-Classical platform or in a specific VPC. For more information, see [Amazon EC2 Security Groups](#) in the *Amazon Elastic Compute Cloud User Guide* and [Security Groups for Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2dgrp**.

Syntax

```
ec2-describe-group [ec2_group_name_or_id | vpc_group_id ...] [--filter "name=value"] ...]
```

Options

Name	Description
<i>ec2_group_name_or_id</i> or <i>vpc_group_id</i>	EC2-Classical, default VPC: The name or ID of one or more security groups. nondefault VPC: The ID of one more security groups. Type: String Default: Describes all your security groups, or only those you specified by name. Required: No Example: webserv
-F, --filter <i>name=value</i>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value string ("name=value"). Type: String Default: Describes all your security groups, or only those you specified by ID. Required: No Example: --filter "group-name=*webserver*"

Supported Filters

You can specify filters so that the response includes information for only certain security groups. For example, you can use a filter to specify that you're interested in groups whose name contains a specific string. You can specify multiple values for a filter. The response includes information for a security group only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify group's whose name contains a specific string, and that give permission to another security group with a different string in its name. The response includes

information for a group only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

Important

Filters are based on literal strings only. This is important to remember when you want to use filters to return only security groups with access allowed on a specific port number or numbers. For example, suppose that you want to get all groups that have access on port 22, and that GroupA gives access on a range of ports using `fromPort=20` and `toPort=30`. If you filter with `ip-permission.from-port=22` or `ip-permission.to-port=22` (or both), the response does not contain information for GroupA. You get information for GroupA only if you specify `ip-permission.from-port=20` or `ip-permission.to-port=30` (or both).

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

description

The description of the security group.

Type: String

group-id

The ID of the security group.

Type: String

group-name

The name of the security group.

Type: String

ip-permission.cidr

The CIDR range that has been granted the permission.

Type: String

ip-permission.from-port

The start of port range for the TCP and UDP protocols, or an ICMP type number.

Type: String

ip-permission.group-name

The name of security group that has been granted the permission.

Type: String

ip-permission.protocol

The IP protocol for the permission.

Type: String

Valid values: `tcp` | `udp` | `icmp` or a protocol number

ip-permission.to-port

The end of port range for the TCP and UDP protocols, or an ICMP code.

Type: String

ip-permission.user-id

The ID of an AWS account that has been granted the permission.

Type: String

owner-id

The AWS account ID of the owner of the security group.

Type: String

tag-key

The key of a tag assigned to the security group.

Type: String

tag-value

The value of a tag assigned to the security group.

Type: String

vpc-id

Only return the security groups that belong to the specified EC2-VPC ID.

Type: String

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>

Option	Description
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

A line containing the group information

- The GROUP identifier
- The ID of the security group
- The AWS account ID of the owner of the security group
- The name of the security group
- A description of the security group

- [VPC only] The ID of the VPC the group belongs to

One of each of the following lines for each permission defined by the group:

- The PERMISSION identifier
- The AWS account ID of the owner of the group
- The name of the group granting permission
- The type of rule. Currently, only `ALLOWS` rules are supported
- The protocol to allow (for example, `tcp`, `udp`, etc)
- The start of port range
- The end of port range
- `FROM` for an ingress rule or `TO` for an egress rule
- The source type (for ingress rules) or destination type (for egress rules)
- The source (for ingress rules) or destination (for egress rules)
- [USER only] The name of the source or destination entity
- [USER only] The group ID
- Whether the rule is ingress rule or an egress rule

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example returns information about a security group for EC2-Classic named `StandardGroup`.

```
PROMPT> ec2-describe-group StandardGroup
GROUP sg-1a2b3c4d 111122223333 StandardGroup A standard EC2 group
PERMISSION 111122223333 StandardGroup ALLOWS tcp 80 80 FROM CIDR 102.11.43.32/32
  ingress
```

Example Request

This example returns information about a security group for EC2-VPC with the ID `sg-1a2b3c4d`.

```
PROMPT> ec2-describe-group sg-1a2b3c4d
GROUP sg-1a2b3c4d 111122223333 WebServerSG web servers vpc-1a2b3c4d
PERMISSION 111122223333 WebServerSG ALLOWS tcp 80 80 FROM CIDR 162.5.5.5/32
  ingress
PERMISSION 111122223333 WebServerSG ALLOWS tcp 80 80 FROM USER 111122223333
  NAME default ID sg-1a2b3c4d ingress
PERMISSION 111122223333 WebServerSG ALLOWS tcp 443 443 FROM USER 111122223333
  NAME default ID sg-1a2b3c4d ingress
PERMISSION 111122223333 WebServerSG ALLOWS all TO CIDR 0.0.0.0/0 egress
PERMISSION 111122223333 WebServerSG ALLOWS tcp 433 433 TO USER 111122223333
  NAME default ID sg-1a2b3c4d egress
```

Example Request

This example returns information about all security groups that grant access over TCP specifically on port 22 from instances in either the `app_server_group` or `database_group`.

```
PROMPT> ec2-describe-group --filter "ip-permission.protocol=tcp"  
--filter "ip-permission.from-port=22" --filter "ip-permission.to-port=22"  
--filter "ip-permission.group-name=app_server_group" --filter "ip-permission.group-name=database_group"
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeSecurityGroups](#)

Related Commands

- [ec2-authorize](#) (p. 49)
- [ec2-create-group](#) (p. 97)
- [ec2-delete-group](#) (p. 192)
- [ec2-revoke](#) (p. 627)

ec2-describe-image-attribute

Description

Describes the specified attribute of an AMI. You can specify only one attribute at a time.

The short version of this command is **ec2dimatt**.

Syntax

```
ec2-describe-image-attribute ami_id {-l | -p | -B | --kernel | --ramdisk}
```

Options

Name	Description
<i>ami_id</i>	The ID of the AMI. Type: String Default: None Required: Yes Example: ami-4fa54026
-l, --launch-permission	The launch permissions of the AMI. Type: String Default: None Required: No Example: -l
-p, --product-code	The product codes associated with the AMI. Each product code contains both a product code and a type. Type: String Default: None Required: No Example: -p
-B, --block-device-mapping	The block device mapping associated with the AMI. Type: String Default: None Required: No Example: -B
--kernel	The ID of the kernel associated with the AMI. Type: String Default: None Required: No Example: --kernel

Name	Description
<code>--ramdisk</code>	<p>The ID of the RAM disk associated with the AMI.</p> <p>Important We recommend that you use PV-GRUB instead of kernels and RAM disks. For more information, see PV-GRUB: A New Amazon Kernel Image in the <i>Amazon Elastic Compute Cloud User Guide</i>.</p> <p>Type: String Default: None Required: No Example: <code>--ramdisk</code></p>

Common Options

Option	Description
<code>--region REGION</code>	<p>Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option.</p> <p>Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set.</p> <p>Example: <code>--region eu-west-1</code></p>
<code>-U, --url URL</code>	<p>The uniform resource locator (URL) of the Amazon EC2 web service entry point.</p> <p>Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set.</p> <p>Example: <code>-U https://ec2.amazonaws.com</code></p>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>

Option	Description
<code>--connection-timeout</code> <i>TIMEOUT</i>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The attribute type identifier

- The ID of the AMI
- Information about the attribute

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example lists the launch permissions for the `ami-1a2b3c4d` AMI

```
PROMPT> ec2-describe-image-attribute ami-1a2b3c4d -l
launchPermission ami-1a2b3c4d group all
launchPermission ami-1a2b3c4d userId 111122223333
```

Example Request

This example lists the product code for the `ami-1a2b3c4d` AMI.

```
PROMPT> ec2-describe-image-attribute ami-1a2b3c4d -p
productCodes ami-1a2b3c4d productCode [marketplace: a1b2c3d4e5f6g7h8i9j10k11]
```

Example Request

This example describes the RAM disk for the `ami-1a2b3c4d` AMI, with the `--show-empty-fields` option.

```
PROMPT> ec2-describe-image-attribute ami-1a2b3c4d --ramdisk --show-empty-fields
ramdisk ami-1a2b3c4d (nil) ari-96c527ff
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeImageAttribute](#)

Related Commands

- [ec2-describe-images](#) (p. 299)
- [ec2-modify-image-attribute](#) (p. 530)
- [ec2-reset-image-attribute](#) (p. 608)

ec2-describe-images

Description

Describes one or more of the images available to you (AMIs, AKIs, and ARIs). Images available to you include public images, private images that you own, and private images owned by other AWS accounts but for which you have explicit launch permissions.

Launch permissions fall into three categories.

Launch Permission	Description
public	The owner of the AMI granted launch permissions for the AMI to the <code>all</code> group. All AWS accounts have launch permissions for these AMIs.
explicit	The owner of the AMI granted launch permissions to a specific AWS account.
implicit	An AWS account has implicit launch permissions for all the AMIs it owns.

The list of AMIs returned can be modified by specifying AMI IDs, AMI owners, or AWS accounts with launch permissions. If no options are specified, Amazon EC2 returns all AMIs for which you have launch permissions.

If you specify one or more AMI IDs, only AMIs that have the specified IDs are returned. If you specify an invalid AMI ID, an error is returned. If you specify an AMI ID for which you do not have access, it is not included in the returned results.

If you specify one or more AMI owners, only AMIs from the specified owners and to which you have access are returned. The results can include the account IDs of the specified owners—`amazon` for AMIs owned by Amazon, `aws-marketplace` for AMIs owned by AWS Marketplace, or `self` for AMIs that you own.

Note

For an overview of the AWS Marketplace, see <https://aws.amazon.com/marketplace/help/200900000>. For details on how to use the AWS Marketplace, see [AWS Marketplace](#).

If you specify a list of users with launch permissions, only AMIs with launch permissions for those users are returned. You can specify account IDs (if you own the AMIs), `self` for AMIs for which you own or have explicit permissions, or `all` for public AMIs.

Note

Deregistered images are included in the returned results for an unspecified interval after deregistration.

The short version of this command is `ec2dim`.

Syntax

```
ec2-describe-images [ami_id ...] [-a] [-o owner ...] [-x user_id ...] [--filter "name=value"] ...]
```


Options

Name	Description
<code>ami_id</code>	One or more AMI IDs. Type: String Default: Describes all AMIs available to you. Required: No Example: <code>ami-78a54011</code>
<code>-a, --all</code>	Describes all AMIs available to you. Type: String Default: None Required: No Example: <code>-a</code>
<code>-o, --owner owner</code>	Describes AMIs owned by the specified owner. You can specify multiple owner options. Use the IDs <code>amazon</code> , <code>aws-marketplace</code> , and <code>self</code> to include AMIs owned by Amazon, AMIs owned by AWS Marketplace, or AMIs owned by you, respectively. Type: String Default: None Valid values: <code>amazon</code> <code>aws-marketplace</code> <code>self</code> AWS account ID <code>all</code> Required: No Example: <code>-o self</code>
<code>-x, --executable-by user_id</code>	Describes AMIs for which the specified user ID has explicit launch permissions. The user ID can be an AWS account ID, <code>self</code> to return AMIs for which the sender of the request has explicit launch permissions, or <code>all</code> to return AMIs with public launch permissions. Type: String Default: None Valid values: <code>all</code> <code>self</code> AWS account ID Required: No Example: <code>-x self</code>
<code>-F, --filter name=value</code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space (" <code>name=value example</code> "). On a Windows system, use quotation marks even without a space in the value string (" <code>name=value</code> "). Type: String Default: Describes all AMIs available to you, or only those you specified. Required: No Example: <code>--filter "tag-value=Production"</code>

Supported Filters

You can specify filters so that the response includes information for only certain images. For example, you can use a filter to specify that you're interested in images that use a specific kernel. You can specify multiple values for a filter. The response includes information for an image only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify images that use a specific kernel and use an Amazon EBS volume as the root device. The response includes information for an image only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

architecture

The image architecture.

Type: String

Valid values: `i386` | `x86_64`

block-device-mapping.delete-on-termination

Whether the Amazon EBS volume is deleted on instance termination.

Type: Boolean

block-device-mapping.device-name

The device name (for example, `/dev/sdh`) for the Amazon EBS volume.

Type: String

block-device-mapping.snapshot-id

The ID of the snapshot used for the Amazon EBS volume.

Type: String

block-device-mapping.volume-size

The volume size of the Amazon EBS volume, in GiB.

Type: Integer

block-device-mapping.volume-type

The volume type of the Amazon EBS volume.

Type: String

Valid values: `standard` | `io1`

description

The description of the image (provided during image creation).

Type: String

image-id

The ID of the image.

Type: String

image-type

The image type.

Type: String

Valid values: `machine` | `kernel` | `ramdisk`

is-public

Whether the image is public.

Type: Boolean

- kernel-id**
The kernel ID.
Type: String
- manifest-location**
The location of the image manifest.
Type: String
- name**
The name of the AMI (provided during image creation).
Type: String
- owner-alias**
The AWS account alias (for example, `amazon`).
Type: String
- owner-id**
The AWS account ID of the image owner.
Type: String
- platform**
The platform. To only list Windows-based AMIs, use `windows`. Otherwise, leave blank.
Type: String
Valid value: `windows`
- product-code**
The product code.
Type: String
- product-code.type**
The type of the product code.
Type: String
Valid values: `devpay` | `marketplace`
- ramdisk-id**
The RAM disk ID.
Type: String
- root-device-name**
The name of the root device volume (for example, `/dev/sda1`).
Type: String
- root-device-type**
The type of the root device volume.
Type: String
Valid values: `ebs` | `instance-store`
- state**
The state of the image.
Type: String
Valid values: `available` | `pending` | `failed`
- state-reason-code**
The reason code for the state change.
Type: String
- state-reason-message**
The message for the state change.
Type: String
- tag-key**
The key of a tag assigned to the resource. This filter is independent of the `tag-value` filter. For example, if you use both the filter `tag-key=Purpose` and the filter `tag-value=X`, you get any

resources assigned both the tag key `Purpose` (regardless of what the tag's value is), and the tag value `X` (regardless of what the tag's key is). If you want to list only resources where Purpose is `X`, see the `tag:key` filter.

For more information about tags, see [Tagging Your Resources](#) in the *Amazon Elastic Compute Cloud User Guide*.

Type: String

tag-value

The value of a tag assigned to the resource. This filter is independent of the `tag-key` filter.

Type: String

tag:key

Filters the response based on a specific tag/value combination.

Example: To list just the resources that have been assigned tag Purpose=`X`, specify:

```
--filter tag:Purpose=X
```

Example: To list just resources that have been assigned tag Purpose=`X` OR Purpose=`Y`, specify:

```
--filter tag:Purpose=X --filter tag:Purpose=Y
```

virtualization-type

The virtualization type.

Type: String

Valid values: `paravirtual` | `hvm`

hypervisor

The hypervisor type.

Type: String

Valid values: `ovm` | `xen`

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key</code> <i>AWS_SECRET_KEY</i>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> TOKEN <i>AWS_DELEGATION_TOKEN</i>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <i>TIMEOUT</i>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following rows of information for each image. Each field is separated by a comma. Some of these values may be empty.

1. The image information

- The IMAGE identifier
- The ID of the image
- The source of the image
- The ID of the image owner
- The status of the image
- The visibility of the image (`public` or `private`)
- The product codes, if any, that are attached to the instance
- The architecture of the image (`i386` or `x86_64`)
- The image type (`machine`, `kernel`, or `ramdisk`)
- The ID of the kernel associated with the image (machine images only)
- The ID of the RAM disk associated with the image (machine images only)

Important

This applies only to legacy AKIs; we recommend that you use PV-GRUB instead of kernels and RAM disks. For more information, see [PV-GRUB: A New Amazon Kernel Image](#) in the *Amazon Elastic Compute Cloud User Guide*.

- The platform of the image
 - The type of root device (`ebs` or `instance-store`)
 - The virtualization type (`paravirtual` or `hvm`)
 - The Hypervisor type (`xen` or `ovm`)
- ### 2. Any Amazon EBS volumes associated with the instance. There will be one of the following for each volume
- The BLOCKDEVICE identifier
 - The device name
 - The snapshot ID
 - The volume size
 - Whether or not the volume will be deleted on termination (`true` or `false`)
 - The volume type
 - The maximum IOPS of the volume
- ### 3. Any tags associated with the instance. There will be one of the following for each tag
- The TAG identifier
 - The resource type identifier
 - The resource ID
 - The tag key
 - The tag value

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example describes the ami-1a2b3c4d AMI.

```
PROMPT> ec2-describe-images ami-1a2b3c4d

IMAGE ami-1a2b3c4d amazon/getting-started-with-ebs-boot amazon available public
        i386 machine aki-a13667e4 ari-a33667e6 ebs paravirtual xen
BLOCKDEVICEMAPPING /dev/sda1 snap-1a2b3c4d 15 standard
```

Example Request

This example filters the response to include only the public Windows images with an x86_64 architecture.

```
PROMPT> ec2-describe-images --filter "is-public=true" --filter "architec
ture=x86_64" --filter "platform=windows"

IMAGE   ami-1a2b3c4d   amazon/getting-started-with-ebs-boot amazon available
public  x86_64 machine   windows ebs hvm xen
IMAGE   ami-2a2b3c4d   amazon/SqlSvrStd2003r2-x86_64-Win-v1.07 amazon available
public  x86_64 machine   windows instance-store hvm xen
...
```

Example Request

This example filters the results to display only images with an AWS Marketplace product code.

```
PROMPT> ec2-describe-images -F product-code.type=marketplace -o self

IMAGE ami-1a2b3c4d 111122223333/My MP Image 111122223333 available private
[marketplace: a1b2c3d4e5f6g7h8i9j10k11] i386 machine   ebs paravirtual xen
BLOCKDEVICEMAPPING /dev/sda1 snap-2de0d457 15 standard
BLOCKDEVICEMAPPING /dev/sdb snap-27e0d45d 100 standard
...
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeImages](#)

Related Commands

- [ec2-describe-image-attribute](#) (p. 295)
- [ec2-describe-instances](#) (p. 320)

ec2-describe-instance-attribute

Description

Describes the specified attribute of the specified instance. You can specify only one attribute at a time.

The short version of this command is **ec2dinatt**.

Syntax

```
ec2-describe-instance-attribute instance_id { --block-device-mapping |
--ebs-optimized | --disable-api-termination | --group-id |
--instance-initiated-shutdown-behavior | --instance-type | --kernel |
--product-code | --ramdisk | --root-device-name | --source-dest-check |
--user-data }
```

Options

Name	Description
<i>instance_id</i>	The instance ID. Type: String Required: Yes Example: i-43a4412a
-b, --block-device-mapping	The block device mapping for the instance. Type: String Required: No Example: -b
--disable-api-termination	Whether the instance can be terminated using the EC2 API. A value of <code>true</code> means you can't terminate the instance using the API (the instance is "locked"). A value of <code>false</code> means you can terminate the instance using the API (the instance is "unlocked"). Set this attribute to <code>true</code> to prevent the instance from being terminated using the EC2 API. Type: Boolean Required: No Example: --disable-api-termination
--ebs-optimized <i>Boolean</i>	Whether the instance is optimized for EBS I/O. This optimization provides dedicated throughput to Amazon EBS and an optimized configuration stack to provide optimal EBS I/O performance. This option isn't available on all instance types. Additional usage charge apply when using this option. Type: Boolean Required: No Example: --ebs-optimized

Amazon Elastic Compute Cloud CLI Reference

Options

Name	Description
<code>-g, --group-id</code>	The security groups the instance is in. Type: String Required: No Example: <code>-g</code>
<code>-p, --product-code</code>	The product codes associated with an instance. Each product code includes a product code and type. Type: String Required: No Example: <code>-p</code>
<code>--instance-initiated-shutdown-behavior</code>	Whether an instance stops or terminates when shutdown is initiated. Type: String Required: No Example: <code>--instance-initiated-shutdown-behavior</code>
<code>-t, --instance-type</code>	The instance type of the instance. See Available Instance Types for more information. Type: String Required: No Example: <code>-t</code>
<code>--kernel</code>	The ID of the kernel associated with the AMI. Type: String Required: No Example: <code>--kernel</code>
<code>--ramdisk</code>	The ID of the RAM disk associated with the AMI. Important We recommend that you use PV-GRUB instead of kernels and RAM disks. For more information, see PV-GRUB: A New Amazon Kernel Image in the <i>Amazon Elastic Compute Cloud User Guide</i> . Type: String Required: No Example: <code>--ramdisk</code>
<code>--root-device-name</code>	The name of the root device (for example, <code>/dev/sda1</code>). Type: String Required: No Example: <code>--root-device-name</code>

Name	Description
<code>--source-dest-check</code>	Enables an instance in a VPC to perform NAT. The attribute controls whether source/destination checking is enabled on the instance. A value of <code>true</code> means checking is enabled, and <code>false</code> means checking is disabled. The value must be <code>false</code> for the instance to perform NAT. For more information, see NAT Instances in the <i>Amazon Virtual Private Cloud User Guide</i> . Type: String Required: No Example: <code>--source-dest-check</code>
<code>--user-data</code>	Any user data made available to the instance. Type: String Required: No Example: <code>--user-data</code>

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
-T, --security-token TOKEN AWS_DELEGATION_TOKEN	The AWS delegation token. Default: The value of the environment variable (if set).
--connection-timeout TIMEOUT	The connection timeout, in seconds. Example: --connection-timeout 30
--request-timeout TIMEOUT	The request timeout, in seconds. Example: --request-timeout 45
-v, --verbose	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
-H, --headers	Includes column headers in the command output.
--show-empty-fields	Shows empty columns as (nil).
--hide-tags	Omits tags for tagged resources.
--debug	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
-?, --help, -h	Displays usage information for the command.
-	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key EC2-PRIVATE-KEY	The private key to use when constructing requests to Amazon EC2. Default: The value of the EC2_PRIVATE_KEY environment variable. Example: -K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem
-C, --cert EC2-CERT	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the EC2_CERT environment variable. Example: -C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem

Output

This command returns a table that contains the following information:

- If the `--block-device-mapping` attribute is requested, one of the following for each Amazon EBS volume:
 - The BLOCKDEVICE identifier,
 - The device name
 - The volume ID
 - The timestamp
- For all other attributes:
 - The attribute type identifier
 - The ID of the instance
 - The attribute or attribute list item value

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example lists the kernel ID of the i-10a64379 instance.

```
PROMPT> ec2-describe-instance-attribute i-10a64379 --kernel  
kernel i-10a64379 aki-f70657b2
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeInstanceAttribute](#)

Related Commands

- [ec2-describe-instances](#) (p. 320)
- [ec2-modify-instance-attribute](#) (p. 535)
- [ec2-reset-instance-attribute](#) (p. 611)

ec2-describe-instance-status

Description

Describes the status of an instance. Instance status has two main components:

- System Status reports impaired functionality that stems from issues related to the systems that support an instance, such as hardware failures and network connectivity problems. The `DescribeInstanceStatus` response elements report such problems as impaired reachability.
- Instance Status reports impaired functionality that arises from problems internal to the instance. The `DescribeInstanceStatus` response elements report such problems as impaired reachability.

Instance status provides information about four types of scheduled events for an instance that may require your attention:

- Scheduled Reboot: When Amazon EC2 determines that an instance must be rebooted, the instances status will return one of two event codes: `system-reboot` or `instance-reboot`. System reboot commonly occurs if certain maintenance or upgrade operations require a reboot of the underlying host that supports an instance. Instance reboot commonly occurs if the instance must be rebooted, rather than the underlying host. Rebooting events include a scheduled start and end time.
- System Maintenance: When Amazon EC2 determines that an instance requires maintenance that requires power or network impact, the instance's status will return an event code called `system-maintenance`. System maintenance is either power maintenance or network maintenance. For power maintenance, your instance will be unavailable for a brief period of time and then rebooted. For network maintenance, your instance will experience a brief loss of network connectivity. System maintenance events include a scheduled start and end time. You will also be notified by email if one of your instances is set for system maintenance. The email message indicates when your instance is scheduled for maintenance.
- Scheduled Retirement: When Amazon EC2 determines that an instance must be shut down, the instance's status returns an event code called `instance-retirement`. Retirement commonly occurs when the underlying host is degraded and must be replaced. Retirement events include a scheduled start and end time. You will also be notified by email if one of your instances is set to retiring. The email message indicates when your instance will be permanently retired.
- Scheduled Stop: When Amazon EC2 determines that an instance must be shut down, the instances status returns an event code called `instance-stop`. Stop events include a scheduled start and end time. You will also be notified by email if one of your instances is set to stop. The email message indicates when your instance will be stopped.

When your instance is retired, it will either be terminated (if its root device type is the instance-store) or stopped (if its root device type is an EBS volume). Instances stopped due to retirement will not be restarted, but you can do so manually. You can also avoid retirement of EBS-backed instances by manually restarting your instance when its event code is `instance-retirement`. This ensures that your instance is started on a different underlying host.

The short version of this command is `ec2dins`.

Syntax

```
ec2-describe-instance-status [instance_id ...] [-I, --hide-healthy ...] [-A, --include-all-instances ...] [--filter "name=value" ...]
```

Options

Name	Description
<code>instance_id</code>	One or more instance IDs. Type: String Default: Describes all your instances. Constraints: Maximum 100 explicitly specified instance IDs. Required: No Example: <code>i-15a4417c</code>
<code>-I, --hide-healthy</code>	Hide instances where all status checks pass. Required: No
<code>-A, --include-all-instances</code>	Describes all running and non-running instances. Required: No
<code>-F, --filter name=value</code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value string ("name=value"). Type: String Default: Describes all your instances, or only those you specified by ID. Required: No Example: <code>--filter "system-status.status=impaired"</code>

Supported Filters

You can specify filters so that the response includes information for only certain instances. For example, you can use a filter to specify that you're interested in instances in a specific Availability Zone. You can specify multiple values for a filter. The response includes information for an instance only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify instances that are in a specific Availability Zone and have a status of `retiring`. The response includes information for an instance only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

availability-zone

The Availability Zone of the instance.

Type: String

event.code

The code identifying the type of event.

Type: String

Valid values: `instance-reboot` | `system-reboot` | `system-maintenance` | `instance-retirement` | `instance-stop`

event.description

A description of the event.

Type: String

event.not-after

The latest end time for the scheduled event.

Type: DateTime

event.not-before

The earliest start time for the scheduled event.

Type: DateTime

instance-state-name

The state of the instance.

Type: String

Valid values: `pending` | `running` | `shutting-down` | `terminated` | `stopping` | `stopped`

instance-state-code

A code representing the state of the instance. The high byte is an opaque internal value and should be ignored. The low byte is set based on the state represented

Type: Integer (16-bit unsigned integer)

Valid values: 0 (`pending`) | 16 (`running`) | 32 (`shutting-down`) | 48 (`terminated`) | 64 (`stopping`) | 80 (`stopped`)

system-status.status

The system status of the instance.

Type: String

Valid values: `ok` | `impaired` | `initializing` | `insufficient-data` | `not-applicable`

system-status.reachability

Filters on system status where the name is `reachability`.

Type: String

Valid values: `passed` | `failed` | `initializing` | `insufficient-data`

instance-status.status

The status of the instance.

Type: String

Valid values: `ok` | `impaired` | `initializing` | `insufficient-data` | `not-applicable`

instance-status.reachability

Filters on instance status where the name is `reachability`.

Type: String

Valid values: `passed` | `failed` | `initializing` | `insufficient-data`

Common Options

Option	Description
<code>--region REGION</code>	<p>Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option.</p> <p>Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set.</p> <p>Example: <code>--region eu-west-1</code></p>

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

The instance information

- The INSTANCE identifier
- The ID of the instance
- The availability zone of the instance
- The state name of the instance
- The state code of the instance
- The status of the instance
- The host system status
- The instance retirement status
- The instance retirement date

The host system status information

- The SYSTEMSTATUS identifier
- The host system status name
- The host system status
- The date and time that the host system became impaired, if applicable

The instance status information

- The INSTANCESSYSTEMSTATUS identifier
- The instance status name
- The instance status
- The date and time that the instance became impaired, if applicable

Any events scheduled for the instance

- The EVENT identifier
- The event type
- The date and time of the opening of the event window
- The date and time of the closing of the event window
- The event description

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example describes the current state of the instances owned by your AWS account.

```
ec2-describe-instance-status
```

```
INSTANCE i-1a2b3c4d us-east-1d running 16 ok ok active
SYSTEMSTATUS reachability passed
INSTANCESTATUS reachability passed
INSTANCE i-2a2b3c4d us-east-1d running 16 ok ok active
SYSTEMSTATUS reachability passed
INSTANCESTATUS reachability passed
INSTANCE i-3a2b3c4d us-east-1d running 16 ok ok active
SYSTEMSTATUS reachability passed
INSTANCESTATUS reachability passed
INSTANCE i-4a2b3c4d us-east-1d running 16 ok ok retiring YYYY-MM-DDTHH:MM:SS+0000
SYSTEMSTATUS reachability passed
INSTANCESTATUS reachability passed
EVENT instance-stop YYYY-MM-DDTHH:MM:SS+0000 The instance is running on degraded
hardware
INSTANCE i-5a2b3c4d us-east-1d running 16 ok ok retiring YYYY-MM-DDTHH:MM:SS+0000
SYSTEMSTATUS reachability passed
INSTANCESTATUS reachability passed
EVENT instance-retiring YYYY-MM-DDTHH:MM:SS+0000 The instance is running on
degraded hardware
INSTANCE i-6a2b3c4d us-east-1d running 16 ok ok retiring YYYY-MM-DDTHH:MM:SS+0000
SYSTEMSTATUS reachability passed
INSTANCESTATUS reachability passed
EVENT instance-stop YYYY-MM-DDTHH:MM:SS+0000 The instance is running on degraded
hardware
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeInstanceStatus](#)

Related Commands

- [ec2-report-instance-status](#) (p. 592)

ec2-describe-instances

Description

Describes one or more of your instances.

If you specify one or more instance IDs, Amazon EC2 returns information for those instances. If you do not specify instance IDs, Amazon EC2 returns information for all relevant instances. If you specify an invalid instance ID, an error is returned. If you specify an instance that you do not own, it will not be included in the returned results.

Recently terminated instances might appear in the returned results. This interval is usually less than one hour.

The short version of this command is **ec2din**.

Syntax

```
ec2-describe-instances [instance_id ...] [--filter "name=value"] ...]
```

Options

Name	Description
<i>instance_id</i>	One or more instance IDs. Type: String Default: Describes all your instances. Required: No Example: i-15a4417c
<code>-F, --filter <i>name=value</i></code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space (" <i>name=value example</i> "). On a Windows system, use quotation marks even without a space in the value string (" <i>name=value</i> "). Type: String Default: Describes all your instances, or only those you specified by ID. Required: No Example: <code>--filter "tag-key=Production"</code>

Supported Filters

You can specify filters so that the response includes information for only certain instances. For example, you can use a filter to specify that you're interested in instances launched with a specific key pair. You can specify multiple values for a filter. The response includes information for an instance only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify instances that are launched with a specific key pair and use an Amazon EBS volume as the root device. The response includes information for an instance only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

architecture

The instance architecture.

Type: String

Valid values: `i386` | `x86_64`

availability-zone

The Availability Zone of the instance.

Type: String

block-device-mapping.attach-time

The attach time for an Amazon EBS volume mapped to the instance (for example, 2010-09-15T17:15:20.000Z)

Type: DateTime

block-device-mapping.delete-on-termination

Indicates whether the Amazon EBS volume is deleted on instance termination.

Type: Boolean

block-device-mapping.device-name

The device name (for example, `/dev/sdh`) for the Amazon EBS volume.

Type: String

block-device-mapping.status

The status for the Amazon EBS volume.

Type: String

Valid values: `attaching` | `attached` | `detaching` | `detached`

block-device-mapping.volume-id

The volume ID of the Amazon EBS volume.

Type: String

client-token

The idempotency token you provided when you launched the instance.

Type: String

dns-name

The public DNS name of the instance.

Type: String

group-id

The ID of the security group for the instance. If the instance is in EC2-Classic or a default VPC, you can use `group-name` instead.

Type: String

group-name

The name of the security group for the instance. If the instance is in a nondefault VPC, you must use `group-id` instead.

Type: String

image-id

The ID of the image used to launch the instance.

Type: String

instance-id

The ID of the instance.

Type: String

instance-lifecycle

Indicates whether this is a Spot Instance.

Type: String

Valid values: `spot`

instance-state-code

The state of the instance. The high byte is an opaque internal value and should be ignored. The low byte is set based on the state represented.

Type: Integer (16-bit unsigned integer)

Valid values: 0 (pending) | 16 (running) | 32 (shutting-down) | 48 (terminated) | 64 (stopping) | 80 (stopped)

instance-state-name

The state of the instance.

Type: String

Valid values: `pending` | `running` | `shutting-down` | `terminated` | `stopping` | `stopped`

instance-type

The type of instance (for example, `m1.small`).

Type: String

instance.group-id

The ID of the security group for the instance. If the instance is in EC2-Classic or a default VPC, you can use `instance.group-name` instead.

Type: String

instance.group-name

The name of the security group for the instance. If the instance is in a nondefault VPC, you must use `instance.group-id` instead.

Type: String

ip-address

The public IP address of the instance.

Type: String

kernel-id

The kernel ID.

Type: String

key-name

The name of the key pair used when the instance was launched.

Type: String

launch-index

When launching multiple instances, this is the index for the instance in the launch group (for example, 0, 1, 2, and so on).

Type: String

launch-time

The time the instance was launched (for example, 2010-08-07T11:54:42.000Z).

Type: DateTime

monitoring-state

Indicates whether monitoring is enabled for the instance.

Type: String

Valid values: `disabled` | `enabled`

owner-id

The AWS account ID of the instance owner.

Type: String

placement-group-name

The name of the placement group for the instance.

- Type: String
- platform**
The platform. Use `windows` if you have Windows based instances; otherwise, leave blank.
Type: String
Valid value: `windows`
- private-dns-name**
The private DNS name of the instance.
Type: String
- private-ip-address**
The private IP address of the instance.
Type: String
- product-code**
The product code associated with the AMI used to launch the instance.
Type: String
- product-code.type**
The type of product code.
Type: String
Valid values: `devpay` | `marketplace`
- ramdisk-id**
The RAM disk ID.
Type: String
- reason**
The reason for the current state of the instance (for example, shows "User Initiated [date]" when you stop or terminate the instance). Similar to the state-reason-code filter.
Type: String
- requester-id**
The ID of the entity that launched the instance on your behalf (for example, AWS Management Console, Auto Scaling, and so on)
Type: String
- reservation-id**
The ID of the instance's reservation. A reservation ID is created any time you launch an instance. A reservation ID has a one-to-one relationship with an instance launch request, but can be associated with more than one instance if you launch multiple instances using the same launch request. For example, if you launch one instance, you'll get one reservation ID. If you launch ten instances using the same launch request, you'll also get one reservation ID.
Type: String
- root-device-name**
The name of the root device for the instance (for example, `/dev/sda1`).
Type: String
- root-device-type**
The type of root device the instance uses.
Type: String
Valid values: `ebs` | `instance-store`
- source-dest-check**
Indicates whether the instance performs source/destination checking. A value of `true` means that checking is enabled, and `false` means checking is disabled. The value must be `false` for the instance to perform network address translation (NAT) in your VPC.
Type: Boolean
- spot-instance-request-id**
The ID of the Spot Instance request.

Type: String

state-reason-code

The reason code for the state change.

Type: String

state-reason-message

A message that describes the state change.

Type: String

subnet-id

The ID of the subnet for the instance.

Type: String

tag-key

The key of a tag assigned to the resource. This filter is independent of the `tag-value` filter. For example, if you use both the filter `tag-key=Purpose` and the filter `tag-value=X`, you get any resources assigned both the tag key `Purpose` (regardless of what the tag's value is), and the tag value `X` (regardless of what the tag's key is). If you want to list only resources where `Purpose` is `X`, see the `tag:key` filter.

For more information about tags, see [Tagging Your Resources](#) in the *Amazon Elastic Compute Cloud User Guide*.

Type: String

tag-value

The value of a tag assigned to the resource. This filter is independent of the `tag-key` filter.

Type: String

tag:key

Filters the response based on a specific tag/value combination.

Example: To list just the resources that have been assigned tag `Purpose=X`, specify:

```
--filter tag:Purpose=X
```

Example: To list just resources that have been assigned tag `Purpose=X` OR `Purpose=Y`, specify:

```
--filter tag:Purpose=X --filter tag:Purpose=Y
```

virtualization-type

The virtualization type of the instance.

Type: String

Valid values: `paravirtual` | `hvm`

vpc-id

The ID of the VPC the instance is running in.

Type: String

hypervisor

The hypervisor type of the instance.

Type: String

Valid values: `ovm` | `xen`

network-interface.description

The description of the network interface.

Type: String

network-interface.subnet-id

The ID of the subnet for the network interface.

Type: String

network-interface.vpc-id

The ID of the VPC for the network interface.

Type: String

network-interface.network-interface-id

The ID of the network interface.

- Type: String
- network-interface.owner-id**
The ID of the owner of the network interface.
Type: String
- network-interface.availability-zone**
The availability zone for the network interface.
Type: String
- network-interface.requester-id**
The requester ID for the network interface.
Type: String
- network-interface.requester-managed**
Indicates whether the network interface is being managed by AWS.
Type: Boolean
- network-interface.status**
The status of the network interface.
Type: String
Valid values: available | in-use
- network-interface.mac-address**
The MAC address of the network interface.
Type: String
Valid values: available | in-use
- network-interface-private-dns-name**
The private DNS name of the network interface.
Type: String
- network-interface.source-destination-check**
Whether the network interface performs source/destination checking. A value of `true` means checking is enabled, and `false` means checking is disabled. The value must be `false` for the network interface to perform network address translation (NAT) in your VPC.
Type: Boolean
- network-interface.group-id**
The ID of a security group associated with the network interface.
Type: String
- network-interface.group-name**
The name of a security group associated with the network interface.
Type: String
- network-interface.attachment.attachment-id**
The ID of the interface attachment.
Type: String
- network-interface.attachment.instance-id**
The ID of the instance to which the network interface is attached.
Type: String
- network-interface.attachment.instance-owner-id**
The owner ID of the instance to which the network interface is attached.
Type: String
- network-interface.addresses.private-ip-address**
The private IP address associated with the network interface.
Type: String
- network-interface.attachment.device-index**
The device index to which the network interface is attached.

- Type: Integer
- network-interface.attachment.status**
The status of the attachment.
Type: String
Valid values: attaching | attached | detaching | detached
- network-interface.attachment.attach-time**
The time that the network interface was attached to an instance.
Type: Date
- network-interface.attachment.delete-on-termination**
Specifies whether the attachment is deleted when an instance is terminated.
Type: Boolean
- network-interface.addresses.primary**
Specifies whether the IP address of the network interface is the primary private IP address.
Type: Boolean
- network-interface.addresses.association.public-ip**
The ID of the association of an Elastic IP address with a network interface.
Type: String
- network-interface.addresses.association.ip-owner-id**
The owner ID of the private IP address associated with the network interface.
Type: String
- association.public-ip**
The address of the Elastic IP address bound to the network interface.
Type: String
- association.ip-owner-id**
The owner of the Elastic IP address associated with the network interface.
Type: String
- association.allocation-id**
The allocation ID that AWS returned when you allocated the Elastic IP address for your network interface.
Type: String
- association.association-id**
The association ID returned when the network interface was associated with an IP address.
Type: String

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following rows of information for each instance. Each field is separated by a comma. Some of these values may be empty.

1. The reservation information
 - The RESERVATION identifier
 - The ID of the reservation
 - The AWS account ID of the instance owner
 - The name of each security group the instance is in
2. The instance information
 - The INSTANCE identifier
 - The ID of the instance
 - The AMI ID of the image on which the instance is based
 - The public DNS name associated with the instance. This is only present for instances in the running state.
 - The private DNS name associated with the instance. This is only present for instances in the running state.
 - The state of the instance
 - The key name. If a key was associated with the instance at launch, its name will appear.
 - The AMI launch index
 - The product codes associated with the instance
 - The instance type
 - The instance launch time
 - The Availability Zone
 - The ID of the kernel
 - The ID of the RAM disk
 - The platform (`windows` or `empty`)
 - The monitoring state
 - The public IP address
 - The private IP address
 - [EC2-VPC] The ID of the VPC
 - [EC2-VPC] The subnet ID
 - The type of root device (`ebs` or `instance-store`)

- The instance lifecycle
 - The Spot Instance request ID
 - The instance license
 - The placement group the cluster instance is in
 - The virtualization type (`paravirtual` or `hvm`)
 - The hypervisor type (`xen` or `ovm`)
 - The client token
 - The ID of each security group the instance is in
 - The tenancy of the instance (`default` or `dedicated`)
 - Whether or not the instance is EBS optimized (`true` or `false`)
 - The [Amazon Resource Name](#) (ARN) of the IAM role
3. Any Amazon EBS volumes associated with the instance. There will be one of the following for each volume
- The BLOCKDEVICE identifier
 - The device name
 - The volume ID
 - The volume attach timestamp
 - Whether or not the volume will be deleted on termination (`true` or `false`)
 - The volume type
 - The I/O operations per second (IOPS)
4. [EC2-VPC] The network interface information. There will be a set of the following for each network interface
- a. The network interface information
 - The NIC identifier
 - The network interface ID
 - The subnet ID
 - The VPC ID
 - The owner ID
 - The network interface status
 - The private IP address of the network interface
 - The private DNS name
 - Whether or not source destination check is enabled (`true` or `false`)
 - b. The network interface attachment information
 - The NICATTACHMENT identifier
 - The attachment ID
 - The device index
 - The device status
 - The attachment timestamp
 - Whether or not the attachment is deleted on termination (`true` or `false`)
 - c. The network interface association information
 - The NICASSOCIATION identifier
 - The public IP address
 - The public IP address owner
 - The private IP address
 - d. The security group information
 - The GROUP identifier

- The security group identifier
- The security group name
- e. The private IP address information
 - The PRIVATEIPADDRESS identifier
 - The private IP address
- 5. Any tags associated with the instance. There will be one of the following for each tag
 - The TAG identifier
 - The resource type identifier
 - The resource ID
 - The tag key
 - The tag value

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example describes the current state of the instances owned by your AWS account.

```
PROMPT> ec2-describe-instances

RESERVATION r-1a2b3c4d 111122223333 my-security-group
INSTANCE i-1a2b3c4d ami-1a2b3c4d ec2-67-202-51-223.compute-1.amazonaws.com ip-
10-251-50-35.ec2.internal running gsg-keypair 0 t1.micro YYYY-MM-
DDTHH:MM:SS+0000 us-west-2a aki-1a2b3c4d monitoring-disabled 184.73.10.99
10.254.170.223 ebs paravirtual xen ABCDE1234567890123 sg-1a2b3c4d default
false
BLOCKDEVICE /dev/sda1 vol-1a2b3c4d YYYY-MM-DDTHH:MM:SS.SSSZ true
BLOCKDEVICE /dev/sdb vol-2a2b3c4d YYYY-MM-DDTHH:MM:SS.SSSZ true
TAG instance i-1a2b3c4d Name Linux
RESERVATION r-2a2b3c4d 111122223333 another-security-group
INSTANCE i-2a2b3c4d ami-2a2b3c4d ec2-67-202-51-223.compute-1.amazonaws.com ip-
10-251-50-35.ec2.internal running gsg-keypair 0 t1.micro YYYY-MM-
DDTHH:MM:SS+0000 us-west-2c windows monitoring-disabled 50.112.203.9
10.244.168.218 ebs hvm xen ABCDE1234567890123 sg-2a2b3c4d default false
TAG instance i-2a2b3c4d Name Windows
```

Example Request

This example filters the response to include only the m1.small or m1.large instances that have an Amazon EBS volume that is both attached and set to delete on termination.

```
PROMPT> ec2-describe-instances --filter "instance-type=m1.small" --filter "in
stance-type=m1.large" --filter "block-device-mapping.status=attached" --filter
"block-device-mapping.delete-on-termination=true"
RESERVATION r-1a2b3c4d 111122223333 my-security-group
INSTANCE i-1a2b3c4d ami-1a2b3c4d ec2-67-202-51-223.compute-1.amazonaws.com ip-
10-251-50-35.ec2.internal running gsg-keypair 0 t1.micro YYYY-MM-
DDTHH:MM:SS+0000 us-west-2a aki-1a2b3c4d monitoring-disabled 184.73.10.99
10.254.170.223 ebs paravirtual xen ABCDE1234567890123 sg-1a2b3c4d default
false
```

```
BLOCKDEVICE    /dev/sdb          vol-1a2b3c4d    YYYY-MM-DDTHH:MM:SS.SSSZ true
TAG instance i-1a2b3c4d Name Linux
```

Example Request

This example describes all instances that are running in a VPC.

```
PROMPT> ec2-describe-instances --filter "vpc-id=*
RESERVATION r-1a2b3c4d 111122223333
INSTANCE i-1a2b3c4d ami-1a2b3c4d    running gsg-keypair 0    m1.small YYYY-MM-
DDTHH:MM:SS+0000 us-west-2b    windows monitoring-disabled 50.112.172.209
10.0.0.167 vpc-1a2b3c4d subnet-1a2b3c4d ebs    hvm xen ABCDE1234567890123 sg-
1a2b3c4d default false
BLOCKDEVICE    /dev/sdb          vol-1a2b3c4d    YYYY-MM-DDTHH:MM:SS.SSSZ true
NIC eni-1a2b3c4d subnet-1a2b3c4d vpc-1a2b3c4d 111122223333 in-use 10.0.1.167
true
NICATTACHMENT eni-attach-1a2b3c4d 0 attached YYYY-MM-DDTHH:MM:SS+0000 true
GROUP sg-1a2b3c4d my-security-group
PRIVATEIPADDRESS 10.0.1.167
PRIVATEIPADDRESS 10.0.1.12
TAG instance i-1a2b3c4d Name Windows
RESERVATION r-2a2b3c4d 111122223333
INSTANCE i-2a2b3c4d ami-2a2b3c4d    running gsg-keypair 0    c1.medium YYYY-MM-
DDTHH:MM:SS+0000 us-west-2b aki-1a2b3c4d    monitoring-disabled 50.112.172.209
10.0.0.233 vpc-1a2b3c4d subnet-1a2b3c4d ebs    hvm xen ABCDE1234567890123 sg-
1a2b3c4d default false
BLOCKDEVICE    /dev/sda1         vol-2a2b3c4d    YYYY-MM-DDTHH:MM:SS.SSSZ true
NIC eni-2a2b3c4d subnet-1a2b3c4d vpc-1a2b3c4d 111122223333 in-use 10.0.1.233
true
NICATTACHMENT eni-attach-2a2b3c4d 0 attached YYYY-MM-DDTHH:MM:SS+0000 true
GROUP sg-1a2b3c4d my-security-group
PRIVATEIPADDRESS 10.0.1.233
PRIVATEIPADDRESS 10.0.1.20
TAG instance i-1a2b3c4d Name Linux
```

Example Request

This example describes any instances with a network interface that have a private IP address of 10.0.0.120.

```
PROMPT> ec2-describe-instances --filter "network-interface.addresses.private-
ip-address=10.0.0.120"
RESERVATION r-1a2b3c4d 111122223333
INSTANCE i-1a2b3c4d ami-1a2b3c4d    running gsg-keypair 0    c1.medium YYYY-MM-
DDTHH:MM:SS+0000 us-west-2b aki-1a2b3c4d    monitoring-disabled 50.112.172.209
10.0.0.98 vpc-1a2b3c4d subnet-1a2b3c4d ebs    hvm xen ABCDE1234567890123 sg-
1a2b3c4d default false
BLOCKDEVICE    /dev/sdb          vol-1a2b3c4d    YYYY-MM-DDTHH:MM:SS.SSSZ true
NIC eni-1a2b3c4d subnet-1a2b3c4d vpc-1a2b3c4d 111122223333 in-use 10.0.1.98
true
NICATTACHMENT eni-attach-1a2b3c4d 0 attached YYYY-MM-DDTHH:MM:SS+0000 true
GROUP sg-1a2b3c4d my-security-group
PRIVATEIPADDRESS 10.0.0.98
PRIVATEIPADDRESS 10.0.0.120
```


Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeInstances](#)

Related Commands

- [ec2-run-instances](#) (p. 633)
- [ec2-start-instances](#) (p. 646)
- [ec2-stop-instances](#) (p. 650)
- [ec2-terminate-instances](#) (p. 654)

ec2-describe-internet-gateways

Description

Describes one or more of your Internet gateways.

The short version of this command is **ec2digw**.

Syntax

```
ec2-describe-internet-gateways [internet_gateway_id ...] [--filter "name=value"]  
...]
```

Options

Name	Description
<i>internet_gateway_id</i>	One or more IDs of the internet gateways. Type: String Default: Describes all your Internet gateways. Required: No Example: igw-15a4417c
<code>-F, --filter name=value</code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space (" <i>name=value example</i> "). On a Windows system, use quotation marks even without a space in the value string (" <i>name=value</i> "). Type: String Default: Describes all your Internet gateways, or only those you specified by ID. Required: No Example: <code>--filter "tag-key=Production"</code>

Supported Filters

You can specify filters so that the response includes information for only certain Internet gateways. For example, you can use a filter to specify that you're interested in the Internet gateways with particular tags. You can specify multiple values for a filter. The response includes information for an Internet gateway only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify Internet gateways that are attached to a specific VPC and have a specific tag. The response includes information for an Internet gateway only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

attachment.state

The current state of the attachment between the gateway and the VPC. Returned only if a VPC is attached.

Type: String

Valid value: `available`

attachment.vpc-id

The ID of an attached VPC.

Type: String

internet-gateway-id

The ID of the Internet gateway.

Type: String

tag-key

The key of a tag assigned to the resource. This filter is independent of the `tag-value` filter. For example, if you use both the filter `tag-key=Purpose` and the filter `tag-value=X`, you get any resources assigned both the tag key `Purpose` (regardless of what the tag's value is), and the tag value `X` (regardless of what the tag's key is). If you want to list only resources where `Purpose` is `X`, see the `tag:key` filter.

For more information about tags, see [Tagging Your Resources](#) in the *Amazon Elastic Compute Cloud User Guide*.

Type: String

tag-value

The value of a tag assigned to the resource. This filter is independent of the `tag-key` filter.

Type: String

tag:key

Filters the response based on a specific tag/value combination.

Example: To list just the resources that have been assigned tag `Purpose=X`, specify:

```
--filter tag:Purpose=X
```

Example: To list just resources that have been assigned tag `Purpose=X` OR `Purpose=Y`, specify:

```
--filter tag:Purpose=X --filter tag:Purpose=Y
```

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The INTERNETGATEWAY identifier
- The ID of the Internet gateway
- The ATTACHMENT identifier
- The ID of the VPC (if the gateway is attached to a VPC)
- The state of the attachment (attaching, attached, detaching, detached)
- Any tags assigned to the Internet gateway

Examples

Example Request

This example describes your Internet gateways.

```
PROMPT> ec2-describe-internet-gateways
INTERNETGATEWAY igw-dfa045b6
ATTACHMENT      vpc-d9a045b0    available
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeInternetGateways](#)

Related Commands

- [ec2-attach-internet-gateway](#) (p. 33)
- [ec2-create-internet-gateway](#) (p. 111)
- [ec2-delete-internet-gateway](#) (p. 196)
- [ec2-detach-internet-gateway](#) (p. 464)

ec2-describe-keypairs

Description

Describes one or more of your key pairs.

The short version of this command is **ec2dkey**.

Syntax

```
ec2-describe-keypairs [keypair_name ...] [--filter "name=value"] ...]
```

Options

Name	Description
<i>keypair_name</i>	One or more key pair names. Type: String Default: Describes all your key pairs. Required: No Example: gsg-keypair
<code>-F, --filter name=value</code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space (" <i>name=value example</i> "). On a Windows system, use quotation marks even without a space in the value string (" <i>name=value</i> "). Type: String Default: Describes all your key pairs, or only those you specified by name. Required: No Example: <code>--filter "tag-name=*Dave*"</code>

Supported Filters

You can specify filters so that the response includes information for only certain key pairs. For example, you can use a filter to specify that you're interested in key pairs whose names include the string `Dave`. You can specify multiple values for a filter. The response includes information for a key pair only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify key pairs whose names include the string `Dave` and whose fingerprint is a specific value. The response includes information for a key pair only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\.`

The following are the available filters.

fingerprint

The fingerprint of the key pair.

Type: String

key-name

The name of the key pair.

Type: String

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>

Option	Description
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains one of the following for each key pair:

- The KEYPAIR identifier
- The key pair name
- The private key fingerprint

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example describes the keypair with name `gsg-keypair`.

```
PROMPT> ec2-describe-keypairs gsg-keypair  
KEYPAIR gsg-keypair 00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00
```

Example Request

This example filters the response to include only key pairs whose names include the string `Dave`.

```
PROMPT> ec2-describe-keypairs --filter "key-name=*Dave*"
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeKeyPairs](#)

Related Commands

- [ec2-create-keypair](#) (p. 114)
- [ec2-delete-keypair](#) (p. 199)
- [ec2-import-keypair](#) (p. 514)

ec2-describe-network-acls

Description

Describes one or more of the network ACLs in your VPC.

For more information about network ACLs, see [Network ACLs](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2dnac1**.

Syntax

```
ec2-describe-network-acls [network_acl_id...] [--filter "name=value"] ...]
```

Options

Name	Description
<i>network_acl_id</i>	One or more IDs of the network ACLs. Type: String Default: Describes all network ACLs in the VPC. Required: No Example: acl-7aa34613
-F, --filter <i>name=value</i>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space (" <i>name=value example</i> "). On a Windows system, use quotation marks even without a space in the value string (" <i>name=value</i> "). Type: String Default: Describes all network ACLs in the VPC, or only those you specified by ID. Required: No Example: --filter "tag-key=Production"

Supported Filters

You can specify filters so that the response includes information for only certain ACLs. For example, you can use a filter to specify that you're interested in the ACLs associated with a particular subnet. You can specify multiple values for a filter. The response includes information for an ACL only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify ACLs that are associated with a specific subnet and have an egress entry that denies traffic to a specific port. The response includes information for an ACL only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

association.association-id

The ID of an association ID for the ACL.

Type: String

association.network-acl-id

The ID of the network ACL involved in the association.

Type: String

association.subnet-id

The ID of the subnet involved in the association.

Type: String

default

Indicates whether the ACL is the default network ACL for the VPC.

Type: Boolean

entry.cidr

The CIDR range specified in the entry.

Type: String

entry.egress

Indicates whether the entry applies to egress traffic.

Type: Boolean

entry.icmp.code

The ICMP code specified in the entry, if any.

Type: Integer

entry.icmp.type

The ICMP type specified in the entry, if any.

Type: Integer

entry.port-range.from

The start of the port range specified in the entry.

Type: Integer

entry.port-range.to

The end of the port range specified in the entry.

Type: Integer

entry.protocol

The protocol specified in the entry.

Type: String

Valid values: `tcp` | `udp` | `icmp` or a protocol number

entry.rule-action

Indicates whether the entry allows or denies the matching traffic.

Type: String

Valid values: `allow` | `deny`

entry.rule-number

The number of an entry (in other words, rule) in the ACL's set of entries.

Type: Integer

network-acl-id

The ID of the network ACL.

Type: String

tag-key

The key of a tag assigned to the resource. This filter is independent of the `tag-value` filter. For example, if you use both the filter `tag-key=Purpose` and the filter `tag-value=X`, you get any resources assigned both the tag key `Purpose` (regardless of what the tag's value is), and the tag

value `x` (regardless of what the tag's key is). If you want to list only resources where Purpose is `X`, see the `tag:key` filter.

For more information about tags, see [Tagging Your Resources](#) in the *Amazon Elastic Compute Cloud User Guide*.

Type: String

tag-value

The value of a tag assigned to the resource. This filter is independent of the `tag-key` filter.

Type: String

tag:key

Filters the response based on a specific tag/value combination.

Example: To list just the resources that have been assigned tag Purpose=`X`, specify:

```
--filter tag:Purpose=X
```

Example: To list just resources that have been assigned tag Purpose=`X` OR Purpose=`Y`, specify:

```
--filter tag:Purpose=X --filter tag:Purpose=Y
```

vpc-id

The ID of the VPC for the network ACL.

Type: String

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-T, --security-token</code> <code>TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <code>TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <code>TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <code>EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <code>EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The NETWORKACL, ENTRY, ASSOCIATION identifier
- The network ACL's ID, the ID of the VPC the ACL is in, and whether the ACL is the default ACL in the VPC
- The entries (in other words, rules) contained in the ACL
- Associations between the ACL and any subnets
- Any tags assigned to the ACL

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example describes all the network ACLs in your VPC.

```
PROMPT> ec2-describe-network-acls
NETWORKACL    acl-5566953c    vpc-5266953b    default
ENTRY    egress    100    allow    0.0.0.0/0    all
ENTRY    egress    32767    deny    0.0.0.0/0    all
ENTRY    ingress    100    allow    0.0.0.0/0    all
ENTRY    ingress    32767    deny    0.0.0.0/0    all
NETWORKACL    acl-5d659634    vpc-5266953b
ENTRY    egress    110    allow    0.0.0.0/0    6    49152    65535
ENTRY    egress    32767    deny    0.0.0.0/0    all
ENTRY    ingress    110    allow    0.0.0.0/0    6    80    80
ENTRY    ingress    120    allow    0.0.0.0/0    6    443    443
ENTRY    ingress    32767    deny    0.0.0.0/0    all
ASSOCIATION    aclassoc-5c659635    subnet-ff669596
ASSOCIATION    aclassoc-c26596ab    subnet-f0669599
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeNetworkAcls](#)

Related Commands

- [ec2-create-network-acl](#) (p. 118)
- [ec2-delete-network-acl](#) (p. 202)
- [ec2-replace-network-acl-association](#) (p. 576)

- [ec2-create-network-acl-entry](#) (p. 121)
- [ec2-delete-network-acl-entry](#) (p. 205)
- [ec2-replace-network-acl-entry](#) (p. 580)

ec2-describe-network-interface-attribute

Description

Describes a network interface attribute. You can specify only one attribute at a time.

The short version of this command is **ec2dnicatt**.

Syntax

```
ec2-describe-network-interface-attribute interface_id --description description
--source-dest-check --group-set --attachment
```

Options

Name	Description
<i>interface_id</i>	The ID of the network interface. Type: String Default: None Required: Yes Example: eni-bc7299d4
-d, --description <i>description</i>	Describes the network interface. Type: String Required: Yes
--source-dest-check	Whether to enable the source/dest check on traffic through this network interface. Type: String Required: Yes
--group-set	Describes the security groups for the network interface. Type: String Required: Yes
-a, --attachment	Describes the attachment (if any) of the network interface. Type: String Required: Yes

Common Options

Option	Description
--region <i>REGION</i>	Overrides the region specified by the EC2_URL environment variable and the URL specified by the -U option. Default: The value of the EC2_URL environment variable, or us-east-1 if EC2_URL isn't set. Example: --region eu-west-1

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the EC2_PRIVATE_KEY environment variable. Example: -K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the EC2_CERT environment variable. Example: -C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem

Output

This command returns the specified network interface attribute.

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example lists the network interface's description.

```
PROMPT> ec2-describe-network-interface-attribute eni-b35da6da -d
NETWORKINTERFACE      eni-b35da6da      description
DESCRIPTION          My ENI
```

This example enables source/destination checking on traffic across the specified network interface.

```
PROMPT> ec2-describe-network-interface-attribute eni-b35da6da --source-dest-  
check
NETWORKINTERFACE      eni-b35da6da      sourceDestCheck
SOURCEDESTCHECK      true
```

This example lists the security groups for the specified network interface.

```
PROMPT> ec2-describe-network-interface-attribute eni-b35da6da --group-set
NETWORKINTERFACE      eni-b35da6da      group
GROUP                 sg-8ealbce2       default
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeNetworkInterfaceAttribute](#)

Related Commands

- [ec2-create-network-interface](#) (p. 126)
- [ec2-delete-network-interface](#) (p. 209)
- [ec2-describe-network-interfaces](#) (p. 352)
- [ec2-attach-network-interface](#) (p. 37)
- [ec2-detach-network-interface](#) (p. 467)
- [ec2-modify-network-interface-attribute](#) (p. 541)
- [ec2-reset-network-interface-attribute](#) (p. 615)

ec2-describe-network-interfaces

Description

Describes one or more of your network interfaces.

The short version of this command is **ec2dnic**.

Syntax

```
ec2-describe-network-interfaces [--filter "name=value"] ...]
```

Options

Name	Description
<code>-F, --filter <i>name=value</i></code>	<p>A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space ("<i>name=value example</i>"). On a Windows system, use quotation marks even without a space in the value string ("<i>name=value</i>").</p> <p>Type: String Default: None Required: No Example: <code>-F "description=My ENI"</code></p>

Supported Filters

You can specify filters so that the response includes information for only certain network interfaces. For example, you can use a filter to specify that you're interested in network interfaces launched in a specific Availability Zone. You can specify multiple values for a filter. The response includes information for a network interface only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify network interfaces in a specific Availability Zone, and that have a specific owner ID. The response includes information for a network interface only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

addresses.private-ip-address

The private IP addresses associated with the network interface.

Type: String

addresses.primary

Whether the private IP address is the primary IP address associated with the network interface.

Type: Boolean

Valid values: `true` | `false`

- addresses.association.public-ip**
The association ID returned when the network interface was associated with the Elastic IP address.
Type: String
- addresses.association.owner-id**
The owner ID of the addresses associated with the network interface.
Type: String
- association.association-id**
The association ID returned when the network interface was associated with an IP address.
Type: String
- association.allocation-id**
The allocation ID that AWS returned when you allocated the Elastic IP address for your network interface.
Type: String
- association.ip-owner-id**
The owner of the Elastic IP address associated with the network interface.
Type: String
- association.public-ip**
The address of the Elastic IP address bound to the network interface.
Type: String
- attachment.attachment-id**
The ID of the interface attachment.
Type: String
- attachment.instance-id**
The ID of the instance to which the network interface is attached.
Type: String
- attachment.instance-owner-id**
The owner ID of the instance to which the network interface is attached.
Type: String
- attachment.device-index**
The device index to which the network interface is attached.
Type: Integer
- attachment.status**
The status of the attachment.
Type: String
Valid values: `attaching` | `attached` | `detaching` | `detached`
- attachment.attach.time**
The time that the network interface was attached to an instance.
Type: DateTime
- attachment.delete-on-termination**
Indicates whether the attachment is deleted when an instance is terminated.
Type: Boolean
- availability-zone**
The Availability Zone of the network interface.
Type: String
- description**
The description of the network interface.
Type: String
- group-id**
The ID of a security group associated with the network interface.

- Type: String
- group-name**
The name of a security group associated with the network interface.
Type: String
- mac-address**
The MAC address of the network interface.
Type: String
- network-interface-id**
The ID of the network interface.
Type: String
- owner-id**
The AWS account ID of the network interface owner.
Type: String
- private-ip-address**
The private IP address or addresses of the network interface.
Type: String
- private-dns-name**
The private DNS name of the network interface.
Type: String
- requester-id**
The ID of the entity that launched the instance on your behalf (for example, AWS Management Console, Auto Scaling, and so on).
Type: String
- requester-managed**
Indicates whether the network interface is being managed by an AWS service (for example, AWS Management Console, Auto Scaling, and so on).
Type: Boolean
- source-dest-check**
Indicates whether the network interface performs source/destination checking. A value of `true` means checking is enabled, and `false` means checking is disabled. The value must be `false` for the network interface to perform Network Address Translation (NAT) in your VPC.
Type: Boolean
- status**
The status of the network interface. If the network interface is not attached to an instance, the status shows `available`; if a network interface is attached to an instance the status shows `in-use`.
Type: String
Valid values: `available` | `in-use`
- subnet-id**
The ID of the subnet for the network interface.
Type: String
- tag-key**
The key of a tag assigned to the resource. This filter is independent of the `tag-value` filter. For example, if you use both the filter `"tag-key=Purpose"` and the filter `"tag-value=X"`, you get any resources assigned both the tag key `Purpose` (regardless of what the tag's value is), and the tag value `X` (regardless of what the tag's key is). If you want to list only resources where Purpose is `X`, see the `tag:key` filter.
For more information about tags, see [Tagging Your Resources](#) in the *Amazon Elastic Compute Cloud User Guide*.
Type: String
- tag-value**
The value of a tag assigned to the resource. This filter is independent of the `tag-key` filter.

Type: String

tag: *key*

Filters the response based on a specific tag/value combination.

Example: To list just the resources that have been assigned tag Purpose=X, specify:

```
--filter tag:Purpose=X
```

Example: To list just resources that have been assigned tag Purpose=X OR Purpose=Y, specify:

```
--filter tag:Purpose=X --filter tag:Purpose=Y
```

vpc-id

The ID of the VPC for the network interface.

Type: String

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>

Option	Description
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

The command returns a table that contains the following information for each network interface.

- The `NETWORKINTERFACE` identifier
- The ID of the network interface
- The ID of the subnet
- The ID of the VPC

- The Availability Zone
- A description
- The ID of the account that created the network interface
- The ID of the entity that launched the instance on your behalf
- Whether the network interface is being managed by AWS
- The status (*available*, *attaching*, *in-use*, *detaching*)
- The MAC address
- The private IP address
- The private DNS name
- Whether traffic to or from the instance is validated
- The GROUP identifier
- The ID of the security group
- The name of the security group
- The ATTACHMENT identifier
- The ID of the instance
- The ID of the attachment
- The ASSOCIATION identifier
- The Elastic IP address
- The ID of the owner of the Elastic IP address
- The ID of the account that created the network association
- The ID of the association
- The private IP address
- The PRIVATEIPADDRESS identifier
- The private IP address

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example lists all network interfaces that you own.

```
PROMPT> ec2-describe-network-interfaces
NETWORKINTERFACE      eni-5e318a37          subnet-c53c87ac vpc-cc3c87a5
ap-southeast-1b 053230519467          false in-use 02:81:60:c7:15:3d
10.0.0.79              true
GROUP sg-084b5664       quick-start-4
ATTACHMENT i-5a0f6b0e           eni-attach-59bf7430  attached      true
PRIVATEIPADDRESS     10.0.0.79
PRIVATEIPADDRESS     10.0.0.183
PRIVATEIPADDRESS     10.0.0.184
NETWORKINTERFACE     eni-236dd74a         My ENI subnet-c88a35a1 vpc-f28a359b
ap-southeast-1a 053230519467          false available      02:78:d7:32:3f:ba
10.0.0.117           true
GROUP sg-854954e9     LinuxGroup
PRIVATEIPADDRESS     10.0.0.117
NETWORKINTERFACE     eni-69ce7500         Primary network interface subnet-
c
```

```
d8a35a4 vpc-f28a359b ap-southeast-1b 053230519467 false in-use
02:78:d7:18:ad:f0 10.0.1.152 true GROUP sg-dc4c51b0
quick-start-2
ATTACHMENT i-e0841fb4 eni-attach-696ba300 attached true
PRIVATEIPADDRESS 10.0.1.152
PRIVATEIPADDRESS 10.0.1.12
NETWORKINTERFACE eni-f25de69b subnet-c88a35a1 vpc-f28a359b
ap-southeast-1a 053230519467 false in-use 02:78:d7:2d:16:5b
10.0.0.133 true
```

This example filters for a network interface with the private IP address of 10.0.0.26.

```
PROMPT> ec2-describe-network-interfaces --filter "addresses.private-ip-ad
dress=10.0.0.26"
NETWORKINTERFACE eni-4cba0725 subnet-73ba071a vpc-6bba0702
ap-southeast-1b 013274050172 false available
02:75:3f:8e:3a:d3 10.0.0.26 true
GROUP sg-8fb3a1e3 default ASSOCIATION 203.0.113.12 013274050172
eipassoc-f008b799 10.0.0.26
PRIVATEIPADDRESS 10.0.0.26
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeNetworkInterfaces](#)

Related Commands

- [ec2-create-network-interface](#) (p. 126)
- [ec2-delete-network-interface](#) (p. 209)
- [ec2-describe-network-interface-attribute](#) (p. 348)
- [ec2-attach-network-interface](#) (p. 37)
- [ec2-detach-network-interface](#) (p. 467)
- [ec2-modify-network-interface-attribute](#) (p. 541)
- [ec2-reset-network-interface-attribute](#) (p. 615)

ec2-describe-placement-groups

Description

Describes one or more of your placement groups. For more information about placement groups and cluster instances, see [Using Cluster Instances](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2dpgrp**.

```
ec2-describe-placement-groups [group_name] [--filter "name=value"] ...]
```

Options

Name	Description
<i>group_name</i>	One or more placement group names. Type: String Default: Describes all placement groups you own. Required: No Example: XYZ-cluster
-F, --filter name=value	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value string ("name=value"). Type: String Default: Describes all your placement groups, or only those you specified by name. Required: No Example: --filter "group-name=*Project"

Supported Filters

You can specify filter so that the response includes information for only certain placement groups. For example, you can use a filter to specify that you're interested in groups in the `deleted` state. You can specify multiple values for a filter. The response includes information for a placement group only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify group's that are in the `deleted` state and have a name that includes the string `Project`. The response includes information for a group only if it matches all your filters. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?.`

The following are the available filters.

group-name
The name of the placement group.
Type: String

state

The state of the placement group.

Type: String

Valid values: pending | available | deleting | deleted

strategy

The strategy of the placement group.

Type: String

Valid value: cluster

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>

Option	Description
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns the following information:

- The PLACEMENTGROUP identifier
- The placement group name
- The placement group strategy
- The state of the placement group

Examples

Example Request

This example describes all your placement groups.

```
PROMPT> ec2-describe-placement-groups  
PLACEMENTGROUP XYZ-cluster cluster available  
PLACEMENTGROUP ABC-cluster cluster available
```

Example Request

This example filters the response to include only placement groups that include the string `Project` in the name.

```
PROMPT> ec2-describe-placement-groups --filter "group-name=*Project*"  
PLACEMENTGROUP Project-cluster cluster available
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribePlacementGroups](#)

Related Commands

- [ec2-create-placement-group](#) (p. 131)
- [ec2-delete-placement-group](#) (p. 212)

ec2-describe-regions

Description

Describes one or more of the regions that are available to you.

For a list of the regions supported by Amazon EC2, see [Regions and Endpoints](#).

The short version of this command is **ec2dre**.

Syntax

```
ec2-describe-regions [region...] [--filter "name=value"] ...]
```

Options

Name	Description
<i>region</i>	One or more region names. Type: String Default: Describes all your regions. Required: No Example: eu-west-1
<code>-F, --filter name=value</code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value string ("name=value"). Type: String Default: Describes all your regions, or only those you specified by name. Required: No Example: --filter "endpoint=*ap**"

Supported Filters

You can specify filters so that the response includes information for only certain regions.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

endpoint

The endpoint of the region (for example, ec2.us-east-1.amazonaws.com).

Type: String

region-name

The name of the region.

Type: String

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.

Option	Description
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The REGION identifier
- The name of the region
- The service endpoint for the region

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example displays information about all the regions that are available to the account.

```
PROMPT> ec2-describe-regions
REGION us-east-1 ec2.us-east-1.amazonaws.com
REGION ap-northeast-1 ec2.ap-northeast-1.amazonaws.com
```

```
REGION ap-southeast-1 ec2.ap-southeast-1.amazonaws.com
..
```

Example Request

This example displays information about all regions that have the string `ap` in the endpoint.

```
PROMPT> ec2-describe-regions --filter "endpoint=*ap*"
REGION ap-southeast-1 ec2.us-east-1.amazonaws.com
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeRegions](#)

Related Commands

- [ec2-describe-availability-zones](#) (p. 262)
- [ec2-run-instances](#) (p. 633)

ec2-describe-reserved-instances

Description

Describes the Reserved Instances that you purchased.

Starting with the 2011-11-01 API version, AWS expanded its offering for Amazon EC2 Reserved Instances to address a range of projected instance use. There are three types of Reserved Instances based on customer utilization levels: *Heavy Utilization*, *Medium Utilization*, and *Light Utilization*. The Medium Utilization offering type is equivalent to the Reserved Instance offering available before API version 2011-11-01. If you are using tools that predate the 2011-11-01 API version, you only have access to the *Medium Utilization* Reserved Instance offering type.

For more information about Reserved Instances, see [Reserved Instances](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2dri**.

Syntax

```
ec2-describe-reserved-instances [reservation_id ...] [--filter "name=value"] ...]
```

Options

Name	Description
<i>reservation_id</i>	The IDs of the Reserved Instances. Type: String Default: Describes all your Reserved Instances. Required: No Example: 4b2293b4-5813-4cc8-9ce3-1957fexample
<code>-F, --filter name=value</code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space (" <i>name=value example</i> "). On a Windows system, use quotation marks even without a space in the value string (" <i>name=value</i> "). Type: String Default: Describes all your Reserved Instances, or only those you specified by ID. Required: No Example: <code>--filter "tag-key=Production"</code>

Supported Filters

You can specify filter so that the response includes information for only certain Reserved Instances. For example, you can use a filter to specify that you're interested in Reserved Instances in a specific Availability Zone. You can specify multiple values for a filter. The response includes information for a Reserved Instance only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify Reserved Instances that are in a specific Availability Zone and have a specific tag. The response includes information for a Reserved Instance only if it matches all of the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

availability-zone

The Availability Zone where the Reserved Instance can be used.

Type: String

duration

The duration of the Reserved Instance (one year or three years), in seconds.

Type: Long

Valid values: 31536000 | 94608000

fixed-price

The purchase price of the Reserved Instance (for example, 9800.0)

Type: Double

instance-type

The instance type on which the Reserved Instance can be used.

Type: String

product-description

The product description of the Reserved Instance.

Type: String

Valid values: Linux/UNIX | Linux/UNIX (Amazon VPC) | Windows | Windows (Amazon VPC)

reserved-instances-id

The ID of the Reserved Instance.

Type: String

start

The time at which the Reserved Instance purchase request was placed (for example, 2010-08-07T11:54:42.000Z).

Type: DateTime

state

The state of the Reserved Instance.

Type: String

Valid values: pending-payment | active | payment-failed | retired

tag-key

The key of a tag assigned to the resource. This filter is independent of the `tag-value` filter. For example, if you use both the filter `"tag-key=Purpose"` and the filter `"tag-value=X"`, you get any resources assigned both the tag key `Purpose` (regardless of what the tag's value is), and the tag value `X` (regardless of what the tag's key is). If you want to list only resources where `Purpose` is `X`, see the `tag:key` filter.

For more information about tags, see [Tagging Your Resources](#) in the *Amazon Elastic Compute Cloud User Guide*.

Type: String

tag-value

The value of a tag assigned to the resource. This filter is independent of the `tag-key` filter.

Type: String

tag: *key*

Filters the response based on a specific tag/value combination.

Example: To list just the resources that have been assigned tag Purpose=X, specify:

```
--filter tag:Purpose=X
```

Example: To list just resources that have been assigned tag Purpose=X OR Purpose=Y, specify:

```
--filter tag:Purpose=X --filter tag:Purpose=Y
```

usage-price

The usage price of the Reserved Instance, per hour (for example, 0.84)

Type: Double

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>

Option	Description
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The `RESERVEDINSTANCES` identifier
- The ID of the Reserved Instance
- The Availability Zone in which the Reserved Instance can be used
- The instance type

- The Reserved Instance description (Linux/UNIX, Windows, Linux/UNIX (Amazon VPC), or Windows (Amazon VPC))
- The duration of the Reserved Instance
- The upfront fee (fixed price) you pay for the Reserved Instance
- The fee (usage price) you pay per hour for using your Reserved Instance
- The number of Reserved Instances purchased
- The start date of the Reserved Instance term
- The state of the Reserved Instance purchase (payment-pending, active, payment-failed)
- The currency of the Reserved Instance purchased. It's specified using ISO 4217 standard code (for example, USD, JPY).
- The tenancy of the reserved instance purchased. An instance with a tenancy of dedicated runs on single-tenant hardware.
- The instance offering type

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example describes Reserved Instances owned by your account.

```
PROMPT> ec2-describe-reserved-instances
RESERVEDINSTANCES 1ba8e2e3-2538-4a35-b749-1f444example us-east-1a m1.small
Linux/UNIX 3y 350.0 0.03 1 2009-03-13T16:01:39+0000 payment-pending USD default
Light Utilization
RESERVEDINSTANCES af9f760e-c1c1-449b-8128-1342dexample us-east-1d m1.xlarge
Linux/UNIX 1y 1820.0 0.24 1 2009-03-13T16:01:39+0000 active USD default Medium
Utilization
```

Example Request

This example filters the response to include only one-year, m1.small Linux/UNIX Reserved Instances. If you want Linux/UNIX Reserved Instances specifically for use with a VPC, set the product description to Linux/UNIX (Amazon VPC).

```
PROMPT> ec2-describe-reserved-instances --filter "duration=31536000" --filter
"instance-type=m1.small" --filter "product-description=Linux/UNIX"
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeReservedInstances](#)

Related Commands

- [ec2-describe-reserved-instances-offerings](#) (p. 378)
- [ec2-purchase-reserved-instances-offering](#) (p. 559)

ec2-describe-reserved-instances-listings

Description

Describes your account's Reserved Instance listings in the Reserved Instance Marketplace. This call returns information about your listings, such as the identifiers of the Reserved Instances that are associated with the Reserved Instances listings.

The Reserved Instance Marketplace matches sellers who want to resell Reserved Instance capacity that they no longer need with buyers who want to purchase additional capacity. Reserved Instances bought and sold through the Reserved Instance Marketplace work like any other Reserved Instances.

As a seller, you choose to list some or all of your Reserved Instances, and you specify the upfront price you want to receive for them. Your Reserved Instances are then listed in the Reserved Instance Marketplace and are available for purchase.

As a buyer, you specify the configuration of the Reserved Instance you want to purchase, and the Marketplace will match what you're searching for with what's available. The Marketplace will first sell the lowest priced Reserved Instances to you, and continue to sell the available Reserved Instance listings to you until your demand is met. You will be charged based on the total upfront price of all the Reserved Instances that you purchase.

For more information about Reserved Instance Marketplace, see [Reserved Instance Marketplace](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2dril**.

Syntax

```
ec2-describe-reserved-instances-listings [LISTING [LISTING [...]]] [--filter "name=value"] ...]
```

Options

Name	Description
<i>LISTING</i>	The ID of the Reserved Instance listing. Type: String Default: None Required: No
<code>-F, --filter FILTER name=value</code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value string ("name=value"). Type: String Default: Describes all your Reserved Instances listings, or only those you specified by ID. Required: No Example: <code>--filter "status=pending"</code>

Supported Filters

Our policy is to provide filters for all `ec2-describe` calls so that you can limit the response to your specified criteria. Therefore, you can use filters to limit the response when describing Reserved Instances listings, even though you can use other options instead.

For example, you can use a filter or an option to get the listing of Reserved Instances that are in an active state. You can also specify multiple options or filters (for example, to limit the response to the Reserved Instances listings that are in the closed state with a specific status message). The response includes information for a listing only if it matches all options or filters. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

status

Status of the Reserved Instance listing.

Valid values: `pending` | `active` | `cancelled` | `closed`

Type: String

status-message

Reason for the status.

Type: String

reserved-instances-listing-id

The ID of the Reserved Instances listing.

Type: String

reserved-instances-id

The ID of the Reserved Instances.

Type: String

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

The command returns a table that contains the following information:

The listing information

- The LISTING identifier
- Reserved Instance listing ID
- Reserved Instances ID
- Create Date
- Update Date
- Status
- Status Message

One or more rows that contain instance count information

- The INSTANCE-COUNT identifier
- The instance count state
- The instance count

One or more rows that contain price schedule information

- The PRICE-SCHEDULE identifier
- The term
- The price
- Whether or not the schedule is active

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example describes a Reserved Instance listing owned by your account.

```
PROMPT> ec2-describe-reserved-instances-listings 095c0e18-c9e6-4692-97e5-653e0example
```

Amazon EC2 returns output similar to the following:

```
PROMPT> ec2-describe-reserved-instances-listings 095c0e18-c9e6-4692-97e5-653e0example
Type ReservedInstancesListingId ReservedInstancesId CreateDate UpdateDate Status
  StatusMessage
LISTING 095c0e18-c9e6-4692-97e5-653e0example b847fa93-c736-4eae-bca1-e3147example
  Tue Aug 28 18:21:07 PDT 2012 Tue Aug 28 18:21:07 PDT 2012 active active
INSTANCE-COUNT available 1
INSTANCE-COUNT sold 0
INSTANCE-COUNT cancelled 0
INSTANCE-COUNT pending 0
PRICE-SCHEDULE 5 $1.2 false
PRICE-SCHEDULE 4 $1.2 true
PRICE-SCHEDULE 3 $1.2 false
PRICE-SCHEDULE 2 $1.2 false
PRICE-SCHEDULE 1 $1.2 true
```

Related Operations

- [ec2-create-reserved-instances-listing](#) (p. 134)
- [ec2-cancel-reserved-instances-listing](#) (p. 71)
- [ec2-describe-reserved-instances](#) (p. 367)

ec2-describe-reserved-instances-offerings

Description

Describes Reserved Instance offerings that are available for purchase. With Amazon EC2 Reserved Instances, you purchase the right to launch instances for a period of time. During that time period you will not receive insufficient capacity errors, and you will pay a lower usage rate than the rate charged for On-Demand instances for the actual time used.

Starting with the 2011-11-01 API version, AWS expanded its offering of Amazon EC2 Reserved Instances to address a range of projected instance usage. There are three types of Reserved Instances based on customer utilization levels: *Heavy Utilization*, *Medium Utilization*, and *Light Utilization*. You determine the type of the Reserved Instance offerings by including the optional *offeringType* parameter when calling `ec2-describe-reserved-instances-offerings`. The Medium Utilization offering type is equivalent to the Reserved Instance offering available before API version 2011-11-01. If you are using tools that predate the 2011-11-01 API version, `ec2-describe-reserved-instances-offerings` will only list information about the `Medium Utilization` Reserved Instance offering type.

For information about Reserved Instances Pricing Tiers, see [Understanding Reserved Instance Pricing Tiers](#) in the *Amazon Elastic Compute Cloud User Guide*. For more information about Reserved Instances, see [Reserved Instances](#) also in the *Amazon Elastic Compute Cloud User Guide*.

Starting with the 2012-08-15 API version, AWS offers the Reserved Instance Marketplace, where you can buy and sell Reserved Instances. The Reserved Instance Marketplace makes it easy to buy and sell Amazon EC2 Reserved Instances by matching sellers who own capacity that they no longer need with buyers who are looking to purchase additional capacity. Reserved Instances bought and sold through the Reserved Instance Marketplace work like any other Reserved Instances.

By default, with the 2012-08-15 API version, `ec2-describe-reserved-instances-offerings` returns information about Amazon EC2 Reserved Instances available directly from AWS, plus instance offerings available from third-party sellers, on the Reserved Instance Marketplace. If you are using tools that predate the 2012-08-15 API version, `ec2-describe-reserved-instances-offerings` will only list information about Amazon EC2 Reserved Instances available directly from AWS.

For more information about the Reserved Instance Marketplace, see [Reserved Instance Marketplace](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is `ec2drrio`.

Syntax

```
ec2-describe-reserved-instances-offerings [offering_id ...] [--type instance_type ...] [--offering-type offering] [--availability-zone zone ...] [--description description ...] [--filter "name=value" ...] [--tenancy tenancy] [--exclude-marketplace] [--min-duration MIN-DURATION] [--max-duration MAX-DURATION]
```

Options

Name	Description
<code>offering_id</code>	The ID of a Reserved Instance offering. Type: String Default: None Required: No Example: 438012d3-4967-4ba9-aa40-cbb1dexample
<code>-t, --type instance_type</code>	The instance type on which the Reserved Instance can be used. Type: String Default: None Required: No Example: -t m1.small
<code>--offering-type offering-type</code>	The Reserved Instance offering type. Type: String Default: None Valid values: "Heavy Utilization" "Medium Utilization" "Light Utilization" Required: No Example: --offering-type "Medium Utilization"
<code>-z, --availability-zone zone</code>	The Availability Zone in which the Reserved Instance can be used. Type: String Default: None Required: No Example: -z us-east-1a
<code>-d, --description description</code>	The Reserved Instance description. Instances that include (Amazon VPC) in the description are for use with Amazon VPC. Type: String Default: None Valid values: Linux/UNIX Linux/UNIX (Amazon VPC) SUSE Linux SUSE Linux (Amazon VPC) Red Hat Enterprise Linux Red Hat Enterprise Linux (Amazon VPC) Windows Windows (Amazon VPC) Windows with SQL Server Standard Windows with SQL Server Standard (Amazon VPC) Windows with SQL Server Web Windows with SQL Server Web (Amazon VPC) Required: No Example: -d Linux/UNIX

Name	Description
<code>-F, --filter FILTER name=value</code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value string ("name=value"). Type: String Default: Describes all your Reserved Instances offerings, or those you specified by ID. Required: No Example: <code>--filter "instance-type=m1.small"</code>
<code>--tenancy TENANCY</code>	Specifies the tenancy of the Reserved Instance offering. A Reserved Instance with tenancy of dedicated will run on single-tenant hardware and can only be launched within a VPC. Type: String Default: default Valid values: <code>default dedicated</code> Required: No
<code>--exclude-marketplace</code>	Excludes the Reserved Instance Marketplace offerings in the response. Required: No
<code>--min-duration MIN-DURATION</code>	Specifies that only offerings that have a duration of at least <i>MIN-DURATION</i> months should be returned. Type: String Default: None Required: No
<code>--max-duration MAX-DURATION</code>	Specifies that only offerings that have a duration of at most <i>MAX-DURATION</i> months should be returned. Type: String Default: None Required: No

Supported Filters

Our policy is to provide filters for all `ec2-describe` calls so that you can limit the response to your specified criteria. Therefore, you can use filters to limit the response when describing Reserved Instances offerings, even though you can use other options instead.

For example, you could use an option or a filter to get the offerings for a specific instance type. You can specify multiple options or filters (for example, limit the response to the `m2.xlarge` instance type, and only for Windows instances). The response includes information for an offering only if it matches all options or filters. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

availability-zone

The Availability Zone where the Reserved Instance can be used.

Type: String

duration

The duration of the Reserved Instance (for example, one year or three years), in seconds.

Type: Long

Valid values: 31536000 | 94608000

fixed-price

The purchase price of the Reserved Instance (for example, 9800.0)

Type: Double

instance-type

The Amazon EC2 instance type on which the Reserved Instance can be used.

Type: String

marketplace

Set to `true` to show only Reserved Instance Marketplace offerings. When this filter is not used, which is the default behavior, all offerings from AWS and Reserved Instance Marketplace are listed.

Type: Boolean

product-description

The description of the Reserved Instance.

Type: String

Valid values: Linux/UNIX | Linux/UNIX (Amazon VPC) | Windows | Windows (Amazon VPC)

reserved-instances-offering-id

The Reserved Instances offering ID.

Type: String

usage-price

The usage price of the Reserved Instance, per hour (for example, 0.84)

Type: Double

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

The command returns a table that contains the following information:

The offering information

- The OFFERING identifier
- The source of the offering (AWS or 3rd Party)
- The offering ID
- The Availability Zone in which the Reserved Instance can be used
- The instance type
- The duration of the Reserved Instance
- The purchase price of the Reserved Instance. This may be contained in one or more subsequent PRICING_DETAIL rows
- The usage price of the Reserved Instance, per hour. This may be contained in one or more subsequent RECURRING-CHARGE rows
- The Reserved Instance description
- The currency of the Reserved Instance. It's specified using ISO 4217 standard (for example, USD). At this time, the only supported currency is USD.
- The tenancy of the Reserved Instance.
- The instance offering type ("Heavy Utilization" | "Medium Utilization" | "Light Utilization")

One or more rows that contain the recurring charge information, if any

- The RECURRING-CHARGE identifier
- The recurring charge frequency
- The recurring charge amount

One or more rows that contain the purchase price detail information, if any

- The PRICING_DETAIL identifier
- The number of times the purchase price must be paid
- The purchase price of the Reserved Instance

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

Check to see what `m1.small` Reserved Instances are available in a specific region.

```
PROMPT> ec2-describe-reserved-instances-offerings -t m1.small -z sa-east-1b -d
Linux/UNIX --headers
```

Amazon EC2 returns output similar to the following example:

```
PROMPT> ec2-describe-reserved-instances-offerings
Type Source ReservedInstancesOfferingId AvailabilityZone InstanceType Duration
FixedPrice UsagePrice ProductDescription Currency InstanceTenancy OfferingType
OFFERING AWS 4b2293b4-3236-49f5-978d-a74c3example sa-east-1b m1.small 3y 574.0
0.0 Linux/UNIX USD default Heavy Utilization
Type Frequency Amount
RECURRING-CHARGE Hourly 0.021
OFFERING AWS 3a98bf7d-07e1-4b33-8e11-e5314example sa-east-1b m1.small 3y 473.0
0.031 Linux/UNIX USD default Medium Utilization
OFFERING AWS 438012d3-5fc5-4e49-a88e-273edexample sa-east-1b m1.small 3y 203.0
0.055 Linux/UNIX USD default Light Utilization
OFFERING AWS d586503b-bb92-41fa-9065-e5b90example sa-east-1b m1.small 1y 372.94
0.0 Linux/UNIX USD default Heavy Utilization
Type Frequency Amount
RECURRING-CHARGE Hourly 0.03
OFFERING AWS ceb6a579-b235-41e2-9aad-15a23example sa-east-1b m1.small 1y 307.13
0.04 Linux/UNIX USD default Medium Utilization
OFFERING AWS 649fd0c8-4ffb-443d-824d-eae3fexample sa-east-1b m1.small 1y 131.63
0.07 Linux/UNIX USD default Light Utilization
OFFERING 3rd Party b6121943-9faf-4350-8047-bc6d4example sa-east-1b m1.small 10m
- 0.032 Linux/UNIX USD default Medium Utilization
Type Count Price
PRICING_DETAIL 2 $1.2
OFFERING 3rd Party 08edcff2-8143-4c1d-b23c-e4c11example sa-east-1b m1.small 5m
- 0.032 Linux/UNIX USD default Medium Utilization
Type Count Price
PRICING_DETAIL 19 $1.2
PRICING_DETAIL 4 $1.23
```

The preceding output shows a part of the overall offerings that are available.

Tip

You can filter this list to return only certain types of Reserved Instances offerings of interest to you.

Example Request

This example filters the response to include only one-year, `m1.small` or `m1.large` Linux/UNIX Reserved Instances. If you want Linux/UNIX Reserved Instances specifically for use with a VPC, set the product description to `Linux/UNIX` (Amazon VPC).

```
PROMPT> ec2-describe-reserved-instances-offerings --filter "duration=31536000"
--filter "instance-type=m1.small" --filter "instance-type=m1.large" --filter
"product-description=Linux/UNIX" -H
```

```
Type ReservedInstancesOfferingId AvailabilityZone InstanceType Duration Fixed
Price UsagePrice ProductDescription Currency InstanceTenancy OfferingType
OFFERING 649fd0c8-7d25-4e81-959e-0e1bcexample us-east-1c m1.large 1y 910.0
0.12 Linux/UNIX USD default Medium Utilization
OFFERING 438012d3-278f-4ad6-9cb9-e2318example us-east-1b m1.large 1y 910.0
0.12 Linux/UNIX USD default Medium Utilization
OFFERING 4b2293b4-20f5-4b3d-9969-46341example us-east-1d m1.large 1y 910.0
0.12 Linux/UNIX USD default Medium Utilization
OFFERING 3a98bf7d-abc6-47a0-870e-e2459example us-east-1a m1.large 1y 910.0
0.12 Linux/UNIX USD default Medium Utilization
OFFERING ceb6a579-757c-474b-b09b-52c84example us-east-1c m1.small 1y 227.5
0.03 Linux/UNIX USD default Medium Utilization
OFFERING 60dcfab3-06bb-4b68-9503-53bf8example us-east-1b m1.small 1y 227.5
0.03 Linux/UNIX USD default Medium Utilization
OFFERING 438012d3-80c7-42c6-9396-a209cexample us-east-1d m1.small 1y 227.5
0.03 Linux/UNIX USD default Medium Utilization
OFFERING 649fd0c8-5d76-4881-a522-fe522example us-east-1a m1.small 1y 227.5
0.03 Linux/UNIX USD default Medium Utilization
...
```

Related Operations

- [ec2-purchase-reserved-instances-offering](#) (p. 559)
- [ec2-describe-reserved-instances](#) (p. 367)

ec2-describe-route-tables

Description

Describes one or more of your route tables.

For more information about route tables, see [Route Tables](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2drtb**.

Syntax

```
ec2-describe-route-tables [route_table_id...]
```

Options

Name	Description
<i>route_table_id</i>	One or more route table IDs. Type: String Default: Describes all your route tables. Required: No Example: rtb-7aa34613
<code>-F</code> , <code>--filter name=value</code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value string ("name=value"). Type: String Default: Describes all your route tables, or only those you specified by ID. Required: No Example: <code>--filter "tag-key=Production"</code>

Supported Filters

You can specify filters so that the response includes information for only certain tables. For example, you can use a filter to specify that you're interested in the tables associated with a particular subnet. You can specify multiple values for a filter. The response includes information for a table only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify tables that have a specific route and are associated with a specific subnet. The response includes information for a table only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

association.route-table-association-id

The ID of an association ID for the route table.

Type: String

association.route-table-id

The ID of the route table involved in the association.

Type: String

association.subnet-id

The ID of the subnet involved in the association.

Type: String

association.main

Indicates whether the route table is the main route table for the VPC.

Type: Boolean

route-table-id

The ID of the route table.

Type: String

route.destination-cidr-block

The CIDR range specified in a route in the table.

Type: String

route.gateway-id

The ID of a gateway specified in a route in the table.

Type: String

route.instance-id

The ID of an instance specified in a route in the table.

Type: String

route.origin

Describes how the route was created.

Type: String

Valid values: `CreateRouteTable` | `CreateRoute` | `EnableVgwRoutePropagation`

`CreateRouteTable` indicates that route was automatically created when the route table was created.

`CreateRoute` indicates that the route was manually added to the route table.

`EnableVgwRoutePropagation` indicates that the route was propagated by route propagation.

route.state

The state of a route in the route table. The `blackhole` state indicates that the route's target isn't available (for example, the specified gateway isn't attached to the VPC, the specified NAT instance has been terminated, and so on).

Type: String

Valid values: `active` | `blackhole`

tag-key

The key of a tag assigned to the resource. This filter is independent of the `tag-value` filter. For example, if you use both the filter `tag-key=Purpose` and the filter `tag-value=X`, you get any resources assigned both the tag key `Purpose` (regardless of what the tag's value is), and the tag value `X` (regardless of what the tag's key is). If you want to list only resources where `Purpose` is `X`, see the `tag:key` filter.

For more information about tags, see [Tagging Your Resources](#) in the *Amazon Elastic Compute Cloud User Guide*.

Type: String

tag-value

The value of a tag assigned to the resource. This filter is independent of the `tag-key` filter.

Type: String

tag: *key*

Filters the response based on a specific tag/value combination.

Example: To list just the resources that have been assigned tag Purpose=X, specify:

```
--filter tag:Purpose=X
```

Example: To list just resources that have been assigned tag Purpose=X OR Purpose=Y, specify:

```
--filter tag:Purpose=X --filter tag:Purpose=Y
```

vpc-id

The ID of the VPC for the route table.

Type: String

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>

Option	Description
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The ROUTETABLE identifier
- The ID of the route table
- The ID of the VPC the route table is in
- The ROUTE identifier

- The route's forwarding target (gateway or NAT instance)
- The route's state (`active` or `blackhole`). Blackhole means the route's forwarding target isn't available (for example, the gateway is detached, the NAT instance is terminated)
- The route's destination CIDR range
- The ASSOCIATION identifier
- The association ID representing the association of the route table to a subnet (or to the VPC if it's the main route table)
- Any tags assigned to the route table
- Network interfaces associated with the route.

Amazon EC2 command line tools display errors on `stderr`.

Examples

Example Request

This example describes the route table with ID `rtb-6aa34603`.

```
PROMPT> ec2-describe-route-tables rtb-6aa34603
ROUTE TABLE rtb-6aa34603 vpc-9ea045f7
ec2-describe-route-tables
ROUTE TABLE rtb-7f6e8217 vpc-7d6e8215
ROUTE vgw-56clf422 active 13.4.5.0/24 CreateRoute
ROUTE local active 12.12.12.0/24 CreateRouteTable
ROUTE igw-906e82f8 active 0.0.0.0/0 CreateRoute
ROUTE vgw-56clf422 active 13.0.0.0/8 EnableVgwRoutePropagation
ROUTE vgw-56clf422 active 11.0.0.0/8 EnableVgwRoutePropagation
ROUTE vgw-56clf422 active 10.0.0.0/8 EnableVgwRoutePropagation
PROPAGATINGVGW vgw-56clf422
ASSOCIATION rtbassoc-706e8218 main
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeRouteTables](#)

Related Commands

- [ec2-associate-route-table](#) (p. 29)
- [ec2-delete-route-table](#) (p. 218)
- [ec2-disassociate-route-table](#) (p. 486)
- [ec2-replace-route-table-association](#) (p. 588)

ec2-describe-snapshot-attribute

Description

Describes an attribute of a snapshot. You can specify only one attribute at a time.

The short version of this command is **ec2dsnapatt**.

Syntax

`ec2-describe-snapshot-attribute` *snapshot_id attribute*

Options

Name	Description
<i>snapshot_id</i>	The ID of the Amazon EBS snapshot. Type: String Default: None Required: Yes Example: snap-78a54011
<code>-c, --create-volume-permission</code>	Describes the create volume permissions of the snapshot. If you don't specify this attribute, you must specify another attribute. Type: String Default: None Required: Conditional Example: -c
<code>-p, --product-code</code>	Describes the product codes associated with the snapshot. Each product code contains a product code and a type. If you don't specify this attribute, you must specify another attribute. Type: String Default: None Required: Conditional Example: -p

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the EC2_PRIVATE_KEY environment variable. Example: -K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the EC2_CERT environment variable. Example: -C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem

Output

This command returns a table that contains the following information:

- The attribute type identifier
- The ID of the snapshot
- The attribute value type
- The attribute value

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example describes permissions for the snap-1a2b3c4d snapshot.

```
PROMPT> ec2-describe-snapshot-attribute snap-1a2b3c4d -c
createVolumePermission snap-1a2b3c4d userId 111122223333
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeSnapshotAttribute](#)

Related Commands

- [ec2-create-snapshot](#) (p. 146)
- [ec2-describe-snapshots](#) (p. 395)
- [ec2-modify-snapshot-attribute](#) (p. 545)
- [ec2-reset-snapshot-attribute](#) (p. 618)

ec2-describe-snapshots

Description

Describes one or more of the Amazon EBS snapshots available to you. Snapshots available to you include public snapshots available for any AWS account to launch, private snapshots you own, and private snapshots owned by another AWS account but for which you've been given explicit create volume permissions.

The create volume permissions fall into 3 categories:

Permission	Description
public	The owner of the snapshot granted create volume permissions for the snapshot to the <code>all</code> group. All AWS accounts have create volume permissions for these snapshots.
explicit	The owner of the snapshot granted create volume permissions to a specific AWS account.
implicit	An AWS account has implicit create volume permissions for all snapshots it owns.

You can modify the list of snapshots returned by specifying snapshot IDs, snapshot owners, or AWS accounts with create volume permissions. If you don't specify any options, Amazon EC2 returns all snapshots for which you have create volume permissions.

If you specify one or more snapshot IDs, only snapshots that have the specified IDs are returned. If you specify an invalid snapshot ID, an error is returned. If you specify a snapshot ID for which you do not have access, it will not be included in the returned results.

If you specify one or more snapshot owners, only snapshots from the specified owners and for which you have access are returned. The results can include the AWS account IDs of the specified owners, `amazon` for snapshots owned by Amazon, or `self` for snapshots that you own.

If you specify a list of restorable users, only snapshots with create snapshot permissions for those users are returned. You can specify AWS account IDs (if you own the snapshots), `self` for snapshots for which you own or have explicit permissions, or `all` for public snapshots.

Tip

Use the `--help` option to view examples of ways to use this command.

The short version of this command is `ec2dsnap`.

Syntax

```
ec2-describe-snapshots [snapshot_id ...] [-a] [-o owner ...] [-r user_id]  
[--filter "name=value"] ...]
```


Options

Name	Description
<code>snapshot_id</code>	One or more snapshot IDs. Type: String Default: Describes all snapshots for which you have launch permissions. Required: No Example: snap-78a54011
<code>-a, --all owner</code>	Describe all snapshots (public, private or shared) to which you have access. Type: String Default: None Required: No Example: -a
<code>-o, --owner owner</code>	Describes snapshots owned by the specified owner. Multiple owners can be specified. Type: String Valid values: <code>self</code> <code>amazon</code> <i>AWS account ID</i> Default: None Required: No Example: -o AKIAIOSFODNN7EXAMPLE
<code>-r, --restorable-by user_id</code>	The ID of an AWS account that can create volumes from the snapshot. Type: String Valid values: <code>self</code> <code>all</code> an AWS account ID Default: None Required: No Example: -r self
<code>-F, --filter name=value</code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value string ("name=value"). Type: String Default: Describes all snapshots for which you have launch permissions, or only those you specified by ID. Required: No Example: --filter "tag-key=Production"

Supported Filters

You can specify filters so that the response includes information for only certain snapshots. For example, you can use a filter to specify that you're interested in snapshots whose status is `pending`. You can specify multiple values for a filter. The response includes information for a snapshot only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify snapshot's that have a `pending` status, and have a specific tag. The response includes information for a snapshot only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

description

A description of the snapshot.

Type: String

owner-alias

The AWS account alias (for example, `amazon`) that owns the snapshot.

Type: String

owner-id

The ID of the AWS account that owns the snapshot.

Type: String

progress

The progress of the snapshot, as a percentage (for example, `80%`).

Type: String

snapshot-id

The snapshot ID.

Type: String

start-time

The time stamp when the snapshot was initiated.

Type: DateTime

status

The status of the snapshot.

Type: String

Valid values: `pending` | `completed` | `error`

tag-key

The key of a tag assigned to the resource. This filter is independent of the `tag-value` filter. For example, if you use both the filter `"tag-key=Purpose"` and the filter `"tag-value=X"`, you get any resources assigned both the tag key `Purpose` (regardless of what the tag's value is), and the tag value `X` (regardless of what the tag's key is). If you want to list only resources where `Purpose` is `X`, see the `tag:key` filter.

For more information about tags, see [Tagging Your Resources](#) in the *Amazon Elastic Compute Cloud User Guide*.

Type: String

tag-value

The value of a tag assigned to the resource. This filter is independent of the `tag-key` filter.

Type: String

tag:key

Filters the response based on a specific tag/value combination.

Example: To list just the resources that have been assigned tag `Purpose=X`, specify:

```
--filter tag:Purpose=X
```

Example: To list just resources that have been assigned tag `Purpose=X` OR `Purpose=Y`, specify:

```
--filter tag:Purpose=X --filter tag:Purpose=Y
```

volume-id

The ID of the volume the snapshot is for.

Type: String

volume-size

The size of the volume, in GiB (for example, 20).

Type: String

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.

Option	Description
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

1. The snapshot information
 - The SNAPSHOT identifier
 - The ID of the snapshot
 - The ID of the volume
 - The state of the snapshot (`pending`, `completed`, `error`)
 - The time stamp when the snapshot initiated
 - The percentage of completion
 - The ID of the snapshot owner
 - The size of the volume
 - The description of the snapshot

2. Any tags associated with the snapshot

- The TAG identifier
- The resource type identifier
- The resource ID
- The tag key
- The tag value

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example describes snapshot `snap-1a2b3c4d`.

```
PROMPT> ec2-describe-snapshots snap-1a2b3c4d
SNAPSHOT snap-1a2b3c4d vol-1a2b3c4d completed YYYY-MM-DDTHH:MM:SS.SSSZ 100%
111122223333 15 Daily Backup
TAG snapshot snap-1a2b3c4d Name Test
```

Example Request

This example filters the response to include only snapshots with the `pending` status, and that are also tagged with a value that includes the string `db_`.

```
PROMPT> ec2-describe-snapshots --filter "status=pending" --filter "tag-value=*db_*"
SNAPSHOT snap-1a2b3c4d vol-1a2b3c4d pending YYYY-MM-DDTHH:MM:SS.SSSZ 30%
111122223333 15 demo_db_14_backup
TAG snapshot snap-1a2b3c4d Purpose db_14
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeSnapshots](#)

Related Commands

- [ec2-create-snapshot](#) (p. 146)
- [ec2-delete-snapshot](#) (p. 221)

ec2-describe-spot-datafeed-subscription

Description

Describes the datafeed for Spot Instances. For more information about Spot Instances, see [Spot Instances](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2dsds**.

Syntax

```
ec2-describe-spot-datafeed-subscription
```

Options

This command does not have any options.

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-T, --security-token</code> <code>TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <code>TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <code>TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <code>EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <code>EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The SPOTDATAFEEDSUBSCRIPTION identifier
- The AWS account ID of the owner
- The Amazon S3 bucket where the data feed is located
- The prefix for the data feed files
- The state (`Active` | `Inactive`)

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example describes the datafeed for the account.

```
PROMPT> ec2-describe-spot-datafeed-subscription  
SPOTDATAFEEDSUBSCRIPTION 111122223333 myawsbucket spotdata_ Active
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeSpotDatafeedSubscription](#)

Related Commands

- [ec2-create-spot-datafeed-subscription](#) (p. 150)
- [ec2-delete-spot-datafeed-subscription](#) (p. 224)

ec2-describe-spot-instance-requests

Description

Describes the Spot Instance requests that belong to your account. Spot Instances are instances that Amazon EC2 starts on your behalf when the maximum price that you specify exceeds the current Spot Price. Amazon EC2 periodically sets the Spot Price based on available Spot Instance capacity and current Spot Instance requests. For more information about Spot Instances, see [Spot Instances](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2dsir**.

Syntax

```
ec2-describe-spot-instance-requests [request_id ...] [--filter "name=value"] ...]
```

Options

Name	Description
<i>request_id</i>	The ID of the Spot Instance request. Type: String Default: None Required: No Example: <code>sir-1a2b3c4d</code>
<code>-F, --filter name=value</code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space (" <code>name=value example</code> "). On a Windows system, use quotation marks even without a space in the value string (" <code>name=value</code> "). Type: String Default: Describes all your Spot Instance requests, or those you specified by ID. Required: No Example: <code>--filter "tag-key=Production"</code>

Supported Filters

You can specify filters so that the response includes information for only certain Spot Instance requests. For example, you can use a filter to specify that you're interested in requests where the Spot Price is a specific value. (You can't use a greater than or less than comparison, however you can use `*` and `?` wildcards.) You can specify multiple values for a filter. The response includes information for a Spot Instance request only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify that the Spot Price is a specific value, and that the instance type is `m1.small`. The response includes information for a request only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

availability-zone-group

The Availability Zone group. If you specify the same Availability Zone group for all Spot Instance requests, all Spot Instances are launched in the same Availability Zone.

Type: String

create-time

The time stamp when the Spot Instance request was created.

Type: String

fault-code

The fault code related to the request.

Type: String

fault-message

The fault message related to the request.

Type: String

instance-id

The ID of the instance that fulfilled the request.

Type: String

launch-group

The Spot Instance launch group. Launch groups are Spot Instances that launch together and terminate together.

Type: String

launch.block-device-mapping.delete-on-termination

Whether the Amazon EBS volume is deleted on instance termination.

Type: Boolean

launch.block-device-mapping.device-name

The device name (for example, `/dev/sdh`) for the Amazon EBS volume.

Type: String

launch.block-device-mapping.snapshot-id

The ID of the snapshot used for the Amazon EBS volume.

Type: String

launch.block-device-mapping.volume-size

The volume size of the Amazon EBS volume, in GiB.

Type: String

launch.block-device-mapping.volume-type

The volume type of the Amazon EBS volume.

Type: String

Valid values: `standard` | `io1`

launch.group-id

The security group for the instance.

Type: String

launch.image-id

The ID of the AMI.

Type: String

launch.instance-type

The type of instance (for example, `m1.small`).

Type: String

- launch.kernel-id**
The kernel ID.
Type: String
- launch.key-name**
The name of the key pair the instance launched with.
Type: String
- launch.monitoring-enabled**
Whether monitoring is enabled for the Spot Instance.
Type: Boolean
- launch.ramdisk-id**
The RAM disk ID.
Type: String
- launch.network-interface.network-interface-id**
The ID of the network interface.
Type: String
- launch.network-interface.device-index**
The index of the device for the network interface attachment on the instance.
Type: Integer
- launch.network-interface.subnet-id**
The ID of the subnet for the instance.
Type: String
- launch.network-interface.description**
A description of the network interface.
Type: String
- launch.network-interface.private-ip-address**
The primary private IP address of the network interface.
Type: String
- launch.network-interface.delete-on-termination**
Indicates whether the network interface is deleted when the instance is terminated.
Type: Boolean
- launch.network-interface.group-id**
The ID of the security group associated with the network interface.
Type: String
- launch.network-interface.group-name**
The name of the security group associated with the network interface.
Type: String
- launch.network-interface.addresses.primary**
Indicates whether the IP address is the primary private IP address.
Type: String
- product-description**
The product description associated with the instance.
Type: String
Valid values: Linux/UNIX | Windows
- spot-instance-request-id**
The Spot Instance request ID.
Type: String
- spot-price**
The maximum hourly price for any Spot Instance launched to fulfill the request.
Type: String

state

The state of the Spot Instance request. Spot bid status information can help you track your Amazon EC2 Spot Instance requests. For information, see [Tracking Spot Requests with Bid Status Codes](#) in the *Amazon Elastic Compute Cloud User Guide*.

Type: String

Valid values: open | active | closed | cancelled | failed

status-code

The short code describing the most recent evaluation of your Spot Instance request. For more information, see [Spot Bid Status](#) in the *Amazon Elastic Compute Cloud User Guide*.

Type: String

status-message

The message explaining the status of the Spot Instance request.

Type: String

tag-key

The key of a tag assigned to the resource. This filter is independent of the `tag-value` filter. For example, if you use both the filter `tag-key=Purpose` and the filter `tag-value=X`, you get any resources assigned both the tag key `Purpose` (regardless of what the tag's value is), and the tag value `X` (regardless of what the tag's key is). If you want to list only resources where `Purpose` is `X`, see the `tag:key` filter.

For more information about tags, see [Tagging Your Resources](#) in the *Amazon Elastic Compute Cloud User Guide*.

Type: String

tag-value

The value of a tag assigned to the resource. This filter is independent of the `tag-key` filter.

Type: String

tag:key

Filters the response based on a specific tag/value combination.

Example: To list just the resources that have been assigned tag `Purpose=X`, specify:

```
--filter tag:Purpose=X
```

Example: To list just resources that have been assigned tag `Purpose=X` OR `Purpose=Y`, specify:

```
--filter tag:Purpose=X --filter tag:Purpose=Y
```

type

The type of Spot Instance request.

Type: String

Valid values: one-time | persistent

launched-availability-zone

The Availability Zone in which the bid is launched.

Type: String

valid-from

The start date of the request.

Type: DateTime

valid-until

The end date of the request.

Type: DateTime

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.

Option	Description
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

The Spot Instance request information

- The SPOTINSTANCEREQUEST identifier
- The ID of the Spot Instance request
- The Spot Instance bid price
- The Spot Instance type (*one-time or persistent*)
- The product description (*Linux/UNIX or Windows*)
- The state of the Spot Instance request (*active, open, closed, cancelled, failed*)
- The date and time the request was created
- The date and time that the request is valid until
- The date and time the request will be held until
- The launch group
- The Availability Zone group
- The instance ID
- The image ID

- The instance type
- The key pair name
- Any security groups the request belongs to
- The Availability Zone the instance belongs to
- The kernel ID of the instance
- The RAM disk ID of the instance
- The monitoring status
- The subnet ID
- The Availability Zone the instance was launched to
- The IAM profile

Any Spot Instance faults

- The SPOTINSTANCEFAULT identifier
- The Spot Instance fault code
- The Spot Instance fault message

The Spot Instance status information

- The SPOTINSTANCESTATUS identifier
- The Spot Instance status
- The date and time of the last update
- The Spot Instance status message

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example returns information about all of your Spot Instance requests.

```
PROMPT> ec2-describe-spot-instance-requests
SPOTINSTANCEREQUEST sir-1a2b3c4d 0.040000 one-time Linux/UNIX active YYYY-MM-
DDTHH:MM:SS-0800 i-1a2b3c4d ami-1a2b3c4d m1.small gsg-keypair sg-1a2b3c4d
monitoring-disabled us-west-2c
SPOTINSTANCESTATUS fulfilled YYYY-MM-DDTHH:MM:SS-0800 Your Spot request is
fulfilled.
SPOTINSTANCEREQUEST sir-2a2b3c4d 0.040000 one-time Linux/UNIX active YYYY-MM-
DDTHH:MM:SS-0800 i-2a2b3c4d ami-1a2b3c4d m1.small gsg-keypair sg-1a2b3c4d
monitoring-disabled us-west-2c
SPOTINSTANCESTATUS fulfilled YYYY-MM-DDTHH:MM:SS-0800 Your Spot request is
fulfilled.
SPOTINSTANCEREQUEST sir-3a2b3c4d 0.040000 one-time Linux/UNIX active YYYY-MM-
DDTHH:MM:SS-0800 i-3a2b3c4d ami-1a2b3c4d m1.small gsg-keypair sg-1a2b3c4d
monitoring-disabled us-west-2c
SPOTINSTANCESTATUS fulfilled YYYY-MM-DDTHH:MM:SS-0800 Your Spot request is
fulfilled.
```

Example Request

This example describes all persistent Spot Instance requests that have resulted in the launch of at least one m1.small instance, that has been fulfilled in the us-east-1a Availability Zone, and that also has monitoring enabled.

```
PROMPT> ec2-describe-spot-instance-requests --filter "type=persistent" --filter  
"launch.instance-type=m1.small" --filter "launch.monitoring-enabled=true"
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeSpotInstanceRequests](#)

Related Commands

- [ec2-cancel-spot-instance-requests](#) (p. 75)
- [ec2-describe-spot-price-history](#) (p. 412)
- [ec2-request-spot-instances](#) (p. 597)

ec2-describe-spot-price-history

Description

Describes the Spot Price history. Spot Instances are instances that Amazon EC2 starts on your behalf when the maximum price that you specify exceeds the current Spot Price. Amazon EC2 periodically sets the Spot Price based on available Spot Instance capacity and current Spot Instance requests. For more information about Spot Instances, see [Spot Instances](#) in the *Amazon Elastic Compute Cloud User Guide*.

When you use the `availability-zone` option, this command describes the price history for the specified Availability Zone with the most recent set of prices listed first. If you don't specify an Availability Zone, the command returns the prices across all Availability Zones, starting with the most recent set. However, if you use this command with versions of the API earlier than the 2011-05-15 version, this command returns the lowest price across the region for the given time period. The prices returned are listed in chronological order — from the oldest to the most recent.

The short version of this command is `ec2dsph`.

Syntax

```
ec2-describe-spot-price-history [--start-time timestamp] [--end-time timestamp]
[--instance-type type] [--product-description description] [--filter
"name=value"] ...] [--availability-zone zone]
```

Options

Name	Description
<code>-s, --start-time <i>timestamp</i></code>	The start date and time of the Spot Instance price history data. Type: DateTime Default: None Required: No Example: <code>-s 2009-12-01T11:51:50.000Z</code>
<code>-e, --end-time <i>timestamp</i></code>	The end date and time of the Spot Instance price history data. Type: DateTime Default: None Required: No Example: <code>-e 2009-12-31T11:51:50.000Z</code>
<code>-t, --instance-type <i>type</i></code>	The instance type to return. Type: String Valid values: <code>t1.micro m1.small m1.medium m1.large m1.xlarge m3.xlarge m3.2xlarge c1.medium c1.xlarge m2.xlarge m2.2xlarge m2.4xlarge cr1.8xlarge cc1.4xlarge cc2.8xlarge cg1.4xlarge</code> . See Available Instance Types for more information. Default: None Required: No Example: <code>-t m1.large</code>

Name	Description
<code>-d, --product-description <i>description</i></code>	Filters the results by basic product description. Type: String Valid values: Linux/UNIX SUSE Linux Windows Linux/UNIX (Amazon VPC) SUSE Linux (Amazon VPC) Windows (Amazon VPC) Default: None Required: No Example: <code>-d Linux/UNIX</code>
<code>-F, --filter <i>name=value</i></code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space (" <code>name=value example</code> "). On a Windows system, use quotation marks even without a space in the value string (" <code>name=value</code> "). Type: String Default: Lists all available history information, or just the information you requested. Required: No Example: <code>--filter "product-description=Linux/UNIX"</code>
<code>-a, --availability-zone <i>zone</i></code>	The Availability Zone for which you want to get the price history. Type: String Default: None Required: No Example: <code>-a us-east-1a</code>

Supported Filters

Note

Our policy is to provide filters for all `ec2-describe` calls so you can limit the response to your specified criteria. Therefore, you can use filters to limit the response when describing Spot Price histories, even though you can use the options instead.

For example, you could use an option or a filter to get the history for a particular instance type. You can specify multiple request parameters or filters (for example, limit the response to the `m2.xlarge` instance type, and only for Windows instances). The response includes information for a price history only if it matches all your options or filters. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

instance-type

The type of instance (for example, `m1.small`).

Type: String

product-description

The product description for the Spot Price.

Type: String

Valid values: Linux/UNIX | SUSE Linux | Windows | Linux/UNIX (Amazon VPC) | SUSE Linux (Amazon VPC) | Windows (Amazon VPC)

spot-price

The Spot Price. The value must match exactly (or use wildcards; greater than or less than comparison is not supported).

Type: String

timestamp

The timestamp of the Spot Price history (for example, 2010-08-16T05:06:11.000Z). You can use wildcards (* and ?). Greater than or less than comparison is not supported.

Type: DateTime

availability-zone

The Availability Zone for which prices should be returned.

Type: String

Common Options

Option	Description
<code>--region REGION</code>	<p>Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option.</p> <p>Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set.</p> <p>Example: <code>--region eu-west-1</code></p>
<code>-U, --url URL</code>	<p>The uniform resource locator (URL) of the Amazon EC2 web service entry point.</p> <p>Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set.</p> <p>Example: <code>-U https://ec2.amazonaws.com</code></p>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>

Option	Description
<code>--connection-timeout</code> <i>TIMEOUT</i>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The `SPOTINSTANCEPRICE` identifier

- The Spot Instance price
- The date and time of the request
- The instance type
- The product description (for example, Linux/UNIX)
- The Availability Zone (for example, us-east-1a)

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example returns Spot Price history for `m1.xlarge` instances for a particular day in May.

```
PROMPT> ec2-describe-spot-price-history -H --instance-type m1.xlarge --start-time 2011-05-06T07:08:09 --end-time 2011-05-06T08:09:10
Type Price Timestamp InstanceType ProductDescription AvailabilityZone
SPOTINSTANCEPRICE 0.417000 2011-05-06T05:54:03-0800 m1.xlarge Windows us-east-1b
SPOTINSTANCEPRICE 0.417000 2011-05-06T05:54:03-0800 m1.xlarge Windows us-east-1d
SPOTINSTANCEPRICE 0.417000 2011-05-06T05:54:03-0800 m1.xlarge Windows us-east-1a
...
```

The following example uses filters instead of request options to get the same results.

```
PROMPT> ec2-describe-spot-price-history -H --instance-type m1.xlarge --start-time 2011-05-06T07:08:09 --end-time 2011-05-06T08:09:10 --product-description 'Linux/UNIX'
Type Price Timestamp InstanceType ProductDescription AvailabilityZone
SPOTINSTANCEPRICE 0.234000 2011-05-06T05:08:03-0800 m1.xlarge Linux/UNIX us-east-1b
SPOTINSTANCEPRICE 0.234000 2011-05-06T05:08:03-0800 m1.xlarge Linux/UNIX us-east-1c
SPOTINSTANCEPRICE 0.234000 2011-05-06T05:08:03-0800 m1.xlarge Linux/UNIX us-east-1d
...
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeSpotPriceHistory](#)

Related Commands

- [ec2-cancel-spot-instance-requests](#) (p. 75)
- [ec2-describe-spot-instance-requests](#) (p. 404)
- [ec2-request-spot-instances](#) (p. 597)

ec2-describe-subnets

Description

Describes one or more of your subnets.

The short version of this command is **ec2ds subnet**.

Syntax

```
ec2-describe-subnets [ subnet_id ... ] [--filter "name=value" ...]
```

Options

Name	Description
<i>subnet_id</i>	One or more subnet IDs. Type: String Default: Describes all your subnets. Required: No Example: subnet-9d4a7b6c
<code>-F, --filter name=value</code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value string ("name=value"). Type: String Default: Describes all your subnets, or only those you specified by ID. Required: No Example: --filter "tag-key=Production"

Supported Filters

You can specify filters so that the response includes information for only certain subnets. For example, you can use a filter to specify that you're interested in the subnets in the `available` state. You can specify multiple values for a filter. The response includes information for a subnet only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify subnets that are in a specific VPC and are in the `available` state. The response includes information for a subnet only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?.`

The following are the available filters.

availability-zone

The Availability Zone for the subnet.

Type: String

available-ip-address-count

The number of IP addresses in the subnet that are available.

Type: String

cidr

The CIDR block of the subnet. The CIDR block you specify must exactly match the subnet's CIDR block for information to be returned for the subnet.

Type: String

Constraints: Must contain the slash followed by one or two digits (for example, /28)

defaultForAz

Indicates whether this is the default subnet for the Availability Zone.

Type: Boolean

state

The state of the subnet.

Type: String

Valid values: pending | available

subnet-id

The ID of the subnet.

Type: String

tag-key

The key of a tag assigned to the resource. This filter is independent of the `tag-value` filter. For example, if you use both the filter "tag-key=Purpose" and the filter "tag-value=X", you get any resources assigned both the tag key `Purpose` (regardless of what the tag's value is), and the tag value `X` (regardless of what the tag's key is). If you want to list only resources where Purpose is `X`, see the `tag:key` filter.

For more information about tags, see [Tagging Your Resources](#) in the *Amazon Elastic Compute Cloud User Guide*.

Type: String

tag-value

The value of a tag assigned to the resource. This filter is independent of the `tag-key` filter.

Type: String

tag:key

Filters the response based on a specific tag/value combination.

Example: To list just the resources that have been assigned tag Purpose=X, specify:

```
--filter tag:Purpose=X
```

Example: To list just resources that have been assigned tag Purpose=X OR Purpose=Y, specify:

```
--filter tag:Purpose=X --filter tag:Purpose=Y
```

vpc-id

The ID of the VPC for the subnet.

Type: String

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.

Option	Description
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information for each subnet:

- The SUBNET identifier
- The ID of the subnet
- The current state of the subnet (`pending` or `available`)
- The ID of the VPC the subnet is in
- The CIDR block assigned to the subnet
- The number of IP addresses in the subnet that are available
- The Availability Zone the subnet is in
- Default subnet for the Availability Zone (`true` or `false`)
- Instances launched in this subnet receive a public IP address (`true` or `false`)
- Any tags assigned to the subnet

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example gives a description of two subnets with IDs `subnet-9d4a7b6c` and `subnet-6e7f829e`.

```
PROMPT> ec2-describe-subnets subnet-9d4a7b6c subnet-6e7f829e
SUBNET subnet-9d4a7b6c available vpc-1a2b3c4d 10.0.1.0/24 251 us-east-
1a false false
SUBNET subnet-6e7f829e available vpc-1a2b3c4d 10.0.0.0/24 251 us-east-
1a false false
```

Example Request

This example uses filters to give a description of any subnet you own that is in the VPC with ID `vpc-1a2b3c4d` or `vpc-6e7f8a92`, and whose state is `available`. The response indicates that the VPC with ID `vpc-6e7f8a92` doesn't have any subnets that match.

```
PROMPT> ec2-describe-subnets --filter "vpc-id=vpc-1a2b3c4d" --filter "vpc-id=vpc-
6e7f8a92" --filter "state=available"
SUBNET subnet-9d4a7b6c available vpc-1a2b3c4d 10.0.1.0/24 251 us-east-
1a false false
SUBNET subnet-6e7f829e available vpc-1a2b3c4d 10.0.0.0/24 251 us-east-
1a false false
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeSubnets](#)

Related Commands

- [ec2-create-subnet](#) (p. 154)
- [ec2-delete-subnet](#) (p. 227)

ec2-describe-tags

Description

Describes one or more of the tags for your EC2 resources. For more information about tags, see [Tagging Your Resources](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2dtag**.

Syntax

```
ec2-describe-tags [--filter "name=value"] ...]
```

Options

Name	Description
<code>-F, --filter name=value</code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value string ("name=value"). Type: String Default: Describes all tags for your EC2 resources. Required: No Example: <code>--filter "resource-type=instance"</code>

Supported Filters

You can specify filters to limit the response when describing tags. For example, you can use a filter to get only the tags for a specific resource type. You can specify multiple values for a filter. The response includes information for a tag only if it matches at least one of the filter values that you specified.

You can specify multiple filters (for example, specify a specific resource type and tag values that contain the string `database`). The response includes information for a tag only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?`.

The following are the available filters.

key

The tag key.

Type: String

resource-id

The resource ID.

Type: String

resource-type

The resource type.

Type: String

Valid values: customer-gateway | dhcp-options | image | instance | internet-gateway | network-acl | network-interface | reserved-instances | route-table | security-group | snapshot | spot-instances-request | subnet | volume | vpc | vpn-connection | vpn-gateway

value

The tag value.

Type: String

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>

Option	Description
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The TAG identifier
- The resource type identifier
- The resource ID
- The tag key
- The tag value

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example describes all your tags.

```
PROMPT> ec2-describe-tags
TAG ami-1a2b3c4d image webserver
TAG ami-1a2b3c4d image stack Production
TAG i-5f4e3d2a instance webserver
TAG i-5f4e3d2a instance stack Production
TAG i-12345678 instance database_server
TAG i-12345678 instance stack Test
```

Example Request

This example describes the tags for your resource with ID ami-1a2b3c4d.

```
PROMPT> ec2-describe-tags --filter "resource-id=ami-1a2b3c4d"
TAG ami-1a2b3c4d image webserver
TAG ami-1a2b3c4d image stack Production
```

Example Request

This example describes the tags for all your instances.

```
PROMPT> ec2-describe-tags --filter "resource-type=instance"
TAG i-5f4e3d2a instance webserver
TAG i-5f4e3d2a instance stack Production
TAG i-12345678 instance database_server
TAG i-12345678 instance stack Test
```

Example Request

This example describes the tags for all your instances that have a tag with the key `webserver`.

```
PROMPT> ec2-describe-tags --filter "resource-type=instance" --filter "key=web
server"
TAG i-5f4e3d2a instance webserver
```

Example Request

This example describes the tags for all your instances that have a tag with the key `stack` and a value of either `Test` or `Production`.

```
PROMPT> ec2-describe-tags --filter "resource-type=instance" --filter "key=stack"
--filter "value=Test" --filter "value=Production"
TAG i-5f4e3d2a instance stack Production
TAG i-12345678 instance stack Test
```

Example Request

This example describes the tags for all your instances that have a tag with the key `Purpose` and no value.

```
PROMPT> ec2-describe-tags --filter "resource-type=instance" --filter "key=Purpose" --filter "value="
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeTags](#)

Related Commands

- [ec2-create-tags](#) (p. 158)
- [ec2-delete-tags](#) (p. 230)

ec2-describe-volume-attribute

Description

Describes an attribute of a volume. You can specify only one attribute at a time.

Currently, volumes have two attributes: `auto-enable-io` and `product-code`.

The short version of this command is `ec2dvolatt`.

Syntax

`ec2-describe-volume-attribute` *volume_id* ... *attribute*

Options

Name	Description
<i>volume_id</i>	The ID of the volume. Type: String Required: Yes Example: vol-4282672b
<i>attribute</i>	The instance attribute. Type: String Default: None Valid values: [--auto-enable-io --product-code] or [-a -p] Required: Yes Example: --auto-enable-io Example: -p

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The ID of the volume
- Information about the attribute

Amazon EC2 command line tools display errors on stderr.

Example

Example Request

This example describes the `autoEnableIo` attribute of the volume `vol-999999`.

```
PROMPT> ec2-describe-volume-attribute vol-999999 -a  
VolumeId      Attribute  
vol-999999    autoEnableIo  
AUTO-ENABLE-IO true
```

Example Request

This example describes the `productCodes` attribute of the volume `vol-777777`.

```
PROMPT> ec2-describe-volume-attribute vol-777777 -p  
VolumeId      Attribute  
vol-777777    productCodes  
PRODUCT_CODES [marketplace: a1b2c3d4e5f6g7h8i9j10k11]
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeVolumeAttribute](#)

Related Commands

- [ec2-describe-volume-status](#) (p. 432)
- [ec2-enable-volume-io](#) (p. 490)
- [ec2-modify-volume-attribute](#) (p. 549)

ec2-describe-volume-status

Description

Describes the status of one or more volumes. Volume status provides the result of the checks performed on your volumes to determine events that can impair the performance of your volumes. The performance of a volume can be affected if an issue occurs on the volume's underlying host. If the volume's underlying host experiences a power outage or system issue, once the system is restored, there could be data inconsistencies on the volume. Volume events notify you if this occurs. Volume action notifies you if any action needs to be taken in response to the event.

The `DescribeVolumeStatus` operation provides the following information about the specified volumes:

Status: Reflects the current status of the volume. The possible values are `ok`, `impaired`, or `insufficient-data`. If all checks pass, the overall status of the volume is `ok`. If the check fails, the overall status is `impaired`. If the status is `insufficient-data`, then the checks may still be taking place on your volume at the time. We recommend you retry the request. For more information on volume status, see [Monitoring the Status of Your Volumes](#).

Events: Reflect the cause of a volume status and may require you to take an action. For example, if your volume returns an `impaired` status, then the volume event might be `potential-data-inconsistency`. This means that your volume has been impacted by an issue with the underlying host, has all I/O operations disabled, and may have inconsistent data.

Actions: Reflect the actions you may have to take in response to an event. For example, if the status of the volume is `impaired` and the volume event shows `potential-data-inconsistency`, then the action will show `enable-volume-io`. This means that you may want to enable the I/O operations for the volume by issuing the [ec2-enable-volume-io](#) (p. 490) command and then check the volume for data consistency.

Note

Volume status is based on the volume status checks, and does not reflect the volume state. Therefore, volume status does not indicate volumes in the `error` state (for example, when a volume is incapable of accepting I/O.)

The short version of this command is `ec2dvs`.

Syntax

```
ec2-describe-volume-status [volume_id ...] [--filter "name=value"] ...]
```

Options

Name	Description
<i>volume_id</i>	One or more volume IDs. Type: String Default: Describes the status of all your volumes. Required: No Example: vol-4282672b

Name	Description
<code>-F, --filter name=value</code>	<p>A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value string ("name=value").</p> <p>Type: String</p> <p>Default: Describes all your volumes, or only those you specified by ID.</p> <p>Required: No</p> <p>Example: <code>--filter "volume-status.status=Ok"</code></p>

Supported Filters

You can specify filters so that the response includes information for only certain volumes. For example, you can use a filter to specify that you're interested in volumes that have `impaired` status. You can specify multiple values for a filter. The response includes information for a volume only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify volumes that are in a specific Availability Zone and have the status `impaired`. The response includes information for a volume only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

availability-zone

The Availability Zone of the instance.

Type: String

volume-status.status

The status of the volume.

Type: String

Valid values: `ok` | `impaired` | `warning` | `insufficient-data`

volume-status.details-name

The cause for the `volume-status.status`.

Type: String

Valid values: `io-enabled` | `io-performance`

volume-status.details-status

The status of the `volume-status.details-name`.

Type: String

Valid values for `io-enabled`: `passed` | `failed`

Valid values for `io-performance`: `normal` | `degraded` | `severely-degraded` | `stalled`

event.description

A description of the event.

Type: String

event.not-after

The latest end time for the event.

Type: DateTime

event.not-before
The earliest start time for the event.
Type: DateTime

event.event-id
The event ID.
Type: String

event.event-type
The event type.
Type: String
Valid values for io-enabled: potential-data-inconsistency
Valid values for io-performance: io-performance:degraded | io-performance:severely-degraded | io-performance:stalled

action.code
The action code for the event, for example, enable-volume-io
Type: String

action.event-id
The event ID associated with the action.
Type: String

action.description
A description of the action.
Type: String

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The VOLUME identifier
- The ID of the volume
- The Availability Zone in which the volume launched
- The volume status name (Ok, impaired, io-enabled, insufficient-data)
- The EVENT identifier
- The ID of the event
- The event type (potential-data-inconsistencies)
- The description of the event
- notBefore (the earliest start time of the event)
- notAfter (the latest end time of the event)
- The ACTION identifier
- The action code (enable-volume-io)
- The ID of the event associated with the action
- The event type associated with the action (potential-data-inconsistency)
- The description of the event associated with the action

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example describes the status of the volumes vol-111111 and vol-222222.

```
PROMPT> ec2-describe-volume-status vol-111111 vol-222222
Type          VolumeId  AvailabilityZone  VolumeStatus
VOLUME       vol-111111 us-east-1a       ok
VOLUME       vol-222222 us-east-1b       impaired
Type          Name      Status
VOLUMESTATUS io-enabled failed
Type  EventType      NotBefore          NotAfter  EventId  EventDescription
EVENT potential-data-inconsistency 2011-12-01T14:00:00.000Z          evol-61a54008 This is an example
Type  ActionCode          EventId  EventType
      EventDescription
ACTION enable-volume-io          evol-61a54008 potential-data-inconsistency
      This is an example
```

Example Request

This example describes the volumes associated with your account that have failing I/O operations.

```
PROMPT> ec2-describe-volume-status --filter "volume-status.details-name=io-enabled" --filter "volume-status.details-status=failed"
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeVolumeStatus](#)

Related Commands

- [ec2-describe-volume-attribute](#) (p. 428)
- [ec2-enable-volume-io](#) (p. 490)
- [ec2-modify-volume-attribute](#) (p. 549)

ec2-describe-volumes

Description

Describes one or more of your Amazon EBS volumes. For more information about Amazon EBS, see [Amazon Elastic Block Store](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2dvol**.

Syntax

```
ec2-describe-volumes [volume_id ...] [--filter "name=value"] ...]
```

Options

Name	Description
<i>volume_id</i>	One or more volume IDs. Type: String Default: Describes all your volumes. Required: No Example: vol-4282672b
-F, --filter <i>name=value</i>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space (" <i>name=value example</i> "). On a Windows system, use quotation marks even without a space in the value string (" <i>name=value</i> "). Type: String Default: Describes all your volumes, or only those you specified by ID. Required: No Example: --filter "tag-key=Production"

Supported Filters

You can specify filters so that the response includes information for only certain volumes. For example, you can use a filter to specify that you're interested in volumes whose status is `available`. You can specify multiple values for a filter. The response includes information for a volume only if it matches at least one of the filter values that you specified.

You can specify multiple filters (for example, specify that the volume is `available`, and has a specific tag). The response includes information for a volume only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

attachment.attach-time

The time stamp when the attachment initiated.

Type: DateTime

attachment.delete-on-termination

Whether the volume is deleted on instance termination.

Type: Boolean

attachment.device

The device name that is exposed to the instance (for example, /dev/sda1).

Type: String

attachment.instance-id

The ID of the instance the volume is attached to.

Type: String

attachment.status

The attachment state.

Type: String

Valid values: attaching | attached | detaching | detached

availability-zone

The Availability Zone in which the volume was created.

Type: String

create-time

The time stamp when the volume was created.

Type: DateTime

size

The size of the volume, in GiB (for example, 20).

Type: String

snapshot-id

The snapshot from which the volume was created.

Type: String

status

The status of the volume.

Type: String

Valid values: creating | available | in-use | deleting | deleted | error

tag-key

The key of a tag assigned to the resource. This filter is independent of the `tag-value` filter. For example, if you use both the filter `tag-key=Purpose` and the filter `tag-value=X`, you get any resources assigned both the tag key `Purpose` (regardless of what the tag's value is), and the tag value `X` (regardless of what the tag's key is). If you want to list only resources where `Purpose` is `X`, see the `tag:key` filter.

For more information about tags, see [Tagging Your Resources](#) in the *Amazon Elastic Compute Cloud User Guide*.

Type: String

tag-value

The value of a tag assigned to the resource. This filter is independent of the `tag-key` filter.

Type: String

tag:key

Filters the response based on a specific tag/value combination.

Example: To list just the resources that have been assigned tag `Purpose=X`, specify:

```
--filter tag:Purpose=X
```

Example: To list just resources that have been assigned tag `Purpose=X` OR `Purpose=Y`, specify:

```
--filter tag:Purpose=X --filter tag:Purpose=Y
```

volume-id

The volume ID.

Type: String

volume-type

The Amazon EBS volume type. If the volume is an `io1` volume, the response includes the IOPS as well.

Type: String

Valid values: `standard` | `io1`

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>

Option	Description
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The volume information
 - The VOLUME identifier
 - The ID of the volume
 - The size of the volume, in GiBs
 - The ID of the snapshot the volume was created from
 - The Availability Zone of the volume
 - The volume status (`creating`, `available`, `in-use`, `deleting`, `deleted`, `error`)

- The time stamp when volume creation was initiated
 - The EBS volume type
 - The I/O operations per second (IOPS) of a provisioned IOPS volume
2. Any attachments for the volume
 - The ATTACHMENT identifier
 - The ID of the volume
 - The ID of the instance
 - The device name
 - The attachment state of the volume
 - The time stamp of the last operation on the volume
 - Whether or not the volume is set to delete on termination (`true` or `false`)
 3. Any tags associated with the volume
 - The TAG identifier
 - The resource type identifier
 - The resource ID
 - The tag key
 - The tag value

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example uses the `ec2-describe-volumes` command to describe all volumes associated with your account.

```
PROMPT> ec2-describe-volumes
VOLUME vol-1a2b3c4d 30 snap-1a2b3c4d us-west-2a available YYYY-MM-
DDTHH:MM:SS+0000 standard
TAG volume vol-1a2b3c4d Name Volume Name
VOLUME vol-2a2b3c4d 8 snap-2a2b3c4d us-west-2a in-use YYYY-MM-DDTHH:MM:SS+0000
standard
ATTACHMENT vol-2a2b3c4d i-1a2b3c4d /dev/sda1 attached YYYY-MM-DDTHH:MM:SS+0000
true
TAG volume vol-2a2b3c4d Name Second Volume Name
```

Example Request

This example describes all volumes that are both attached to instance `i-1a2b3c4d` and also set to delete when the instance terminates.

```
PROMPT> ec2-describe-volumes --filter "attachment.instance-id=i-1a2b3c4d" --
filter "attachment.delete-on-termination=true"
VOLUME vol-2a2b3c4d 8 snap-2a2b3c4d us-west-2a in-use YYYY-MM-DDTHH:MM:SS+0000
standard
ATTACHMENT vol-2a2b3c4d i-1a2b3c4d /dev/sda1 attached YYYY-MM-DDTHH:MM:SS+0000
true
TAG volume vol-2a2b3c4d Name Second Volume Name
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeVolumes](#)

Related Commands

- [ec2-create-snapshot](#) (p. 146)
- [ec2-delete-snapshot](#) (p. 221)

ec2-describe-vpc-attribute

Description

Describes the specified attribute of the specified VPC. You can specify only one attribute at a time.

The short version of this command is **ec2dva**.

Syntax

```
ec2-describe-vpc-attribute vpc-id { --dns-support | --dns-hostname }
```

Options

Name	Description
<i>vpc-id</i>	The ID of the VPC. Type: String Required: Yes Example: vpc-1a2b3c4d
-s, --dns-support	Indicates whether the DNS resolution is supported for the VPC. If this attribute is <code>true</code> , the Amazon DNS server resolves DNS hostnames for your instances to their corresponding IP addresses; otherwise, it does not. Type: String Required: No Example: -s
-d, --dns-hostnames	Indicates whether the instances launched in the VPC get DNS hostnames. If this attribute is <code>true</code> , instances in the VPC get DNS hostnames; otherwise, they do not. You can only specify this option if you also specify the <code>--dns-support</code> option. Type: String Required: No Example: -d

Common Options

Option	Description
--region <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: --region eu-west-1

**Amazon Elastic Compute Cloud CLI Reference
Common Options**

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the EC2_PRIVATE_KEY environment variable. Example: -K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the EC2_CERT environment variable. Example: -C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem

Output

This command returns the specified VPC attribute.

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

Use the following command to describe the EnableDnsSupport attribute for the VPC with the ID vpc-1a2b3c4d.

```
PROMPT> ec2-describe-vpc-attribute vpc-1a2b3c4d --dns-support
```

Example Response

This example output indicates that DNS resolution is enabled.

```
RETURN true
```

Example Request

Use the following command to describe the EnableDnsHostnames attribute for the VPC with the ID vpc-1a2b3c4d.

```
PROMPT> ec2-describe-vpc-attribute vpc-1a2b3c4d --dns-hostnames
```

Example Response

This example output indicates that DNS hostnames are enabled.

```
RETURN true
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeVpcAttribute](#)

Related Commands

- [ec2-modify-vpc-attribute](#) (p. 553)

ec2-describe-vpcs

Description

Describes one or more of your VPCs.

The short version of this command is **ec2dvpc**.

Syntax

```
ec2-describe-vpcs [ vpc_id ... ] [--filter "name=value"] ...]
```

Options

Name	Description
<i>vpc_id</i>	One or more VPC IDs. Type: String Default: Describes all your VPCs. Required: No Example: vpc-1a2b3c4d
<code>-F, --filter <i>name=value</i></code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space (" <i>name=value example</i> "). On a Windows system, use quotation marks even without a space in the value string (" <i>name=value</i> "). Type: String Default: Describes all your VPCs, or only those you specified by ID. Required: No Example: <code>--filter "tag-key=Production"</code>

Supported Filters

You can specify filters so that the response includes information for only certain VPCs. For example, you can use a filter to specify that you're interested in VPCs in the `available` state. You can specify multiple values for a filter. The response includes information for a VPC only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify VPCs that use one of several sets of DHCP options and are in the `available` state. The results include information for a VPC only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?`.

The following are the available filters.

cidr

The CIDR block of the VPC. The CIDR block you specify must exactly match the VPC's CIDR block for information to be returned for the VPC.

Type: String

Constraints: Must contain the slash followed by one or two digits (for example, /28)

dhcp-options-id

The ID of a set of DHCP options.

Type: String

isDefault

Indicates whether the VPC is the default VPC.

Type: Boolean

state

The state of the VPC.

Type: String

Valid values: pending | available

tag-key

The key of a tag assigned to the resource. This filter is independent of the `tag-value` filter. For example, if you use both the filter `tag-key=Purpose` and the filter `tag-value=X`, you get any resources assigned both the tag key `Purpose` (regardless of what the tag's value is), and the tag value `X` (regardless of what the tag's key is). If you want to list only resources where `Purpose` is `X`, see the `tag:key` filter.

For more information about tags, see [Tagging Your Resources](#) in the *Amazon Elastic Compute Cloud User Guide*.

Type: String

tag-value

The value of a tag assigned to the resource. This filter is independent of the `tag-key` filter.

Type: String

tag:key

Filters the response based on a specific tag/value combination.

Example: To list just the resources that have been assigned tag `Purpose=X`, specify:

```
--filter tag:Purpose=X
```

Example: To list just resources that have been assigned tag `Purpose=X` OR `Purpose=Y`, specify:

```
--filter tag:Purpose=X --filter tag:Purpose=Y
```

vpc-id

The ID of the VPC.

Type: String

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information for each VPC:

- The VPC identifier
- The ID of the VPC
- The current state of the VPC (`pending` or `available`)
- The CIDR block of the VPC
- The ID of the DHCP options associated with the VPC (or `default` if none)
- Any tags assigned to the VPC
- The allowed tenancy of instances launched into the VPC (`default` or `dedicated`)
- Default VPC (`true` or `false`)

Amazon EC2 command line tools display errors on `stderr`.

Examples

Example Request

This example describes the VPC with ID `vpc-1a2b3c4d`.

```
PROMPT> ec2-describe-vpcs vpc-1a2b3c4d
VPC vpc-1a2b3c4d available 10.0.0.0/23 dopt-7a8b9c2d default false
```

Example Request

This example uses filters to describe any VPC you own that uses the set of DHCP options with the ID `dopt-7a8b9c2d` or `dopt-2b2a3d3c` and whose state is `available`.


```
PROMPT> ec2-describe-vpcs --filter "dhcp-options-id=dopt-7a8b9c2d" --filter  
"dhcp-options-id=dopt-2b2a3d3c" --filter "state=available"  
VPC vpc-1a2b3c4d available 10.0.0.0/23 dopt-7a8b9c2d default false
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeVpcs](#)

Related Commands

- [ec2-create-vpc](#) (p. 167)
- [ec2-delete-vpc](#) (p. 237)
- [ec2-associate-dhcp-options](#) (p. 25)
- [ec2-create-dhcp-options](#) (p. 93)

ec2-describe-vpn-connections

Description

Describes one or more of your VPN connections.

For VPN connections in the pending or available state only, you can also optionally get the configuration information for the VPN connection's customer gateway. You do this by specifying a format with the `--format` option, or by specifying an XSL stylesheet of your own design with the `--stylesheet` option (you were also able to do this when you created the VPN connection).

For more information about VPN connections, see [Adding a Hardware Virtual Private Gateway to Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is `ec2dvpn`.

Syntax

```
ec2-describe-vpn-connections [vpn_connection_id ... ] [{"--format format"} |
{"--stylesheet your_stylesheet"} [{"--filter "name=value"} ...]
```

Options

Name	Description
<code>vpn_connection_id</code>	A VPN connection ID. You can specify more than one in the request. Type: String Default: Describes all your VPN connections. Required: No Example: vpn-44a8938f
<code>--format format</code>	Includes customer gateway configuration information in the response, in the format specified by this option. The information is returned only if the VPN connection is in the pending or available state. The returned information can be formatted for various devices, including a Cisco device (cisco-ios-isr) or Juniper device (juniper-junos-j), in human readable format (generic), or in the native XML format (xml). Type: String Default: None Valid values: cisco-ios-isr juniper-junos-j juniper-screens-6.2 juniper-screens-6.1 generic xml Required: No Example: --format cisco-ios-isr

Name	Description
<code>--stylesheet <i>your_stylesheet</i></code>	Includes customer gateway configuration information in the response, formatted according to the custom XSL stylesheet you specify with this option. The information is returned only if the VPN connection is in the pending or available state. Type: String Default: None Required: No Example: <code>--stylesheet c:\my_stylesheet.xml</code>
<code>-F, --filter <i>name=value</i></code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space (" <code>name=value example</code> "). On a Windows system, use quotation marks even without a space in the value string (" <code>name=value</code> "). Type: String Default: Describes all your VPN connections, or only those you specified by ID. Required: No Example: <code>--filter "tag-key=Production"</code>

Supported Filters

You can specify filters so that the response includes information for only certain VPN connections. For example, you can use a filter to specify that you're interested in the VPN connections in the `pending` or `available` state. You can specify multiple values for a filter. The response includes information for a VPN connection only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify VPN connections that are associated with a specific virtual private gateway, and the gateway is in the `pending` or `available` state. The response includes information for a VPN connection only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\`.

The following are the available filters.

customer-gateway-configuration

The configuration information for the customer gateway.

Type: String

customer-gateway-id

The ID of a customer gateway associated with the VPN connection.

Type: String

state

The state of the VPN connection.

Type: String

Valid values: `pending` | `available` | `deleting` | `deleted`

option.static-routes-only

Indicates whether the connection has static routes only. Used for devices that do not support Border Gateway Protocol (BGP).

Type: Boolean

route.destination-cidr-block

The destination CIDR block. This corresponds to the subnet used in a customer data center.

Type: String

bgp-asn

The BGP Autonomous System Number (ASN) associated with a BGP device.

Type: Integer

tag-key

The key of a tag assigned to the resource. This filter is independent of the `tag-value` filter. For example, if you use both the filter `"tag-key=Purpose"` and the filter `"tag-value=X"`, you get any resources assigned both the tag key `Purpose` (regardless of what the tag's value is), and the tag value `X` (regardless of what the tag's key is). If you want to list only resources where Purpose is `X`, see the `tag:key` filter.

For more information about tags, see [Tagging Your Resources](#) in the *Amazon Elastic Compute Cloud User Guide*.

Type: String

tag-value

The value of a tag assigned to the resource. This filter is independent of the `tag-key` filter.

Type: String

tag:key

Filters the response based on a specific tag/value combination.

Example: To list just the resources that have been assigned tag `Purpose=X`, specify:

```
--filter tag:Purpose=X
```

Example: To list just resources that have been assigned tag `Purpose=X` OR `Purpose=Y`, specify:

```
--filter tag:Purpose=X --filter tag:Purpose=Y
```

type

The type of VPN connection. Currently the only supported type is `ipsec.1`.

Type: String

Valid values: `ipsec.1`

vpn-connection-id

The ID of the VPN connection.

Type: String

vpn-gateway-id

The ID of a virtual private gateway associated with the VPN connection.

Type: String

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The VPNCONNECTION identifier
- The VPN connection ID
- The type of VPN connection
- The customer gateway ID
- The virtual private gateway ID
- The state of the VPN connection (pending, available, deleting, deleted)
- Configuration information for the customer gateway (optional and available only if the VPN connection is in the pending or available state)
- Any tags assigned to the VPN connection

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example gives a description of the VPN connection with ID `vpn-44a8938f`. The example specifies that the configuration information be formatted as needed for a Cisco customer gateway. Because it's a long set of information, we haven't displayed it here in the response. To see an example of the configuration information, see the [Amazon Virtual Private Cloud Network Administrator Guide](#).

```
PROMPT> ec2-describe-vpn-connections vpn-44a8938f --format cisco-ios-isr
VPNCONNECTION vpn-44a8938f ipsec.1 vgw-8db04f81 cgw-b4dc3961 available
<Long customer gateway configuration data formatted for Cisco device... >
```

Example Request

This example uses filters to give a description of any VPN connection you own associated with the customer gateway with ID `cgw-b4dc3961`, and whose state is either `pending` or `available`. Note that it doesn't use the option that causes the output to include the customer gateway configuration.

```
PROMPT> ec2-describe-vpn-connections --filter "customer-gateway-id=cgw-b4dc3961"  
--filter "state=pending" --filter "state=available"  
VPNCONNECTION vpn-44a8938f ipsec.1 vgw-8db04f81 cgw-b4dc3961 available
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeVpnConnections](#)

Related Commands

- [ec2-create-vpn-connection](#) (p. 171)
- [ec2-delete-vpn-connection](#) (p. 240)

ec2-describe-vpn-gateways

Description

Describes one or more of your virtual private gateways.

For more information about virtual private gateways, see [Adding a Hardware Virtual Private Gateway to Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2dvgw**.

Syntax

```
ec2-describe-vpn-gateways [vpn_gateway_id ... ] [--filter "name=value"] ...]
```

Options

Name	Description
<i>vpn_gateway_id</i>	One or more virtual private gateway IDs. Type: String Default: Describes all your virtual private gateways. Required: No Example: vgw-8db04f81
<code>-F</code> , <code>--filter name=value</code>	A filter for limiting the results. See the Supported Filters section for a list of supported filters. Use quotation marks if the value string has a space (" <i>name=value example</i> "). On a Windows system, use quotation marks even without a space in the value string (" <i>name=value</i> "). Type: String Default: Describes all your virtual private gateways, or only those you specified by ID. Required: No Example: <code>--filter "tag-key=Production"</code>

Supported Filters

You can specify filters so that the response includes information for only certain virtual private gateways. For example, you can use a filter to specify that you're interested in the virtual private gateways in the `pending` or `available` state. You can specify multiple values for a filter. The response includes information for a virtual private gateway only if it matches at least one of the filter values that you specified.

You can specify multiple filters; for example, specify virtual private gateways that are in a specific Availability Zone and are in the `pending` or `available` state. The response includes information for a virtual private gateway only if it matches all the filters that you specified. If there's no match, no special message is returned, the response is simply empty.

You can use wildcards in a filter value. An asterisk (*) matches zero or more characters, and a question mark (?) matches exactly one character. You can escape special characters using a backslash (\) before the character. For example, a value of `*amazon\?\` searches for the literal string `*amazon?\.`

The following are the available filters.

attachment.state

The current state of the attachment between the gateway and the VPC.

Type: String

Valid values: attaching | attached | detaching | detached

attachment.vpc-id

The ID of an attached VPC.

Type: String

availability-zone

The Availability Zone for the virtual private gateway.

Type: String

state

The state of the virtual private gateway.

Type: String

Valid values: pending | available | deleting | deleted

tag-key

The key of a tag assigned to the resource. This filter is independent of the `tag-value` filter. For example, if you use both the filter "tag-key=Purpose" and the filter "tag-value=X", you get any resources assigned both the tag key `Purpose` (regardless of what the tag's value is), and the tag value `X` (regardless of what the tag's key is). If you want to list only resources where Purpose is X, see the `tag:key` filter.

For more information about tags, see [Tagging Your Resources](#) in the *Amazon Elastic Compute Cloud User Guide*.

Type: String

tag-value

The value of a tag assigned to the resource. This filter is independent of the `tag-key` filter.

Type: String

tag:key

Filters the response based on a specific tag/value combination.

Example: To list just the resources that have been assigned tag Purpose=X, specify:

```
--filter tag:Purpose=X
```

Example: To list just resources that have been assigned tag Purpose=X OR Purpose=Y, specify:

```
--filter tag:Purpose=X --filter tag:Purpose=Y
```

type

The type of virtual private gateway. Currently the only supported type is `ipsec.1`.

Type: String

Valid values: ipsec.1

vpn-gateway-id

The ID of the virtual private gateway.

Type: String

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.

Option	Description
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The VPNGATEWAY identifier
- The virtual private gateway ID
- The state of the virtual private gateway (pending, available, deleting, deleted)
- The Availability Zone where the virtual private gateway was created
- The type of VPN connection the virtual private gateway supports
- The VGWATTACHMENT identifier
- The ID of each attached VPC and the state of each attachment (attaching, attached, detaching, detached)
- Any tags assigned to the virtual private gateway

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example gives a description of the virtual private gateway with ID vgw-8db04f81.

```
PROMPT> ec2-describe-vpn-gateways vgw-8db04f81  
VPNGATEWAY vgw-8db04f81 available us-east-1a ipsec.1  
VGWATTACHMENT vpc-1a2b3c4d attached
```

Example Request

This example uses filters to give a description of any virtual private gateway you own that is in the us-east-1a Availability Zone, and whose state is either pending or available.

```
PROMPT> ec2-describe-vpn-gateways --filter "availability-zone=us-east-1a" --  
filter "state=pending" --filter "state=available"  
VPNGATEWAY vgw-8db04f81 available ipsec.1  
VGWATTACHMENT vpc-1a2b3c4d attached
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DescribeVpnGateways](#)

Related Commands

- [ec2-create-vpn-gateway](#) (p. 176)
- [ec2-delete-vpn-gateway](#) (p. 246)

ec2-detach-internet-gateway

Description

Detaches an Internet gateway from a VPC, disabling connectivity between the Internet and the VPC. The VPC must not contain any running instances with an Elastic IP address. For more information about your VPC and Internet gateway, see the [Amazon Virtual Private Cloud User Guide](#).

The short version of this command is **ec2detigw**.

Syntax

```
ec2-detach-internet-gateway vpn_gateway_id -c vpc_id
```

Options

Name	Description
<i>vpn_gateway_id</i>	The ID of the Internet gateway. Type: String Default: None Required: Yes Example: igw-8db04f81
<i>-c, --vpc vpc_id</i>	The ID of the VPC. Type: String Default: None Required: Yes Example: -c vpc-1a2b3c4d

Common Options

Option	Description
<i>--region REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<i>-U, --url URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- Success status (`true` or `false`)

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example detaches the Internet gateway with ID `igw-eaad4883` from the VPC with ID `vpc-11ad4878`.

```
PROMPT> ec2-detach-internet-gateway igw-eaad4883 -c vpc-11ad4878  
RETURN true
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DetachInternetGateway](#)

Related Commands

- [ec2-detach-internet-gateway](#) (p. 33)
- [ec2-create-internet-gateway](#) (p. 111)
- [ec2-delete-internet-gateway](#) (p. 196)
- [ec2-describe-internet-gateways](#) (p. 333)

ec2-detach-network-interface

Description

Detaches a network interface from an instance.

The short version of this command is **ec2detnic**.

Syntax

```
ec2-detach-network-interface attachment_id [--force]
```

Options

Name	Description
<i>attachment_id</i>	One or more network IDs. Type: String Default: Describes all your virtual private gateways. Required: Yes Example: eni-attach-083fda61
<i>-f, --force</i>	Forcefully disconnect the network interface from the instance. Type: String Default: None Required: No

Common Options

Option	Description
<i>--region REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<i>-U, --url URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns the name of the network attachment that was detached.

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example detaches the specified network interface.

```
PROMPT> ec2-detach-network-interface eni-attach-083fda61  
  
ATTACHMENT      eni-attach-083fda61      detaching
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DetachNetworkInterface](#)

Related Commands

- [ec2-attach-network-interface](#) (p. 37)
- [ec2-create-network-interface](#) (p. 126)
- [ec2-delete-network-interface](#) (p. 209)
- [ec2-describe-network-interface-attribute](#) (p. 348)
- [ec2-describe-network-interfaces](#) (p. 352)
- [ec2-modify-network-interface-attribute](#) (p. 541)

- [ec2-reset-network-interface-attribute](#) (p. 615)

ec2-detach-volume

Description

Detaches an Amazon EBS volume from an instance. Make sure to unmount any file systems on the device within your operating system before detaching the volume. Failure to do so will result in volume being stuck in "busy" state while detaching. For more information about Amazon EBS, see [Elastic Block Store](#) in the *Amazon Elastic Compute Cloud User Guide*.

Note

If an Amazon EBS volume is the root device of an instance, it cannot be detached while the instance is in the `running` state. To detach the root volume, stop the instance first. If the root volume is detached from an instance with an AWS Marketplace product code, then the AWS Marketplace product codes from that volume are no longer associated with the instance.

The short version of this command is `ec2detvol`.

Syntax

```
ec2-detach-volume volume_id [--instance instance_id [--device device]] [--force]
```

Options

Name	Description
<code>volume_id</code>	The ID of the volume. Type: String Default: None Required: Yes Example: vol-4282672b
<code>-i, --instance instance_id</code>	The ID of the instance. Type: String Default: None Required: No Example: -i i-6058a509
<code>-d, --device device</code>	The device name. Type: String Default: None Required: No Example: -d /dev/sdh

Name	Description
-f, --force	<p>Forces detachment if the previous detachment attempt did not occur cleanly (logging into an instance, unmounting the volume, and detaching normally). This option can lead to data loss or a corrupted file system. Use this option only as a last resort to detach a volume from a failed instance. The instance will not have an opportunity to flush file system caches or file system metadata. If you use this option, you must perform file system check and repair procedures.</p> <p>Type: Boolean Default: None Required: No Example: -f</p>

Common Options

Option	Description
--region <i>REGION</i>	<p>Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option.</p> <p>Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set.</p> <p>Example: <code>--region eu-west-1</code></p>
-U, --url <i>URL</i>	<p>The uniform resource locator (URL) of the Amazon EC2 web service entry point.</p> <p>Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set.</p> <p>Example: <code>-U https://ec2.amazonaws.com</code></p>
-O, --aws-access-key <i>AWS_ACCESS_KEY</i>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
-W, --aws-secret-key <i>AWS_SECRET_KEY</i>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
-T, --security-token <i>TOKEN</i> <i>AWS_DELEGATION_TOKEN</i>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>

Option	Description
<code>--connection-timeout</code> <i>TIMEOUT</i>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The ATTACHMENT identifier

- The ID of the volume
- The ID of the instance
- The device name
- The attachment state of the volume
- The time stamp of the last operation on the volume
- Whether or not the volume is set to delete on termination (*true* or *false*)

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example detaches volume `vol-1a2b3c4d`.

```
PROMPT> ec2-detach-volume vol-1a2b3c4d  
ATTACHMENT vol-1a2b3c4d i-1a2b3c4d /dev/sdh detaching YYYY-MM-DDTHH:MM:SS+0000
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DetachVolume](#)

Related Commands

- [ec2-attach-volume](#) (p. 41)
- [ec2-create-volume](#) (p. 162)
- [ec2-delete-volume](#) (p. 234)
- [ec2-describe-volumes](#) (p. 438)

ec2-detach-vpn-gateway

Description

Detaches a virtual private gateway from a VPC. You do this if you're planning to turn off the VPC and not use it anymore. You can confirm a virtual private gateway has been completely detached from a VPC by describing the virtual private gateway (any attachments to the virtual private gateway are also described).

You must wait for the attachment's state to switch to `detached` before you can delete the VPC or attach a different VPC to the virtual private gateway.

For more information about virtual private gateways, see [Adding a Hardware Virtual Private Gateway to Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is `ec2detvgw`.

Syntax

```
ec2-detach-vpn-gateway -p vpn_gateway_id -c vpc_id
```

Options

Name	Description
<code>-p <i>vpn_gateway_id</i></code>	The ID of the virtual private gateway. Type: String Default: None Required: Yes Example: <code>-p vgw-8db04f81</code>
<code>-c <i>vpc_id</i></code>	The ID of the VPC. Type: String Default: None Required: Yes Example: <code>-c vpc-1a2b3c4d</code>

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The VPNGATEWAY identifier
- The ID of the VPC
- The state of detachment (attaching, attached, detaching, detached)

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example detaches the virtual private gateway with ID `vgw-8db04f81` from the VPC with the ID `vpc-1a2b3c4d`.

```
PROMPT> ec2-detach-vpn-gateway -p vgw-8db04f81 -c vpc-1a2b3c4d
VGWATTACHMENT vpc-1a2b3c4d detaching
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DetachVpnGateway](#)

Related Commands

- [ec2-attach-vpn-gateway](#) (p. 45)
- [ec2-describe-vpn-gateways](#) (p. 459)

ec2-disable-vgw-route-propagation

Description

Disables a virtual private gateway (VGW) from propagating routes to the routing tables of a VPC. This command is only available in EC2-VPC.

The short version of this command is **ec2drp**.

Syntax

```
ec2-disable-vgw-route-propagation --route-table route_table_id --vgw vgw_id
```

Options

Name	Description
<code>--route-table <i>route_table_id</i></code>	The ID of the routing table. Type: String Default: None Required: Yes
<code>--vgw <i>vgw_id</i></code>	The ID of the virtual private gateway. Type: String Default: None Required: Yes

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url <i>URL</i></code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

The command returns true if the operation succeeds or an error if the operation does not succeed.

Amazon EC2 command line tools display errors on stderr.

Example

Example Request

This example disables the virtual private gateway, `vgw-2acfb1` from propagating routes to route table `rtb-5c6de435`.

```
PROMPT> ec2-disable-vgw-route-propagation --route-table rtb-5c6de435 --vgw
vgw-2acfb1
RETURN true
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DisableVgwRoutePropagation](#)

ec2-disassociate-address

Description

Disassociates an Elastic IP address from the instance or network interface it's associated with.

An Elastic IP address is for use either in the EC2-Classic platform or in a VPC. For more information, see [Elastic IP Addresses](#) in the *Amazon Elastic Compute Cloud User Guide*.

This is an idempotent action. If you enter it more than once, Amazon EC2 does not return an error.

The short version of this command is **ec2disaddr**.

Syntax

```
ec2-disassociate-address { ip_address | -a association_id }
```

Options

Name	Description
<i>ip_address</i>	[EC2-Classic] The Elastic IP address. Type: String Default: None Required: Conditional Condition: Required for EC2-Classic. Example: 192.0.2.1
-a, --association-id <i>association_id</i>	[EC2-VPC] The association ID. Type: String Default: None Required: Conditional Condition: Required for EC2-VPC. Example: -a eipassoc-fc5ca095

Common Options

Option	Description
--region <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: --region eu-west-1
-U, --url <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: -U https://ec2.amazonaws.com

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The ADDRESS identifier
- The Elastic IP address

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example disassociates the Elastic IP address (192.0.2.1) from the instance it's associated with in EC2-Classic.

```
PROMPT> ec2-disassociate-address 192.0.2.1  
ADDRESS 192.0.2.1
```

Example Request

This example disassociates the Elastic IP address with association ID eipassoc-048c746d from the instance it's associated with in a VPC.

```
PROMPT> ec2-disassociate-address -a eipassoc-048c746d  
ADDRESS eipassoc-048c746d
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DisassociateAddress](#)

Related Commands

- [ec2-allocate-address](#) (p. 12)
- [ec2-associate-address](#) (p. 20)
- [ec2-describe-addresses](#) (p. 256)
- [ec2-release-address](#) (p. 572)

ec2-disassociate-route-table

Description

Disassociates a subnet from a route table.

After you perform this action, the subnet no longer uses the routes in the route table. Instead, it uses the routes in the VPC's main route table. For more information about route tables, see [Route Tables](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2disrtb**.

Syntax

`ec2-disassociate-route-table` *route_table_association_id*

Options

Name	Description
<i>route_table_association_id</i>	The association ID representing the current association between the route table and subnet. Type: String Default: None Required: Yes Example: rtbassoc-61a34608

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- Success status (`true` or `false`)

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example disassociates the route table with association ID `rtbassoc-fdad4894` from the subnet it's associated to.

```
PROMPT> ec2-disassociate-route-table rtbassoc-fdad4894  
RETURN      true
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [DisassociateRouteTable](#)

Related Commands

- [ec2-associate-route-table](#) (p. 29)
- [ec2-create-route-table](#) (p. 143)
- [ec2-delete-route-table](#) (p. 218)
- [ec2-describe-route-tables](#) (p. 386)

- [ec2-replace-route-table-association](#) (p. 588)

ec2-enable-volume-io

Description

Enables I/O operations for a volume that had I/O operations disabled because the data on the volume was potentially inconsistent.

The short version of this command is **ec2evio**.

Syntax

`ec2-enable-volume-io` *volume_id*

Options

Name	Description
<i>volume_id</i>	The ID of the volume. Type: String Default: None Required: Yes Example: vol-43a4412a

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U</code> , <code>--url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O</code> , <code>--aws-access-key</code> <i>AWS_ACCESS_KEY</i>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXI1BH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a Boolean value indicating whether the request succeeded.

- Boolean value representing whether the call succeeded.

Amazon EC2 command line tools display errors on stderr.

Example

Example Request

This example enables the I/O operations for the volume vol-232323.

```
PROMPT> ec2-enable-volume-io vol-232323  
RETURN true
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [EnableVolumeIO](#)

Related Commands

- [ec2-describe-volume-status](#) (p. 432)

ec2-enable-vgw-route-propagation

Description

Enables a virtual private gateway (VGW) to propagate routes to the routing tables of a VPC. This command is only available in EC2-VPC.

The short version of this command is **ec2erp**.

Syntax

```
ec2-enable-vgw-route-propagation --route-table route_table_id --vgw vgw_id
```

Options

Name	Description
<code>--route-table <i>route_table_id</i></code>	The ID of the routing table. Type: String Default: None Required: Yes
<code>--vgw <i>vgw_id</i></code>	The ID of the virtual private gateway. Type: String Default: None Required: Yes

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url <i>URL</i></code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

The command returns true if the operation succeeds or an error if the operation does not succeed.

Amazon EC2 command line tools display errors on stderr.

Example

Example Request

This example enables the virtual private gateway, `vgw-2acfb1` to propagate static routes to route table `rtb-5c6de435`.

```
PROMPT> ec2-enable-vgw-route-propagation --route-table rtb-5c6de435 --vgw vgw-2acfb1  
RETURN true
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [EnableVgwRoutePropagation](#)

ec2-fingerprint-key

Description

Computes and displays the fingerprint for a private key produced by Amazon EC2.

This operation is performed entirely on the client-side. Network access is not required.

The short version of this command is **ec2fp**.

Syntax

`ec2-fingerprint-key keyfile`

Options

Name	Description
<i>keyfile</i>	The path to a file containing an unencrypted PEM-encoded PKCS#8 private key. Type: String Default: None Required: Yes Example: mykey.pem

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url <i>URL</i></code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key <i>AWS_ACCESS_KEY</i></code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key EC2_PRIVATE_KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- A key fingerprint. This is formatted as a hash digest with each octet separated by a colon

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example computes and displays the fingerprint for the `mykey.pem` private key.

```
PROMPT> ec2-fingerprint-key mykey.pem  
00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Commands

- [ec2-describe-keypairs](#) (p. 338)

ec2-get-console-output

Description

Retrieves console output for the specified instance.

Instances do not have a physical monitor through which you can view their console output. They also lack physical controls that allow you to power up, reboot, or shut them down. To allow these actions, we provide them through the Amazon EC2 API and the command line tools.

Instance console output is buffered and posted shortly after instance boot, reboot, and termination. Amazon EC2 preserves the most recent 64 KB output which will be available for at least one hour after the most recent post.

For Linux/UNIX instances, the instance console output displays the exact console output that would normally be displayed on a physical monitor attached to a machine. This output is buffered because the instance produces it and then posts it to a store where the instance's owner can retrieve it.

For Windows instances, the instance console output displays the last three system event log errors.

The short version of this command is **ec2gcons**.

Syntax

```
ec2-get-console-output instance_id [-r]
```

Options

Name	Description
<i>instance_id</i>	The ID of the instance. Type: String Default: None Required: Yes Example: i-10a64379
-r, --raw-console-output	Returns raw output without escapes to facilitate reading. Type: String Default: Disabled Required: No Example: -r

Common Options

Option	Description
--region <i>REGION</i>	Overrides the region specified by the EC2_URL environment variable and the URL specified by the -U option. Default: The value of the EC2_URL environment variable, or us-east-1 if EC2_URL isn't set. Example: --region eu-west-1

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The instance ID
- A timestamp indicating the time of the last update
- The instance console output. By default the ^ESC character is escaped and duplicate new-lines are removed to facilitate reading

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example retrieves the console output for the `i-10a64379` Linux and UNIX instance.

```
PROMPT> ec2-get-console-output i-10a64379
i-10a64379
2010-04-08T09:20:29+0000
Linux version 2.6.21.7-2.ec2.v1.2.fc8xen (root@domU-12-34-56-0A-78-01) (gcc
version 4.1.2 20070925 (Red Hat 4.1.2-33)) #1 SMP Fri Nov 20 19:22:36 EST 2009
BIOS-provided physical RAM map:
sanitize start
sanitize bail 0
copy_e820_map() start: 0000000000000000 size: 000000006ac00000 end:
000000006ac00000 type: 1
Xen: 0000000000000000 - 000000006ac00000 (usable)
980MB HIGHMEM available.
727MB LOWMEM available.
NX (Execute Disable) protection: active
...
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [GetConsoleOutput](#)

Related Commands

- [ec2-run-instances](#) (p. 633)

ec2-get-password

Description

Retrieves and decrypts the administrator password for the instances running Windows.

You must specify the key pair used to launch the instance.

The Windows password is only generated the first time an AMI is launched. It is not generated for rebundled AMIs or after the password is changed on an instance.

The password is encrypted using the key pair that you provided.

Password generation and encryption takes a few moments. Please wait up to 15 minutes after launching an instance before trying to retrieve the generated password.

The short version of this command is **ec2gpass**.

Syntax

```
ec2-get-password instance_id -k key_file
```

Options

Name	Description
<i>instance_id</i>	A Windows instance ID. Type: String Default: None Required: Yes Example: i-9b76d0f3
<code>-k, --priv-launch-key <i>key_file</i></code>	The file that contains the private key used to launch the instance. Type: String Default: None Required: Yes Example: -k windows-keypair.pem

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the EC2_PRIVATE_KEY environment variable. Example: -K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the EC2_CERT environment variable. Example: -C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem

Output

This command returns a table that contains the following information:

- The Windows administrator password

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example returns the administrator password for the i-2574e22a instance.

```
PROMPT> ec2-get-password i-2574e22a -k windows-keypair.pem
q96A40B9w
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [GetPasswordData](#)

Related Commands

- [ec2-run-instances](#) (p. 633)
- [ec2-describe-instances](#) (p. 320)

ec2-import-instance

Description

Creates a new import instance task using metadata from the specified disk image, and imports the image to Amazon EC2. For more information about prerequisites for importing an instance, see [Before You Get Started](#) and [Using the Command Line Tools to Import Your Virtual Machine to Amazon EC2](#) in the *Amazon Elastic Compute Cloud User Guide*.

If the upload task doesn't complete, use `ec2-resume-import` to resume the import from where it was interrupted.

The short version of this command is `ec2iin`.

Syntax

```
ec2-import-instance -t instance_type [-g group] -f file_format -a architecture
[-p platform_name] -b s3_bucket_name [-o owner] -w secret_key [--prefix prefix]
[--manifest-url url] [-s volume_size] [-z availability_zone] [-d description]
[--user-data user_data] [--user-data-file disk_image_filename] [--subnet
subnet_id] [--private-ip-address ip_address] [--monitor]
[--instance-initiated-shutdown-behavior behavior] [--x days]
[--ignore-region-affinity] [--dry-run] [--no-upload] [--dont-verify-format]
```

Options

Name	Description
<code>-t, --instance-type <i>instance_type</i></code>	<p>The type of instance to be launched. See Available Instance Types for more information.</p> <p>Type: String</p> <p>Default: <code>m1.small</code></p> <p>Required: Yes</p> <p>Example: <code>-t m1.small</code></p> <p>Note The <code>-a</code> option is only honored if the <code>-t</code> option is passed. If the <code>-t</code> option is not passed, then <code>-a</code> is treated as <code>i386</code>. If the <code>-t</code> option is not passed, the instance type defaults to <code>m1.small</code>.</p>
<code>-g, --group <i>group</i></code>	<p>The security group within which the instances should be run. Determines the ingress firewall rules that are applied to the launched instances. Only one security group is supported for an instance.</p> <p>Type: String</p> <p>Default: Your default security group</p> <p>Required: No</p> <p>Example: <code>-g myGroup</code></p>

Name	Description
<code>-f, --format <i>file_format</i></code>	The file format of the disk image. Type: String Default: None Valid values: VMDK RAW VHD Required: Yes Example: -f VMDK
<code>-a, --architecture <i>architecture</i></code>	The architecture of the image. Using this option ensures that your image is imported as the expected instance type. Type: String Default: i386 Valid values: i386 x86_64 Required: Yes Condition: Required if instance type is specified; otherwise defaults to i386. Note The -a option is only honored if the -t option is passed. If the -t option is not passed, then -a is treated as i386 . If the -t option is not passed, the instance type defaults to <code>m1.small</code> . Example: -a i386
<code>-p, --platform <i>platform_name</i></code>	The operating system of the instance. Type: String Default: None Valid value: windows Required: No
<code>-b, --bucket <i>s3_bucket_name</i></code>	The Amazon S3 destination bucket for the manifest. Type: String Default: None Required: Conditional Condition: The <code>--manifest-url</code> parameter is not specified. Example: myawsbucket
<code>-o, --owner-akid <i>access_key_id</i></code>	The access key ID of the bucket owner. Type: String Default: None Required: No Example: AKIAIOSFODNN7EXAMPLE
<code>-w, --owner-sak <i>secret_access_key</i></code>	The secret access key of the bucket owner. Type: String Default: None Required: Yes Example: wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY

Amazon Elastic Compute Cloud CLI Reference
Options

Name	Description
<code>--prefix <i>prefix</i></code>	The prefix for the manifest file and disk image file parts within the Amazon S3 bucket. Type: String Default: None Required: No Example: <code>--prefix MyDiskParts</code>
<code>--manifest-url <i>url</i></code>	The URL for an existing import manifest file already uploaded to Amazon S3. Type: String Default: None. This option cannot be specified if the <code>--bucket</code> option is present. Required: No Example: <code>my-ami.manifest.xml</code>
<code>-s, --volume-size <i>volume_size</i></code>	The size of the Amazon EBS volume, in GiB (2 ³⁰ bytes), that will hold the converted image. If not specified, Amazon EC2 calculates the value using the disk image file. Type: String Default: None Required: No Example: <code>-s 30</code>
<code>-z, --availability-zone <i>availability_zone</i></code>	The Availability Zone for the converted VM. Type: String Default: None Valid values: Use <code>ec2-describe-availability-zones</code> for a list of values Required: No Example: <code>-z us-east-1</code>
<code>-d, --description <i>description</i></code>	An optional, free-form comment returned verbatim during subsequent calls to <code>ec2-describe-conversion-tasks</code> . Type: String Default: None Constraint: Maximum length of 255 characters Required: No Example: <code>-d Test of ec2-import-instance</code>
<code>--user-data <i>user_data</i></code>	User data to be made available to the imported instance. Type: String Default: None Required: No Example: <code>--user-data This is user data</code>

Amazon Elastic Compute Cloud CLI Reference
Options

Name	Description
<code>--user-data-file</code> <i>disk_image_filename</i>	The file containing user data made available to the imported instance. Type: String Default: None Required: No Example: <code>--user-data-file my_data_file</code>
<code>--subnet</code> <i>subnet_id</i>	[EC2-VPC] The ID of the subnet into which you're launching the instance. Type: String Default: None Required: No Example: <code>--subnet subnet-f3e6ab83</code>
<code>--private-ip-address</code> <i>ip_address</i>	[EC2-VPC] The specific IP address within <i>subnet</i> to use for the instance. Type: String Default: None Required: No Example: <code>--private-ip-address 10.0.0.3</code>
<code>--monitor</code>	Enables monitoring of the specified instances. Type: String Default: None Required: No Example: <code>--monitor</code>
<code>--instance-initiated-shutdown-behavior</code> <i>behavior</i>	If an instance shutdown is initiated, this determines whether the instance stops or terminates. Type: String Default: None Valid values: <code>stop terminate</code> Required: No Example: <code>--instance-initiated-shutdown-behavior stop</code>
<code>-x, --expires</code> <i>days</i>	The validity period for the signed Amazon S3 URLs that allow Amazon EC2 to access the manifest. Type: String Default: 30 days Required: No Example: <code>-x 10</code>
<code>--ignore-region-affinity</code>	Ignores the verification check to determine whether the bucket's region matches the region where the conversion task is created. Type: None Default: None Required: No Example: <code>--ignore-region-affinity</code>

Name	Description
<code>--dry-run</code>	Validates that the disk image matches a known type, without creating an import task. Type: None Default: None Required: No Example: <code>--dry-run</code>
<code>--dont-verify-format</code>	Skips verifying the file format. We don't recommend this option because it can result in a failed conversion. Type: None Default: None Required: No Example: <code>--dont-verify-format</code>
<code>--no-upload</code>	Creates an import task, without uploading a disk image to Amazon S3. To complete the import task and upload the disk image, use <code>ec2-resume-import</code> . Type: None Default: None Required: No Example: <code>--no-upload</code>

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key</code> <code>AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> <code>TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <code>TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <code>TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <code>EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXI1BH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns the following information:

- Task ID, which you will use in other commands
- General information about the disk image, such as the size and format
- General information about the import operation, such as the status, bytes received, and expiration deadline

Amazon EC2 command line tools display errors on stderr.

Example

Example Request

This example creates an import instance task that migrates a Windows Server 2008 SP2 (32-bit) VM into the AWS us-east-1 region.

```
PROMPT> ec2-import-instance -t m1.xlarge ./WinSvr8-disk1.vmdk -f VMDK -o AKI  
AIOFODNN7EXAMPLE -w wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY -b myawsbucket
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ImportInstance](#)

Related Commands

- [ec2-cancel-conversion-task](#) (p. 64)
- [ec2-delete-disk-image](#) (p. 189)
- [ec2-describe-conversion-tasks](#) (p. 272)
- [ec2-import-volume](#) (p. 518)
- [ec2-resume-import](#) (p. 622)

ec2-import-keypair

Description

Imports the public key from an RSA key pair that you created with a third-party tool. Compare this with `ec2-create-keypair`, in which AWS creates the key pair and gives the keys to you (AWS keeps a copy of the public key). With `ec2-import-keypair`, you create the key pair and give AWS just the public key. The private key is never transferred between you and AWS.

You can easily create an RSA key pair on Windows and Linux using the `ssh-keygen` command line tool (provided with the standard OpenSSH installation). Standard library support for RSA key pair creation is also available in Java, Ruby, Python, and many other programming languages.

Supported formats:

- OpenSSH public key format (e.g., the format in `~/.ssh/authorized_keys`)
- Base64 encoded DER format
- SSH public key file format as specified in [RFC4716](#)

DSA keys are not supported. Make sure your key generator is set up to create RSA keys.

Supported lengths: 1024, 2048, and 4096.

Note that you can have up to five thousand key pairs per region.

The short version of this command is `ec2ikey`.

Syntax

```
ec2-import-keypair key_name --public-key-file key_file
```

Options

Name	Description
<code><i>key_name</i></code>	A unique name for the key pair. Type: String Default: None Required: Yes Example: myfavoritekeypair
<code>-f, --public-key-file <i>key_file</i></code>	The path and name of the file containing the public key. Type: String Default: None Required: Yes Example: -f C:\keys\myfavoritekeypair_public.ppk

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.

Option	Description
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

The command returns a table that contains the following information:

- The KEYPAIR identifier
- The name of the key pair
- The MD5 public key fingerprint as specified in section 4 of [RFC4716](#)

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example imports the public key from the file `C:\keys\mykey.ppk`.

```
PROMPT> ec2-import-keypair gsg-keypair --public-key-file C:\keys\mykey.ppk
KEYPAIR gsg-keypair 00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ImportKeyPair](#)

Related Commands

- [ec2-create-keypair](#) (p. 114)
- [ec2-delete-keypair](#) (p. 199)
- [ec2-describe-keypairs](#) (p. 338)

ec2-import-volume

Description

Creates a new import volume task using metadata from the specified disk image, and imports the image to Amazon EC2. For more information about prerequisites for importing a volume, see [Before You Get Started](#) and [Using the Command Line Tools to Import Your Virtual Machine to Amazon EC2](#) in the *Amazon Elastic Compute Cloud User Guide*.

If the upload task doesn't complete, use `ec2-resume-import` to resume the import from where it was interrupted.

The short version of this command is `ec2ivol`.

Syntax

```
ec2-import-volume disk_image -f file_format [-s volume_size] -z availability_zone
[-b s3_bucket_name] [-o owner] -w secret_key [--prefix prefix] [--manifest-url
url] [-d description] [--x days] [--ignore-region-affinity] [--dry-run]
[--no-upload] [--dont-verify-format]
```

Options

Name	Description
<i>disk_image</i>	The local file name of the disk image. Type: String Default: None Required: Yes Example: WinSvr8-64-disk1.vmdk
<code>-f, --format</code> <i>file_format</i>	The file format of the disk image. Type: String Default: None Valid values: VMDK RAW VHD Required: Yes Example: <code>-f VMDK</code>
<code>-s, --volume-size</code> <i>volume_size</i>	The size, in GB (2 ³⁰ bytes), of an Amazon EBS volume that will hold the converted image. If not specified, Amazon EC2 calculates the value using the disk image file. Type: String Default: None Required: No Example: <code>-s 30</code>

Amazon Elastic Compute Cloud CLI Reference
Options

Name	Description
<code>-z, --availability-zone zone</code>	The Availability Zone for the converted VM. Type: String Valid values: Use <code>ec2-describe-availability-zones</code> for a list of values. Required: No Example: <code>-z us-east-1a</code>
<code>-b, --bucket bucket</code>	The Amazon S3 destination bucket for the manifest. Type: String Default: None Condition: Required when the <code>--manifest-url</code> parameter is not specified. Required: Yes Example: <code>-b myawsbucket</code>
<code>-o, --owner-akid access_key_id</code>	The access key ID of the bucket owner. Type: String Default: None Required: No Example: <code>AKIAIOSFODNN7EXAMPLE</code>
<code>-w, --owner-sak secret_access_key</code>	The secret access key of the bucket owner. Type: String Default: None Required: Yes Example: <code>wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code>
<code>--prefix prefix</code>	The prefix for the manifest file and disk image file parts within the Amazon S3 bucket. Type: String Default: None Required: No Example: <code>--prefix MyDiskParts</code>
<code>--manifest-url url</code>	The URL for an existing import manifest file already uploaded to Amazon S3. Type: String Default: None Condition: This option cannot be specified if the <code>--bucket</code> option is present. Required: No Example: <code>my-ami.manifest.xml</code>

Amazon Elastic Compute Cloud CLI Reference
Options

Name	Description
<code>-d, --description <i>description</i></code>	An optional, free-form comment returned verbatim during subsequent calls to <code>ec2-describe-conversion</code> tasks. Type: String Default: None Constraint: Maximum length of 255 characters Required: No Example: <code>-d Test of ec2-import-instance</code>
<code>-x, --expires <i>days</i></code>	The validity period for the signed Amazon S3 URLs that allow Amazon EC2 to access the manifest. Type: String Default: 30 days Required: No Example: <code>-x 10</code>
<code>--ignore-region-affinity</code>	Ignores the verification check to determine whether the bucket's region matches the region where the conversion-task is created. Type: None Default: None Required: No Example: <code>--ignore-region-affinity</code>
<code>--dry-run</code>	Does not create an import task, only validates that the disk image matches a known type. Type: None Default: None Required: No Example: <code>--dry-run</code>
<code>--no-upload</code>	Does not upload a disk image to Amazon S3, only creates an import task. To complete the import task and upload the disk image, use <code>ec2-resume-import</code> . Type: None Default: None Required: No Example: <code>--no-upload</code>
<code>--dont-verify-format</code>	Does not verify the file format. We don't recommend this option because it can result in a failed conversion. Type: None Default: None Required: No Example: <code>--dont-verify-format</code>

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.

Option	Description
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns the following information:

- The percentage of the import completed
- The checksum value
- Information about the volume, such as the size and format

Amazon EC2 command line tools display errors on stderr.

Example

Example Request

This example creates an import volume task that migrates a Windows Server 2008 (32-bit) volume into the AWS us-east-1 region.

```
PROMPT>ec2-import-volume 123M.vmdk -f VMDK -z us-east-1a -s 9 -b myawsbucket -
o AKIAIOSFODNN7EXAMPLE -w wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ImportVolume](#)

Related Commands

- [ec2-cancel-conversion-task](#) (p. 64)
- [ec2-delete-disk-image](#) (p. 189)
- [ec2-describe-conversion-tasks](#) (p. 272)
- [ec2-import-instance](#) (p. 507)
- [ec2-resume-import](#) (p. 622)

ec2-migrate-image

Description

Copies a bundled AMI from one region to another.

Important

This tool does not work with AMIs backed by Amazon EBS.

Note

This tool replaces [ec2-migrate-bundle](#) (p. 688).

The short version of this command is **ec2mim**.

Syntax

```
ec2-migrate-image --private-key private_key --cert cert -U url --owner-akid
access_key_id --owner-sak secret_access_key --bucket source_s3_bucket
--destination-bucket destination_s3_bucket --manifest manifest_path --acl acl
--location {US | EU} --ec2cert ec2_cert_path [--kernel kernel-id] [--ramdisk
ramdisk_id] [--no-mapping] --region mapping_region_name
```

Options

Name	Description
-K, --private-key <i>private_key</i>	The path to your PEM-encoded RSA key file. Type: String Default: Uses the EC2_PRIVATE_KEY environment variable Required: No
-C, --cert <i>cert</i>	The user's PEM encoded RSA public key certificate file. Type: String Default: Uses the EC2_CERT environment variable Required: No Example: -C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem
-U, --url <i>url</i>	The URL to use as the web service URL. Type: String Default: https://ec2.amazonaws.com Required: No Example: -U https://ec2.amazonaws.com
-o, --owner-akid <i>access_key_id</i>	The access key ID of the bucket owner. Type: String Default: None Required: Yes Example: -o AKIAIOSFODNN7EXAMPLE

Amazon Elastic Compute Cloud CLI Reference
Options

Name	Description
<code>-w, --owner-sak</code> <i>secret_access_key</i>	The secret access key of the bucket owner. Type: String Default: None Required: Yes Example: -w wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY
<code>--bucket</code> <i>source_s3_bucket</i>	The source Amazon S3 bucket where the AMI is located, followed by an optional '/'-delimited path prefix. Type: String Default: None Required: Yes Example: --bucket myawsbucket
<code>--destination-bucket</code> <i>destination_s3_bucket</i>	The destination Amazon S3 bucket, followed by an optional '/'-delimited path prefix. If the destination bucket does not exist, it is created. Type: String Default: None Required: Yes Example: --destination-bucket myotherawsbucket
<code>--manifest</code> <i>manifest</i>	The location of the Amazon S3 source manifest. Type: String Default: None Required: Yes Example: --manifest my-ami.manifest.xml
<code>--location</code> {US EU}	The location of the destination Amazon S3 bucket. Type: String Valid values: US EU Default: US Required: No Example: --location EU
<code>--acl</code> <i>acl</i>	The access control list policy of the bundled image. Type: String Valid values: public-read aws-exec-read Default: None Required: Yes Example: --acl public-read
<code>--kernel</code>	The ID of the kernel to select. Type: String Default: None Required: No Example: --kernel aki-ba3adfd3

Name	Description
<code>--ramdisk</code>	<p>The ID of the RAM disk to select.</p> <p>Important We recommend that you use PV-GRUB instead of kernels and RAM disks. For more information, see PV-GRUB: A New Amazon Kernel Image in the <i>Amazon Elastic Compute Cloud User Guide</i>.</p> <p>Type: String Default: None Required: No Example: <code>--ramdisk ari-badbad00</code></p>
<code>--no-mapping</code>	<p>Disables automatic mapping of kernels and RAM disks.</p> <p>Type: String Default: Mapping is enabled. Required: No Example: <code>--no-mapping</code></p>
<code>--region <i>region</i></code>	<p>The region to look up in the mapping file.</p> <p>Type: String Default: Amazon EC2 attempts to determine the region from the location of the Amazon S3 bucket. Required: No Example: <code>--region eu-west-1</code></p>

Common Options

Option	Description
<code>--region <i>REGION</i></code>	<p>Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option.</p> <p>Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code></p>
<code>-U, --url <i>URL</i></code>	<p>The uniform resource locator (URL) of the Amazon EC2 web service entry point.</p> <p>Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code></p>
<code>-O, --aws-access-key <i>AWS_ACCESS_KEY</i></code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>

Option	Description
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key EC2_PRIVATE_KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- Status messages describing the stages and status of the migration

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example copies the AMI specified in the `my-ami.manifest.xml` manifest from the US to the EU.

```
PROMPT> ec2-migrate-image --cert cert-THUMBPRINT.pem --private-key pk-THUMB  
PRINT.pem --owner-akid  
AKIAIOSFODNN7EXAMPLE --owner-sak wJalrXUtnFEMI/K7MDENG/bPxrFicYEXAMPLEKEY --  
bucket myawsbucket  
--destination-bucket my-eu-bucket --manifest my-ami.manifest.xml --acl aws-  
exec-read --location EU  
Copying 'my-ami.part.00'...  
Copying 'my-ami.part.01'...  
Copying 'my-ami.part.02'...  
Copying 'my-ami.part.03'...  
Copying 'my-ami.part.04'...  
Copying 'my-ami.part.05'...  
Copying 'my-ami.part.06'...  
Copying 'my-ami.part.07'...  
Copying 'my-ami.part.08'...  
Copying 'my-ami.part.09'...  
Copying 'my-ami.part.10'...  
Your new bundle is in S3 at the following location:  
my-eu-bucket/my-ami.manifest.xml
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- There is no underlying API action for this command.

Related Commands

- [ec2-register](#) (p. 566)
- [ec2-run-instances](#) (p. 633)

ec2-modify-image-attribute

Description

Modifies an attribute of an AMI.

Note

AWS Marketplace product codes cannot be modified. Images with an AWS Marketplace product code cannot be made public.

The short version of this command is **ec2mimatt**.

Syntax

```
ec2-modify-image-attribute ami_id {-l (-a entity | -r entity) | --product-code code}
```

Options

Name	Description
<i>ami_id</i>	The AMI ID. Type: String Default: None Required: Yes Example: ami-2bb65342
-p, --product-code <i>code</i>	The product code to add to the specified instance store-backed AMI. After you add a product code to an AMI, it can't be removed. Type: String Default: None Required: No Example: -p D662E989
-l, --launch-permission	Used with the --add or --remove flags to grant or revoke launch permissions. Type: String Default: None Required: Yes Example: --launch-permission
-a, --add <i>entity</i>	Adds a launch permission for the specified AWS account or for all accounts. Type: String Valid values: <i>AWS account ID</i> all Default: None Required: Yes Example: --launch-permission --add all

Name	Description
<code>-r, --remove entity</code>	Removes a launch permission for the specified AWS account or for all users. Type: String Valid values: <i>AWS account ID</i> <i>all</i> Default: None Required: Yes Example: <code>--launch-permission --remove all</code>

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>

Option	Description
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The attribute type identifier
- The ID of the AMI on which attributes are being modified
- The action performed on the attribute
- The attribute or attribute list item value type

- The attribute or attribute list item value

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example makes the AMI public (for example, so any AWS account can launch it).

```
PROMPT> ec2-modify-image-attribute ami-1a2b3c4d -l -a all  
launchPermission ami-1a2b3c4d ADD group all
```

Example Request

This example makes the AMI private (for example, so only you as the owner can launch it).

```
PROMPT> ec2-modify-image-attribute ami-1a2b3c4d -l -r all  
launchPermission ami-1a2b3c4d REMOVE group all
```

Example Request

This example grants launch permission to the AWS account with ID 444455556666.

```
PROMPT> ec2-modify-image-attribute ami-2bb65342 -l -a 444455556666  
launchPermission ami-2bb65342 ADD userId 444455556666
```

Example Request

This example removes launch permission from the AWS account with ID 444455556666.

```
PROMPT> ec2-modify-image-attribute ami-1a2b3c4d -l -r 444455556666  
launchPermission ami-1a2b3c4d REMOVE userId 444455556666
```

Example Request

This example adds the 774F4FF8 product code to the ami-1a2b3c4d AMI.

```
PROMPT> ec2-modify-image-attribute ami-1a2b3c4d -p 774F4FF8  
productcodes ami-1a2b3c4d productCode 774F4FF8
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ModifyImageAttribute](#)

Related Commands

- [ec2-reset-image-attribute](#) (p. 608)
- [ec2-describe-image-attribute](#) (p. 295)

ec2-modify-instance-attribute

Description

Modifies the specified attribute of the specified instance. You can specify only one attribute at a time.

Note

To modify some attributes, the instance must be stopped. For more information, see [Modifying Attributes of a Stopped Instance](#) in the *Amazon Elastic Compute Cloud User's Guide*.

The short version of this command is **ec2minatt**.

Syntax

```
ec2-modify-instance-attribute instance_id { --block-device-mapping mapping |  
--disable-api-termination Boolean | --ebs-optimized Boolean--> | --group-id  
group_id [...] | --instance-initiated-shutdown-behavior behavior |  
--instance-type type | --kernel kernel_id | --ramdisk ramdisk_id |  
--source-dest-check Boolean | --user-data user_data }
```

Options

Name	Description
<i>instance_id</i>	The instance ID. Type: String Default: None Required: Yes Example: i-43a4412a
-b, --block-device-mapping <i>mapping</i>	Modifies the <code>DeleteOnTermination</code> attribute for volumes that are currently attached. The volume must be owned by the caller. If no value is specified for <code>DeleteOnTermination</code> , the volume is deleted when the instance is terminated. To add instance store volumes to an Amazon EBS-backed instance, you must add them when you launch the instance. For more information, see Updating the Block Device Mapping when Launching an Instance in the <i>Amazon Elastic Compute Cloud User Guide</i> . Type: BlockDeviceMapping Required: No Example: -b "/dev/sdb=:false"

Amazon Elastic Compute Cloud CLI Reference
Options

Name	Description
<code>--disable-api-termination</code> <i>Boolean</i>	<p>Whether the instance can be terminated using the EC2 API. A value of <code>true</code> means you can't terminate the instance using the API (the instance is "locked"). A value of <code>false</code> means you can terminate the instance using the API (the instance is "unlocked"). Set this attribute to <code>true</code> to prevent the instance from being terminated using the EC2 API.</p> <p>Type: Boolean Default: <code>false</code> Required: No Example: <code>--disable-api-termination true</code></p>
<code>--ebs-optimized</code> <i>Boolean</i>	<p>Whether the instance is optimized for EBS I/O. This optimization provides dedicated throughput to Amazon EBS and an optimized configuration stack to provide optimal EBS I/O performance. This option isn't available on all instance types. Additional usage charge apply when using this option.</p> <p>Type: Boolean Default: <code>false</code> Required: No Example: <code>--ebs-optimized true</code></p>
<code>-g, --group-id group_id</code>	<p>[EC2-VPC] Modify the security groups an instance is in. The new set of groups you specify replaces the current set. You must specify at least one group, even if it's just the default security group for the VPC. You must specify the group ID and not the group name.</p> <p>Type: String Default: None Required: No Example: <code>-g sg-1a1a1a1a -g sg-9b9b9b9b</code></p>
<code>--instance-initiated-shutdown-behavior</code> <i>behavior</i>	<p>Whether the instance stops or terminates when you initiate instance shutdown.</p> <p>Type: String Valid values: <code>stop terminate</code> Default: <code>stop</code> Required: No Example: <code>--instance-initiated-shutdown-behavior stop</code></p>
<code>-t, --instance-type type</code>	<p>The type of the instance. See Available Instance Types for more information. An <code>InvalidInstanceAttributeValue</code> error will be returned if the instance type is not valid.</p> <p>Type: String Default: <code>m1.small</code> Required: No Example: <code>-t m1.large</code></p>

Name	Description
<code>--kernel <i>kernel_id</i></code>	The ID of the kernel associated with the AMI. Type: String Default: None Required: No Example: <code>--kernel aki-1a2b3c4d</code>
<code>--ramdisk <i>ramdisk_id</i></code>	The ID of the RAM disk associated with the AMI. Important We recommend that you use PV-GRUB instead of kernels and RAM disks. For more information, see PV-GRUB: A New Amazon Kernel Image in the <i>Amazon Elastic Compute Cloud User Guide</i> . Type: String Default: None Required: No Example: <code>--ramdisk ari-1a2b3c4d</code>
<code>--source-dest-check <i>Boolean</i></code>	Enables an instance in a VPC to perform NAT. The attribute controls whether source/destination checking is enabled on the instance. A value of <code>true</code> means checking is enabled, and <code>false</code> means checking is disabled. The value must be <code>false</code> for the instance to perform NAT. For more information, see NAT Instances in the <i>Amazon Virtual Private Cloud User Guide</i> . Type: Boolean Default: <code>true</code> Required: No Example: <code>--source-dest-check false</code>
<code>--user-data <i>user_data</i></code>	The Base64-encoded MIME user data to be made available to the instances in this reservation. Type: String Default: None Required: No Example: <code>--user-data "My user data"</code>

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The attribute type identifier
- The ID of the instance on which attributes are being modified
- The new attribute value

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example changes the kernel for the instance.

```
PROMPT> ec2-modify-instance-attribute i-10a64379 --kernel aki-f70657b2
kernel i-10a64379 aki-f70657b2
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ModifyInstanceAttribute](#)

Related Commands

- [ec2-describe-instance-attribute](#) (p. 308)
- [ec2-reset-instance-attribute](#) (p. 611)

ec2-modify-network-interface-attribute

Description

Modifies a network interface attribute. You can specify only one attribute at a time.

The short version of this command is **ec2mnicatt**.

Syntax

```
ec2-modify-network-interface-attribute interface_id -d, --description description  
-a, --attachment attachment_id --delete-on-termination boolean  
--source-dest-check boolean --group-id group_id
```

Options

Name	Description
<code>-d, --description <i>description</i></code>	Changes the description of the network interface. Type: String Default: None Required: Yes Example: -d "My Second ENI"
<code>-a, --attachment <i>attachment_id</i></code>	Changes properties of the attachment. Type: String Default: None Constraints: Must be used in conjunction with --delete-on-termination. Required: Yes Example: -a eni-attach-09703260
<code>--delete-on-termination <i>boolean</i></code>	Sets whether the network interface shall be deleted when the network interface is detached. Type: String Default: None Constraints: Must be used in conjunction with --attachment. Required: Yes Example: -delete-on-termination false
<code>--source-dest-check <i>boolean</i></code>	Sets whether to enable the source/dest check on traffic through this network interface. Type: String Default: None Valid values: true false Required: Yes Example: --source-dest-check false

Name	Description
<code>--group-id group_id</code>	Replaces the security groups for this network interface. Type: String Default: None Required: Yes Example: <code>--group-id sg-b90619d5 -group id sg-a92639c9</code>

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>

Option	Description
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns the name of the attribute that was modified.

Amazon EC2 command line tools display errors on `stderr`.

Examples

Example Request

This example adds a description to the network interface.

```
PROMPT> ec2-modify-network-interface-attribute eni-b35da6da -d "This is an ENI"  
NETWORKINTERFACE    eni-b35da6da    description
```

This example turns off source/destination checking for network traffic across the network interface.

```
PROMPT> ec2-modify-network-interface-attribute eni-b35da6da --source-dest-check  
false  
NETWORKINTERFACE    eni-b35da6da    sourceDestCheck  
SOURCEDESTCHECK     false
```

This example changes the security group for the specified network interface.

```
PROMPT> ec2-modify-network-interface-attribute eni-b35da6da --group-id sg-  
8ea1bce2  
NETWORKINTERFACE    eni-b35da6da    group  
GROUPID             sg-8ea1bce2
```

This example retains the network interface when it is detached from an instance.

```
PROMPT> ec2-modify-network-interface-attribute eni-b35da6da --delete-on-termin  
ation false -a eni-attach-083fda61  
NETWORKINTERFACE    eni-b35da6da    attachment
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ModifyNetworkInterfaceAttribute](#)

Related Commands

- [ec2-attach-network-interface](#) (p. 37)
- [ec2-create-network-interface](#) (p. 126)
- [ec2-delete-network-interface](#) (p. 209)
- [ec2-describe-network-interface-attribute](#) (p. 348)
- [ec2-describe-network-interfaces](#) (p. 352)
- [ec2-detach-network-interface](#) (p. 467)
- [ec2-reset-network-interface-attribute](#) (p. 615)

ec2-modify-snapshot-attribute

Description

Adds or remove permission settings for the specified snapshot.

The short version of this command is **ec2msnapatt**.

Note

Snapshots with AWS Marketplace product codes cannot be made public.

Syntax

```
ec2-modify-snapshot-attribute snapshot_id -c [--add entity | --remove entity]
```

Options

Name	Description
<i>snapshot_id</i>	The ID of the snapshot. Type: String Default: None Required: Yes Example: snap-78a54011
-c, --create-volume-permission	Modifies the create volume permissions of the snapshot. Type: String Default: None Required: Yes Example: -c
-a, --add <i>entity</i>	Adds a permission for the specified AWS account or for all accounts. Type: String Valid values: <i>AWS account ID</i> all Default: None Required: No Example: -c --add all
--remove <i>entity</i>	Removes a permission for the specified AWS account or for all accounts. Type: String Valid values: <i>AWS account ID</i> all Default: None Required: No Example: -c --remove all

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.

Option	Description
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The `createVolumePermission` identifier
- The ID of the snapshot
- The action performed on the attribute
- The attribute or attribute list item value type
- The attribute or attribute list item value

Amazon EC2 command line tools display errors on `stderr`.

Examples

Example Request

This example makes the `snap-1a2b3c4d` snapshot public.


```
PROMPT> ec2-modify-snapshot-attribute snap-1a2b3c4d -c --add all  
createVolumePermission snap-1a2b3c4d ADD group all
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ModifySnapshotAttribute](#)

Related Commands

- [ec2-create-snapshot](#) (p. 146)
- [ec2-describe-snapshot-attribute](#) (p. 391)
- [ec2-describe-snapshots](#) (p. 395)
- [ec2-reset-snapshot-attribute](#) (p. 618)

ec2-modify-volume-attribute

Description

Modifies a volume attribute.

By default, all I/O operations for the volume are suspended when the data on the volume is determined to be potentially inconsistent, to prevent undetectable, latent data corruption. The I/O access to the volume can be resumed by first issuing the [ec2-enable-volume-io](#) (p. 490) command to enable I/O access and then checking the data consistency on your volume.

You can change the default behavior to resume I/O operations without issuing the [ec2-enable-volume-io](#) (p. 490) command by setting the `auto-enable-io` attribute of the volume to `true`. We recommend that you change this attribute only for volumes that are stateless or disposable, or for boot volumes.

The short version of this command is `ec2mvolatt`.

Syntax

```
ec2-modify-volume-attribute volume_id ... --attribute_flag ATTRIBUTE_VALUE
```

Options

Name	Description
<i>volume_id</i>	The ID of the volume. Type: String Required: Yes Example: vol-4282672b
<code>-a --auto-enable-io</code>	Determines whether the volume should be auto-enabled for I/O operations. Type: Boolean Required: Yes Example: <code>--auto-enable-io true</code>

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The ID of the volume
- A Boolean value for the attribute

Amazon EC2 command line tools display errors on stderr.

Example

Example Request

This example modifies the attribute of the volume vol-999999.

```
PROMPT> ec2-modify-volume-attribute vol-999999 --auto-enable-io true
VolumeId      Attribute
vol-999999    autoEnableIo
AUTO-ENABLE-IO true
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ModifyVolumeAttribute](#)

Related Commands

- [ec2-describe-volume-attribute](#) (p. 428)
- [ec2-describe-volume-status](#) (p. 432)
- [ec2-enable-volume-io](#) (p. 490)

ec2-modify-vpc-attribute

Description

Modifies the specified attribute of the specified VPC.

Syntax

```
ec2-modify-vpc-attribute --vpc vpc-id [--dns-support {true|false}]
[--dns-hostname {true|false}]
```

Options

Name	Description
<code>-c, --vpc <i>vpc-id</i></code>	The ID of the VPC. Type: String Required: Yes Example: <code>vpc-1a2b3c4d</code>
<code>-s, --dns-support {true false}</code>	Specifies whether the Amazon DNS server is enabled for the VPC. If this attribute is <code>true</code> , this DNS resolution is enabled; otherwise, this DNS resolution is disabled. Type: Boolean Default: <code>true</code> Required: No Example: <code>--dns-support true</code>
<code>-d, --dns-hostnames {true false}</code>	Specifies whether DNS hostnames are provided for the instances launched in this VPC. If this attribute is <code>true</code> , DNS hostnames are provided; otherwise, DNS hostnames are not provided. You can only set this attribute to <code>true</code> if <code>--dns-support</code> is also <code>true</code> . Type: Boolean Default: <code>true</code> Required: No Example: <code>--dns-hostnames false</code>

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns `true` if the command succeeded and `false` otherwise.

Examples

Example Request

This example disables support for DNS hostnames in the VPC with the ID `vpc-1a2b3c4d`.

```
PROMPT> ec2-modify-vpc-attribute --vpc vpc-1a2b3c4d --dns-hostnames false
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ModifyVpcAttribute](#)

Related Commands

- [ec2-describe-vpc-attribute](#) (p. 444)

ec2-monitor-instances

Description

Enables monitoring for a running instance. For more information, see [Monitoring Your Instances and Volumes](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2min**.

Syntax

```
ec2-monitor-instances instance_id [instance_id...]
```

Options

Name	Description
<i>instance_id</i>	The instance ID. Type: String Default: None Required: Yes Example: i-43a4412a

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key EC2_PRIVATE_KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The instance ID
- The monitoring state

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example enables monitoring for `i-43a4412a` and `i-23a3397d`.

```
PROMPT> ec2-monitor-instances i-43a4412a i-23a3397d
i-43a4412a monitoring-pending
i-23a3397d monitoring-pending
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [MonitorInstances](#)

Related Commands

- [ec2-run-instances](#) (p. 633)
- [ec2-unmonitor-instances](#) (p. 660)

ec2-purchase-reserved-instances-offering

Description

Purchases a Reserved Instance for use with your account. With Amazon EC2 Reserved Instances, you obtain a capacity reservation for a certain instance configuration over a specified period of time. You pay a lower usage rate than with On-Demand instances for the time that you actually use the capacity reservation.

Starting with the 2011-11-01 API version, AWS expanded its offering of Amazon EC2 Reserved Instances to address a range of projected instance usage. There are three types of Reserved Instances based on customer utilization levels: *Heavy Utilization*, *Medium Utilization*, and *Light Utilization*.

The Medium Utilization offering type is equivalent to the Reserved Instance offering available before API version 2011-11-01. If you are using tools that predate the 2011-11-01 API version, `ec2-describe-reserved-instances-offerings` will only list information about the Medium Utilization Reserved Instance offering type.

For information about Reserved Instance pricing tiers, see [Understanding Reserved Instance pricing tiers](#) in the *Amazon Elastic Compute Cloud User Guide*. For more information about Reserved Instances, see [Reserved Instances](#) also in the *Amazon Elastic Compute Cloud User Guide*.

You determine the type of the Reserved Instances offerings by including the optional `offeringType` parameter when calling `ec2-describe-reserved-instances-offerings`. After you've identified the Reserved Instance with the offering type you want, specify its `ReservedInstancesOfferingId` when you call `ec2-purchase-reserved-instances-offering`.

Starting with the 2012-08-15 API version, you can also purchase Reserved Instances from the Reserved Instance Marketplace. The Reserved Instance Marketplace matches sellers who want to resell Reserved Instance capacity that they no longer need with buyers who want to purchase additional capacity. Reserved Instances bought from third parties through the Reserved Instance Marketplace work like any other Reserved Instances.

By default, with the 2012-08-15 API version, `ec2-describe-reserved-instances-offerings` returns information about Amazon EC2 Reserved Instances available directly from AWS, plus instance offerings available from third parties, on the Reserved Instance Marketplace. If you are using tools that predate the 2012-08-15 API version, the `ec2-describe-reserved-instances-offerings` action will only list information about Amazon EC2 Reserved Instances available directly from AWS.

For more information about the Reserved Instance Marketplace, see [Reserved Instance Marketplace](#) in the *Amazon Elastic Compute Cloud User Guide*.

You determine the Reserved Instance Marketplace offerings by specifying `true` for the optional `includeMarketplace` parameter when calling `ec2-describe-reserved-instances-offerings`. After you've identified the Reserved Instance with the offering type you want, specify its `reservedInstancesOfferingId` when you call `ec2-purchase-reserved-instances-offering`.

The short version of this command is `ec2prio`.

Syntax

```
ec2-purchase-reserved-instances-offering --offering offering --instance-count count [-1 limit-price]
```

Options

Name	Description
<code>-o, --offering offering</code>	The offering ID of the Reserved Instance to purchase. Type: String Default: None Required: Yes Example: <code>-o 4b2293b4-5813-4cc8-9ce3-1957fexample</code>
<code>-c, --instance-count count</code>	The number of Reserved Instances to purchase. Type: Integer Default: None Required: Yes Example: <code>-c 5</code>
<code>-l limit-price</code>	The maximum price that you are willing to pay. Type: Integer Default: None Required: Yes Example: <code>-c 5</code>

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key EC2_PRIVATE_KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

The command returns a table that contains the following information:

- `RESERVEDINSTANCES` identifier
- The ID of the purchased Reserved Instances

Amazon EC2 command line tools display errors on `stderr`.

Examples

This example illustrates a purchase of a Reserved Instances offering.

```
PROMPT> ec2-purchase-reserved-instances-offering --offering 649fd0c8-becc-49d9-  
b259-fc8e2example --instance-count 3  
RESERVEDINSTANCES b847fa93-0c31-405b-b745-b6bf0example
```

Related Operations

- [ec2-describe-reserved-instances-offerings](#) (p. 378)
- [ec2-describe-reserved-instances](#) (p. 367)

ec2-reboot-instances

Description

Requests a reboot of one or more instances. This operation is asynchronous; it only queues a request to reboot the specified instances. The operation will succeed if the instances are valid and belong to you. Requests to reboot terminated instances are ignored.

Note

If a Linux/UNIX instance does not cleanly shut down within four minutes, Amazon EC2 will perform a hard reboot.

The short version of this command is **ec2reboot**.

Syntax

```
ec2-reboot-instances instance_id [instance_id ...]
```

Options

Name	Description
<i>instance_id</i>	One or more instance IDs of instances. Type: String Default: None Required: Yes Example: i-3ea74257

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- This command displays no output on success

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example reboots an instance.

```
PROMPT> ec2-reboot-instances i-28a64341  
-
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [RebootInstances](#)

Related Commands

- [ec2-run-instances](#) (p. 633)

ec2-register

Description

Registers a new AMI with Amazon EC2. When you're creating an AMI, this is the final step you must complete before you can launch an instance from the AMI. For more information about creating AMIs, see [Creating Your Own AMIs](#) in the *Amazon Elastic Compute Cloud User Guide*.

Note

For Amazon EBS-backed instances, the `ec2-create-image` command creates and registers the AMI in a single request, so you don't have to register the AMI yourself.

You can also use `ec2-register` to create an Amazon EBS-backed AMI from a snapshot of a root device volume. For more information, see [Launching an Instance from a Snapshot](#) in the *Amazon Elastic Compute Cloud User Guide*.

If needed, you can deregister an AMI at any time. Any modifications you make to an AMI backed by Amazon EC2 instance store invalidates its registration. If you make changes to an image, deregister the previous image and register the new image.

The short version of this command is **ec2reg**.

Note

You cannot register an image where a secondary (non-root) snapshot has AWS Marketplace product codes.

Syntax

```
ec2-register { [manifest] -n name [-a architecture] [-b mapping [...]] [-d description] [-s snapshot_id] [--kernel kernel_id] [--ramdisk ramdisk_id] [--root-device-name name] }
```

Options

Name	Description
<i>manifest</i>	The full path to your AMI manifest in Amazon S3 storage. Type: String Default: None Required: Conditional Condition: Required if registering an instance store-backed AMI. Example: myawsbucket/image.manifest.xml
-n, --name <i>name</i>	A name for your AMI. Type: String Default: None Constraints: 3-128 alphanumeric characters, parentheses (()), commas (,), slashes (/), dashes (-), or underscores(_) Required: Yes Example: -n "Standard Web Server"

Amazon Elastic Compute Cloud CLI Reference Options

Name	Description
<code>-d, --description <i>description</i></code>	The description of the AMI. Type: String Default: None Constraints: Up to 255 characters. Required: No Example: <code>-d "Standard Web Server AMI"</code>
<code>-a, --architecture <i>architecture</i></code>	The architecture of the image. Type: String Valid values: <code>i386 x86_64</code> Default: None Required: No Example: <code>-a i386</code>
<code>--kernel</code>	The ID of the kernel associated with the image. Type: String Default: None Required: No Example: <code>--kernel aki-ba3adfd3</code>
<code>--ramdisk</code>	The ID of the RAM disk to associate with the image. Important We recommend that you use PV-GRUB instead of kernels and RAM disks. For more information, see PV-GRUB: A New Amazon Kernel Image in the <i>Amazon Elastic Compute Cloud User Guide</i> . Type: String Default: None Required: No Example: <code>--ramdisk ari-badbad00</code>
<code>--root-device-name <i>name</i></code>	The root device name (for example, <code>/dev/sda1</code> or <code>xvda</code>). Type: String Default: <code>/dev/sda1</code> Condition: Required if registering an Amazon EBS-backed AMI. Required: No Example: <code>--root-device-name /dev/sda1</code>

Name	Description
<p><code>-b, --block-device-mapping <i>mapping</i></code></p>	<p>The block device mapping for the instance. This argument is passed in the form of <code><devicename>=<blockdevice></code>. The <i>devicename</i> is the name of the device within Amazon EC2. The <i>blockdevice</i> can be one of the following values:</p> <ul style="list-style-type: none"> • <code>none</code> - Suppresses an existing mapping of the device from the AMI used to launch the instance. For example: <code>"/dev/sdc=none"</code>. • <code>ephemeral[0..3]</code> - An instance store volume to be mapped to the device. For example: <code>"/dev/sdc=ephemeral0"</code>. • <code>[snapshot-id]:[volume-size]:[true false]:[standard io1[:iops]]</code> - An EBS volume to be mapped to the device. <i>[snapshot-id]</i> To create a volume from a snapshot, specify the snapshot ID. <i>[volume-size]</i> To create an empty EBS volume, omit the snapshot ID and specify a volume size instead. For example: <code>"/dev/sdh=:20"</code>. <i>[delete-on-termination]</i> To prevent the volume from being deleted on termination of the instance, specify <code>false</code>. The default is <code>true</code>. <i>[volume-type]</i> To create a Provisioned IOPS volume, specify <code>io1</code>. The default volume type is <code>standard</code>. If the volume type is <code>io1</code>, you can also provision the number of IOPS that the volume supports. For example, <code>"/dev/sdh=snap-7eb96d16::false:io1:500"</code>. <p>You can specify multiple <i>block-device-mapping</i> arguments in one call.</p> <p>For more detailed information about block device mapping, see Block Device Mapping in the <i>Amazon Elastic Compute Cloud User Guide</i>.</p> <p>Type: String Default: None Required: Conditional</p> <p>Condition: If registering an Amazon EBS-backed AMI from a snapshot, at a minimum you must specify a block device mapping entry for the root device. Be sure to include the device name (<code>/dev/sda1</code> or <code>xvda</code>) and the snapshot ID.</p> <p>Example: <code>-b "/dev/sda1=snap-7eb96d16"</code></p> <p>Note On Windows, the <i>mapping</i> argument must be enclosed in double quotes, as shown in the example.</p>
<p><code>-s, --snapshot <i>snapshot</i></code></p>	<p>The ID of the Amazon EBS snapshot to be used as the root device.</p> <p>Type: String Default: None Required: No</p> <p>Example: <code>-s snap-78a54011</code></p>

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.

Option	Description
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The IMAGE identifier
- The ID of the newly registered machine image

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example registers the AMI specified in the `image.manifest.xml` manifest file, located in the bucket named `myawsbucket`.

```
PROMPT> ec2-register myawsbucket/image.manifest.xml -n MyImage
IMAGE ami-1a2b3c4d
```

Example Request

This example registers an Amazon EBS snapshot to create an AMI backed by Amazon EBS.

```
PROMPT> ec2-register -n MyImage -s snap-1a2b3c4d  
IMAGE ami-1a2b3c4d
```

Example Request

This example registers the AMI with an Amazon EBS snapshot as the root device, a separate snapshot as a secondary device, and an empty 100 GiB Amazon EBS volume as a storage device.

```
PROMPT> ec2-register -n MyImage -s snap-1a2b3c4d -b /dev/sdb=snap-2a2b3c4d -b  
/dev/sdc=:100  
IMAGE ami-1a2b3c4d
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [RegisterImage](#)

Related Commands

- [ec2-deregister](#) (p. 249)
- [ec2-describe-images](#) (p. 299)
- [ec2-run-instances](#) (p. 633)

ec2-release-address

Description

Releases an Elastic IP address allocated to your account.

Important

After releasing an Elastic IP address, it is released to the public IP address pool for the platform and might be unavailable to you. Make sure to update your DNS records and any servers or devices that communicate with the address. If you attempt to release an Elastic IP address that you already released, you'll get an `AuthFailure` error if the address is already allocated to another AWS account.

An Elastic IP address is for use either in the EC2-Classic platform or in a VPC. For more information, see [Elastic IP Addresses](#) in the *Amazon Elastic Compute Cloud User Guide*.

[EC2-Classic, default VPC] Releasing an Elastic IP address automatically disassociates it from any instance that it's associated with. To disassociate an Elastic IP address without releasing it, use the `ec2-disassociate-address` command.

[nondefault VPC] You must use the `ec2-disassociate-address` command to disassociate the Elastic IP address before you try to release it. Otherwise, Amazon EC2 returns an error (`InvalidIPAddress.InUse`).

The short version of this command is `ec2reladdr`.

Syntax

```
ec2-release-address [ip_address | -a allocation_id]
```

Options

Name	Description
<i>ip_address</i>	[EC2-Classic] The Elastic IP address. Type: String Default: None Required: Conditional Condition: Required for EC2-Classic. Example: 192.0.2.1
-a, --allocation-id <i>allocation_id</i>	[EC2-VPC] The allocation ID. Type: String Default: None Required: Conditional Condition: Required for EC2-VPC. Example: -a eipalloc-5723d13e

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.

Option	Description
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The ADDRESS identifier
- The Elastic IP address

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example releases an Elastic IP address for EC2-Classic.

```
PROMPT> ec2-release-address 192.0.2.1
ADDRESS 192.0.2.1
```

Example Request

This example releases an Elastic IP address for EC2-VPC.

```
PROMPT> ec2-release-address -a eipalloc-5723d13e  
ADDRESS      eipalloc-5723d13e
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ReleaseAddress](#)

Related Commands

- [ec2-allocate-address](#) (p. 12)
- [ec2-associate-address](#) (p. 20)
- [ec2-describe-addresses](#) (p. 256)
- [ec2-disassociate-address](#) (p. 482)

ec2-replace-network-acl-association

Description

Changes which network ACL a subnet is associated with. By default when you create a subnet, it's automatically associated with the default network ACL. For more information about network ACLs, see [Network ACLs](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2repnaclassoc**.

Syntax

`ec2-replace-network-acl-association` *network_acl_association_id* **-a** *network_acl_id*

Options

Name	Description
<i>network_acl_association_id</i>	The ID representing the current association between the original network ACL and the subnet. Type: String Default: None Required: Yes Example: aclassoc-33ae4b5a
-a, --network-acl <i>network_acl_id</i>	The ID of the new ACL to associate with the subnet. Type: String Default: None Required: Yes Example: -a acl-10b95c79

Common Options

Option	Description
--region <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
-U, --url <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The ASSOCIATION identifier
- The new association ID and the network ACL ID

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example starts with a network ACL associated with a subnet, and a corresponding association ID `aclassoc-e5b95c8c`. You want to associate a different network ACL (`acl-5fb85d36`) with the subnet. The result is a new association ID representing the new association.

```
PROMPT> ec2-replace-network-acl-association aclassoc-e5b95c8c -a acl-5fb85d36  
ASSOCIATION      aclassoc-17b85d7e acl-5fb85d36
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ReplaceNetworkAclAssociation](#)

Related Commands

- [ec2-create-network-acl](#) (p. 118)
- [ec2-delete-network-acl](#) (p. 202)

- [ec2-describe-network-acls](#) (p. 342)

ec2-replace-network-acl-entry

Description

Replaces an entry (rule) in a network ACL. For more information about network ACLs, see [Network ACLs](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2repnae**.

Syntax

```
ec2-replace-network-acl-entry acl_id -n rule_number [--egress] -P protocol -r cidr [-p port_range] [-t icmp_type_code] { --allow | --deny }
```

Options

Name	Description
<i>acl_id</i>	The ID of the ACL. Type: String Default: None Required: Yes Example: acl-5fb85d36
<i>-n, --rule-number rule_number</i>	The rule number of the entry to replace. Type: Number Default: None Required: Yes Example: -n 100
<i>--egress</i>	Optional flag to indicate whether to replace the egress rule. Default: If no value is specified, we replace the ingress rule Required: No
<i>-P, --protocol protocol</i>	The IP protocol. You can specify <code>all</code> or <code>-1</code> to mean all protocols. Type: String Valid values: <code>all</code> <code>-1</code> <code>tcp</code> <code>udp</code> <code>icmp</code> or any protocol number (for a list, see Protocol Numbers). Required: Yes Example: -P 6
<i>-r, --cidr cidr</i>	The CIDR range to allow or deny, in CIDR notation. Type: String Default: None Required: Yes Example: -r 172.16.0.0/24

Name	Description
<code>-p, --port-range port_range</code>	For TCP or UDP: The range of ports to allow. Type: String Default: None Valid values: A single integer or a range (min-max). You can specify -1 to mean all ports (for example, port range 0-65535). Condition: Required if specifying <code>tcp</code> or <code>udp</code> (or the equivalent number) for the protocol. Required: Conditional Example: <code>-p 80-84</code>
<code>-t, --icmp-type-code icmp_type_code</code>	For ICMP: The ICMP type and code using format <code>type:code</code> , where both are integers. You can use -1 for the type or code to mean all types or all codes Type: String Default: None Required: Conditional Condition: Required if specifying <code>icmp</code> (or the equivalent number) for the protocol. Example: <code>-t -1:-1</code>
<code>--allow</code>	Allows any traffic matching the rule. Required: Conditional Condition: Either <code>--allow</code> or <code>--deny</code> must be specified, but not both.
<code>--deny</code>	Denies any traffic matching the rule. Required: Conditional Condition: Either <code>--allow</code> or <code>--deny</code> must be specified, but not both.

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- Success status (`true` or `false`)

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example replaces the egress entry numbered 110 in the network ACL with ID `acl-2cb85d45`. The new rule denies egress traffic destined for anywhere (`0.0.0.0/0`) on TCP port 139.

```
PROMPT> ec2-replace-network-acl-entry acl-2cb85d45 -n 110 --egress -r 0.0.0.0/0
-P tcp -p 139 --deny
RETURN true
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ReplaceNetworkAclEntry](#)

Related Commands

- [ec2-create-network-acl-entry](#) (p. 121)
- [ec2-delete-network-acl-entry](#) (p. 205)
- [ec2-describe-network-acls](#) (p. 342)

ec2-replace-route

Description

Replaces an existing route within a route table in a VPC. For more information about route tables, see [Route Tables](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2reprt**.

Syntax

```
ec2-replace-route route_table_id -r cidr {-g gateway_id | -i instance_id | -n,
--network-interface interface_id}
```

Options

Name	Description
<i>route_table_id</i>	The ID of the route table. Type: String Default: None Required: Yes Example: rtb-5da34634
-r, --cidr <i>cidr</i>	The CIDR address block used for the destination match. Routing decisions are based on the most specific match. Type: String Default: None Required: Yes Example: -r 0.0.0.0/0
-g, --gateway <i>gateway_id</i>	The ID of a gateway in your VPC. Type: String Default: None Required: Conditional Condition: You must provide one of the following: a gateway ID, instance ID, or a network interface ID. Example: -g igw-68a34601
-i, --instance <i>instance_id</i>	The ID of a NAT instance in your VPC. Type: String Default: None Required: Conditional Condition: You must provide one of the following: a gateway ID, instance ID, or a network interface ID. Example: -i i-a7c871e3

Name	Description
<code>-n, --network-interface interface_id</code>	The network interface associated with the route. Type: String Default: None Required: Conditional Condition: You must provide one of the following: a gateway ID, instance ID, or a network interface. Example: <code>-n eni-5b729933</code>

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>

Option	Description
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- Success status (`true` or `false`)

Amazon EC2 command line tools display errors on `stderr`.

Examples

Example Request

This example replaces a route in the route table with ID `rtb-e4ad488d`. The new route matches the CIDR `10.0.0.0/8` and sends it to the virtual private gateway with ID `vgw-1d00376e`.

```
PROMPT> ec2-replace-route rtb-e4ad488d -r 10.0.0.0/8 -g vgw-1d00376e  
RETURN true
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ReplaceRoute](#)

Related Commands

- [ec2-create-route](#) (p. 139)
- [ec2-delete-route](#) (p. 215)
- [ec2-describe-route-tables](#) (p. 386)

ec2-replace-route-table-association

Description

Changes the route table associated with a subnet in a VPC.

You can also use this to change which table is the main route table in the VPC. You just specify the main route table's association ID and the route table that you want to be the new main route table.

After you execute this action, the subnet uses the routes in the new route table it's associated with. For more information about route tables, see [Route Tables](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is **ec2reprtassoc**.

Syntax

```
ec2-replace-route-table-association route_table_association_id -r route_table_id
```

Options

Name	Description
<i>route_table_association_id</i>	The ID for the existing association to replace (which was returned to you when you associated the original route table with the subnet). Type: String Default: None Required: Yes Example: rtbassoc-93a045fa
-r <i>route_table_id</i>	The ID of the new route table to associate with the subnet. Type: String Default: None Required: Yes Example: -r rtb-6aa34603

Common Options

Option	Description
--region <i>REGION</i>	Overrides the region specified by the EC2_URL environment variable and the URL specified by the -U option. Default: The value of the EC2_URL environment variable, or us-east-1 if EC2_URL isn't set. Example: --region eu-west-1

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the EC2_PRIVATE_KEY environment variable. Example: -K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the EC2_CERT environment variable. Example: -C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem

Output

This command returns a table that contains the following information:

- The ASSOCIATION identifier
- The new association ID
- The route table ID

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example starts with a route table associated with a subnet, and a corresponding association ID rtbassoc-f8ad4891. You want to associate a different route table (table rtb-f9ad4890) to the subnet. The result is a new association ID representing the new association.

```
PROMPT> ec2-replace-route-table-association rtbassoc-f8ad4891 -r rtb-f9ad4890
ASSOCIATION    rtbassoc-61a34608 rtb-f9ad4890
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ReplaceRouteTableAssociation](#)

Related Commands

- [ec2-create-route-table](#) (p. 143)
- [ec2-delete-route-table](#) (p. 218)
- [ec2-describe-route-tables](#) (p. 386)
- [ec2-disassociate-route-table](#) (p. 486)
- [ec2-replace-route-table-association](#) (p. 588)

ec2-report-instance-status

Description

Reports the status for instances that you own.

This command works only for instances that are in the `running` state. If you disagree with the instance status returned by the `ec2-report-instance-status` action, use `ec2-report-instance-status` command to report a more accurate status. Amazon EC2 collects this information to improve the accuracy of status checks.

Note

Use of this action does not change the value returned by `ec2-report-instance-status`.

To report an instance's status, specify an instance ID with the `INSTANCE` parameter and a reason code with the `--reason` parameter that applies to that instance. The following table contains descriptions of all available reason codes.

instance-stuck-in-state

My instance is stuck in a state.

unresponsive

My instance is unresponsive.

not-accepting-credentials

My instance is not accepting my credentials.

password-not-available

A password is not available for my instance.

performance-network

My instance is experiencing performance problems which I believe are network related.

performance-instance-store

My instance is experiencing performance problems which I believe are related to the instance stores.

performance-ebs-volume

My instance is experiencing performance problems which I believe are related to an EBS volume.

performance-other

My instance is experiencing performance problems.

other

Other, explained in the submitted description parameter.

The short version of this command is `ec2rep`.

Syntax

```
ec2-report-instance-status instance_id --status value --reason value  
[--start-time date] [--end-time date] [--description description]
```

Options

Name	Description
<i>instance_id</i>	The IDs of the instances. Type: String Required: Yes Example: i-15a4417c
<code>--status value</code>	The status of all instances listed in the <i>instance_id</i> parameter. Type: String Valid values: ok impaired Required: Yes
<code>--reason value</code>	A reason code that describes a specific instance's health state. Each code you supply corresponds to an instance ID that you supply with the <i>InstanceID.n</i> parameter. See the Description (p. 592) section for descriptions of each reason code. Type: String Valid values: instance-stuck-in-state unresponsive not-accepting-credentials password-not-available performance-network performance-instance-store performance-ebs-volume performance-other other Required: Yes
<code>--start-time date</code>	The time at which the reported instance health state began. The date uses the format: yyyy-MM-dd'T'HH:mm:ss Type: DateTime Required: No Example: 2011-07-25T14:00:00
<code>--end-time date</code>	The time at which the reported instance health state ended. The date uses the format: yyyy-MM-dd'T'HH:mm:ss Type: DateTime Required: No Example: 2011-07-25T14:00:00
<code>--description description</code>	Descriptive text about the instance health state. Type: String Default: None Required: No

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.

Option	Description
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The request ID
- A Boolean return value that indicates whether Amazon EC2 accepted the values.

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example reports the current state of the instance as impaired.

```
PROMPT> ec2-report-instance-status i-15a4417c --status="impaired" --reason="unresponsive"
```


Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ReportInstanceStatus](#)

Related Commands

- [ec2-describe-instance-status](#) (p. 313)

ec2-request-spot-instances

Description

Creates a Spot Instance request. Spot Instances are instances that Amazon EC2 starts on your behalf when the maximum price that you specify exceeds the current Spot Price. Amazon EC2 periodically sets the Spot Price based on available Spot Instance capacity and current Spot Instance requests. For more information about Spot Instances, see [Spot Instances](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2rsi**.

Syntax

```
ec2-request-spot-instances ami_id --addressing addressing_type --price price
[--instance-count count] [--type type] [--valid-from timestamp] [--valid-until
timestamp] [--launch-group group] [--availability-zone-group group] [--user-data
data | --user-data-file data-file] [--group group [--group group ...]] [--key
key-pair] [--instance-type type] [--subnet subnet_id] [--availability-zone zone]
[--kernel kernel] [--ramdisk ramdisk] [--block-device-mapping mapping]
[--monitor] [--iam-profile arn | name] [--network-interface NETWORKINTERFACE]
[--secondary-private-ip-address IP_ADDRESS] |
[--secondary-private-ip-address-count COUNT]] [--ebs-optimized Boolean]
```

Options

Name	Description
<i>ami_id</i>	The ID of the AMI. Type: String Default: None Required: Yes Example: ami-2bb65342
-p, --price <i>price</i>	The maximum hourly price for any Spot Instance launched to fulfill the request. Type: String Default: None Required: Yes Example: -p .15
-n, --instance-count <i>count</i>	The maximum number of Spot Instances to launch. Type: xs:integer Default: 1 Required: No Example: -n 10

Amazon Elastic Compute Cloud CLI Reference
Options

Name	Description
<code>-r, --type type</code>	The Spot Instance request type. Type: String Valid values: <code>one-time</code> <code>persistent</code> Default: <code>one-time</code> Required: No Example: <code>-r persistent</code>
<code>-s, --subnet subnet_id</code>	The ID of the subnet in which to launch the Spot Instance. Type: String Default: None Required: No Example: <code>-s subnet-baab943d3</code>
<code>--valid-from date</code>	The start date of the request. If this is a one-time request, the request becomes active at this date and time and remains active until all instances launch, the request expires, or the request is canceled. If the request is persistent, the request becomes active at this date and time and remains active until it expires or is canceled. Type: DateTime Default: Request is effective indefinitely. Required: No Example: <code>--valid-from 2009-12-31T11:51:50</code>
<code>--valid-until date</code>	The end date of the request. If this is a one-time request, the request remains active until all instances launch, the request is canceled, or this date is reached. If the request is persistent, it remains active until it is canceled or this date and time is reached. Type: DateTime Default: Request is effective indefinitely. Required: No Example: <code>--valid-until 2009-12-31T11:51:50</code>
<code>--launch-group group</code>	The instance launch group. Launch groups are Spot Instances that launch together and terminate together. Type: String Default: Instances are launched and terminated individually. Required: No Example: <code>--launch-group Skynet</code>

Name	Description
<p><code>--availability-zone-group group</code></p>	<p>The user-specified name for a logical grouping of bids.</p> <p>When you specify <code>--availability-zone-group</code> in a Spot Instance request, all Spot Instances in the request are launched in the same Availability Zone. Instance proximity is maintained with this parameter, but choice of Availability Zone is not. <code>--availability-zone-group</code> applies only to bids for Spot Instances of the same instance type. Any additional Spot Instance requests that are specified with the same <code>--availability-zone-group</code> name will be launched in that same Availability Zone, as long as at least one instance from the group is still active.</p> <p>If there is no active instance running in the Availability Zone group that you specify for a new Spot Instance request (for example, all instances are terminated, the bid is expired, or the bid falls below current market), then Amazon EC2 will launch the instance in any Availability Zone where the constraint can be met. Consequently, the subsequent set of Spot Instances could be placed in a different zone from the original request, even if the same <code>--availability-zone-group</code> name was specified.</p> <p>To ensure that all Spot Instances across all bids are launched into a particular Availability Zone, specify <code>LaunchSpecification.Placement.AvailabilityZone</code> in the API or <code>--availability-zone</code> in the CLI.</p> <p>Type: String Default: Instances are launched in any available Availability Zone. Required: No Example: <code>--availability-zone-group batchGroup01</code></p>
<p><code>--placement-group group_name</code></p>	<p>The name of an existing placement group you want to launch the instance into (for cluster instances).</p> <p>Type: String Default: Instances are launched in the default placement group. Required: No Example: <code>--placement-group default</code></p>
<p><code>-d, --user-data user_data</code></p>	<p>The user data to make available to the instances.</p> <p>Type: String Default: None Required: No Example: <code>-d "My user data"</code></p>
<p><code>-g, --group group</code></p>	<p>The ID of the security group.</p> <p>Type: String Default: User's default group. Required: No Example: <code>-g MySecurityGroupID</code></p>

Name	Description
<code>-k, --key key_name</code>	The name of the key pair. Type: String Default: None Required: No Example: <code>-k gsg-keypair</code>
<code>-t, --instance-type instance_type</code>	The instance type. Type: String Valid values: <code>t1.micro m1.small m1.medium m1.large m1.xlarge m3.xlarge m3.2xlarge c1.medium c1.xlarge m2.xlarge m2.2xlarge m2.4xlarge cr1.8xlarge cc1.4xlarge cc2.8xlarge cg1.4xlarge</code> . See Available Instance Types for more information. Default: <code>m1.small</code> Required: No Example: <code>-t m1.large</code>
<code>-z, --availability-zone zone</code>	The placement constraint (for example, a specific Availability Zone) for launching the instances. Specify whether you want all of the Spot Instances in all of your bids to be launched in a particular Availability Zone. Specifying this option requires Amazon EC2 to find capacity in the specified Availability Zone instead of letting Amazon EC2 pick the best Availability Zone available; this can potentially delay the fulfillment of your bid, and/or require a higher bid price. Type: String Default: Amazon EC2 selects an Availability Zone in the current region. Required: No Example: <code>-z us-east-1b</code>
<code>--kernel kernel</code>	The ID of the kernel to select. Type: String Default: None Required: No Example: <code>--kernel aki-ba3adfd3</code>
<code>--ramdisk ramdisk</code>	The ID of the RAM disk to select. Important We recommend that you use PV-GRUB instead of kernels and RAM disks. For more information, see PV-GRUB: A New Amazon Kernel Image in the <i>Amazon Elastic Compute Cloud User Guide</i> . Type: String Default: None Required: No Example: <code>--ramdisk ari-badbad00</code>

Name	Description
<p><code>-b, --block-device-mapping mapping</code></p>	<p>The block device mapping for the instance. This argument is passed in the form of <code><devicename>=<blockdevice></code>. The <i>devicename</i> is the name of the device within Amazon EC2. The <i>blockdevice</i> can be one of the following values:</p> <ul style="list-style-type: none"> • <code>none</code> - Suppresses an existing mapping of the device from the AMI used to launch the instance. For example: <code>"/dev/sdc=none"</code>. • <code>ephemeral[0..3]</code> - An instance store volume to be mapped to the device. For example: <code>"/dev/sdc=ephemeral0"</code>. • <code>[snapshot-id]:[volume-size]:[true false]:[standard io1[:iops]]</code> - An EBS volume to be mapped to the device. <i>[snapshot-id]</i> To create a volume from a snapshot, specify the snapshot ID. <i>[volume-size]</i> To create an empty EBS volume, omit the snapshot ID and specify a volume size instead. For example: <code>"/dev/sdh=:20"</code>. <i>[delete-on-termination]</i> To prevent the volume from being deleted on termination of the instance, specify <code>false</code>. The default is <code>true</code>. <i>[volume-type]</i> To create a Provisioned IOPS volume, specify <code>io1</code>. The default volume type is <code>standard</code>. If the volume type is <code>io1</code>, you can also provision the number of IOPS that the volume supports. For example, <code>"/dev/sdh=snap-7eb96d16::false:io1:500"</code>. <p>You can specify multiple <i>block-device-mapping</i> arguments in one call.</p> <p>For more detailed information about block device mapping, see Block Device Mapping in the <i>Amazon Elastic Compute Cloud User Guide</i>.</p> <p>Type: String Default: None Required: No Example: <code>-b "/dev/sdb=snap-92d333fb::false"</code></p> <p>Note On Windows, the <i>mapping</i> argument must be enclosed in double quotes, as shown in the example.</p>
<p><code>--monitor</code></p>	<p>Enables monitoring for the instance.</p> <p>Type: String Default: Disabled Required: No Example: <code>--monitor</code></p>

Name	Description
<p><code>--iam-profile <i>arn/name</i></code></p>	<p>The IAM instance profile to associate with the launched instances. IAM instance profiles enable you to manage permissions for applications running on EC2. This is either the Amazon Resource Name (ARN) of the instance profile (for example, <code>arn:aws:iam::111111111111:instance-profile/s3access</code>) or the name of the role (for example, <code>s3access</code>).</p> <p>Type: String Default: None Required: No Example: <code>arn:aws:iam::111111111111:instance-profile/s3access</code></p>
<p><code>-a, --network-interface <i>NETWORKINTERFACE</i></code></p>	<p>[EC2-VPC] The network attachment for the launched instance. The format of the <code>NETWORKINTERFACE</code> definition is as follows:</p> <p>For an existing <code>NETWORKINTERFACE</code> - <code>eni :dev index</code></p> <p>For a new <code>NETWORKINTERFACE</code> - <code>dev index : subnet [: description [":<priv IP>":<SGs>[:<DOT>[:SIP count[:<SIPs>]]]]]]]</code>, where <code>SGs</code> is a comma separated list of security group IDs, <code>DOT</code> is either true or false, denoting whether to delete the interface on terminate, <code>SIP count</code> is the number of secondary IP addresses to assign, <code>SIPs</code> is a list of secondary IP addresses. You cannot specify both <code>SIP count</code> and <code>SIPs</code>.</p> <p>Type: String Default: None Required: No</p>

Name	Description
<code>--secondary-private-ip-address</code> <i>IP_ADDRESS</i>	<p>Assigns the specified IP address as a secondary private IP address to the network interface or instance. This option can be used multiple times to assign multiple secondary IP addresses. This option is only available for instances running in a VPC. You cannot specify this parameter when also specifying <code>--secondary-private-ip-address-count</code>.</p> <p>You can do one of the following:</p> <ul style="list-style-type: none"> • Use the <code>--secondary-private-ip-address</code> option without a value and AWS will automatically assign a secondary private IP address within the subnet range. • Use the <code>--secondary-private-ip-address</code> option and provide a specific IP address that you want to assign. <p>Note On Windows clients, you must enclose IP addresses in quotes.</p> <p>Type: String Default: None Required: No Example: <code>--secondary-private-ip-address "10.0.2.18" --secondary-private-ip-address "10.0.2.28"</code></p>
<code>--secondary-private-ip-address-count</code> <i>COUNT</i>	<p>The number of secondary IP addresses to assign to the network interface or instance. You cannot specify this parameter when also specifying <code>--secondary-private-ip-address</code>. This option is only available for instances running in a VPC.</p> <p>Type: Integer Default: None Required: No Example: <code>--secondary-private-ip-address-count 2</code></p>
<code>--ebs-optimized</code> <i>Boolean</i>	<p>Whether the instance is optimized for EBS I/O. This optimization provides dedicated throughput to Amazon EBS and an optimized configuration stack to provide optimal EBS I/O performance. This option isn't available on all instance types. Additional usage charge apply when using this option.</p> <p>Type: Boolean Default: <code>false</code> Required: No Example: <code>--ebs-optimized true</code></p>

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.

Option	Description
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information for each Spot Instance request:

The Spot Instance request information

- The SPOTINSTANCEREQUEST identifier
- The ID of the Spot Instance request
- The Spot Instance bid price
- The Spot Instance type (*one-time or persistent*)
- The product description (*Linux/UNIX or Windows*)
- The state of the Spot Instance request (*active, open, closed, cancelled, failed*)
- The date and time the request was created
- The date and time that the request is valid until
- The date and time the request will be held until
- The launch group
- The Availability Zone group
- The instance ID
- The image ID

- The instance type
- The key pair name
- Any security groups the request belongs to
- The Availability Zone the instance belongs to
- The kernel ID of the instance
- The RAM disk ID of the instance
- The monitoring status
- The subnet ID
- The Availability Zone the instance was launched to
- The IAM profile

Any Spot Instance faults

- The SPOTINSTANCEFAULT identifier
- The Spot Instance fault code
- The Spot Instance fault message

The Spot Instance status information

- The SPOTINSTANCESTATUS identifier
- The Spot Instance status
- The date and time of the last update
- The Spot Instance status message

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example creates a Spot Instances request for three `m1.small` instances.

```
PROMPT> ec2-request-spot-instances ami-1a2b3c4d -p 0.04 --key gsg-keypair --  
group default --instance-type m1.small -n 3 --type one-time  
SPOTINSTANCEREQUEST sir-1a2b3c4d 0.040000 one-time Linux/UNIX open YYYY-MM-  
DDTHH:MM:SS-0800      ami-1a2b3c4d m1.small gsg-keypair sg-1a2b3c4d  monitor  
ing-disabled  
SPOTINSTANCESTATUS pending-evaluation YYYY-MM-DDTHH:MM:SS-0800 Your Spot request  
has been submitted for review, and is pending evaluation.  
SPOTINSTANCEREQUEST sir-2a2b3c4d 0.040000 one-time Linux/UNIX open YYYY-MM-  
DDTHH:MM:SS-0800      ami-1a2b3c4d m1.small gsg-keypair sg-1a2b3c4d  monitor  
ing-disabled  
SPOTINSTANCESTATUS pending-evaluation YYYY-MM-DDTHH:MM:SS-0800 Your Spot request  
has been submitted for review, and is pending evaluation.  
SPOTINSTANCEREQUEST sir-3a2b3c4d 0.040000 one-time Linux/UNIX open YYYY-MM-  
DDTHH:MM:SS-0800      ami-1a2b3c4d m1.small gsg-keypair sg-1a2b3c4d  monitor  
ing-disabled  
SPOTINSTANCESTATUS pending-evaluation YYYY-MM-DDTHH:MM:SS-0800 Your Spot request  
has been submitted for review, and is pending evaluation.
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [RequestSpotInstances](#)

Related Commands

- [ec2-cancel-spot-instance-requests](#) (p. 75)
- [ec2-describe-spot-instance-requests](#) (p. 404)
- [ec2-describe-spot-price-history](#) (p. 412)

ec2-reset-image-attribute

Description

Resets an attribute of an AMI to its default value.

Note

The productCodes attribute cannot be reset.

The short version of this command is **ec2rimatt**.

Syntax

`ec2-reset-image-attribute` *ami_id* [-l]

Options

Name	Description
<i>ami_id</i>	The ID of the AMI. Type: String Default: None Required: Yes Example: ami-15a4417c
-l, --launch-permission	Resets the launch permissions of the AMI. Type: String Default: None Required: No Example: -l

Common Options

Option	Description
--region <i>REGION</i>	Overrides the region specified by the EC2_URL environment variable and the URL specified by the -U option. Default: The value of the EC2_URL environment variable, or us-east-1 if EC2_URL isn't set. Example: --region eu-west-1
-U, --url <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the EC2_URL environment variable, or https://ec2.amazonaws.com if EC2_URL isn't set. Example: -U https://ec2.amazonaws.com

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The attribute type identifier
- The ID of the AMI
- The action identifier (`RESET`)

Amazon EC2 command line tools display errors on `stderr`.

Examples

Example Request

This example resets the `launchPermission` attribute.

```
PROMPT> ec2-reset-image-attribute ami-1a2b3c4d -l  
launchPermission ami-1a2b3c4d RESET
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ResetImageAttribute](#)

Related Commands

- [ec2-describe-image-attribute](#) (p. 295)
- [ec2-modify-image-attribute](#) (p. 530)

ec2-reset-instance-attribute

Description

Resets an attribute of an instance to its default value. To reset the kernel or RAM disk, the instance must be in a stopped state. To reset the `SourceDestCheck`, the instance can be either running or stopped.

The `SourceDestCheck` attribute exists to enable an instance in a VPC to perform NAT. The attribute controls whether source/destination checking is enabled on the instance. The default value is `true`, which means checking is enabled. The value must be `false` for the instance to perform NAT. For more information, see [NAT Instances](#) in the *Amazon Virtual Private Cloud User Guide*.

The short version of this command is `ec2rinatt`.

Syntax

```
ec2-reset-instance-attribute instance_id { --kernel kernel_id | --ramdisk  
ramdisk_id | --source-dest-check }
```

Options

Name	Description
<i>instance_id</i>	The ID of the instance. Type: String Default: None Required: Yes Example: i-43a4412a
--kernel	Resets the ID of the kernel. Type: String Default: None Required: No Example: --kernel
--ramdisk	Resets the ID of the RAM disk. Type: String Default: None Required: No Example: --ramdisk
--source-dest-check	Resets the <code>SourceDestCheck</code> flag to <code>true</code> (which means source/destination checking is enabled). Type: String Default: None Required: No Example: --source-dest-check

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.

Option	Description
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The attribute type identifier
- The ID of the instance
- The action identifier ("RESET")

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example resets the `kernel` attribute.

```
PROMPT> ec2-reset-instance-attribute i-10a64379 --kernel
kernel i-10a64379 RESET
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ResetInstanceAttribute](#)

Related Commands

- [ec2-describe-instance-attribute](#) (p. 308)
- [ec2-modify-instance-attribute](#) (p. 535)

ec2-reset-network-interface-attribute

Description

Resets a network interface attribute. You can specify only one attribute at a time.

The short version of this command is **ec2rnicatt**.

Syntax

```
ec2-reset-network-interface-attribute interface_id --source-dest-check boolean
```

Options

Name	Description
<i>interface_id</i>	The ID of the network interface. Type: String Default: None Required: Yes Example: -n eni-b35da6da
<code>--source-dest-check</code> <i>boolean</i>	Resets the source/dest check to the default value. Type: String Default: True Valid values: true false Required: Yes Example: --source-dest-check

Common Options

Option	Description
<code>--region</code> <i>REGION</i>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: --region eu-west-1
<code>-U</code> , <code>--url</code> <i>URL</i>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: -U https://ec2.amazonaws.com

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns the name of the network interface that was reset.

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example resets network interface attributes for the specified network interface.

```
PROMPT> ec2-reset-network-interface-attribute eni-b35da6da --source-dest-check  
sourceDestCheck eni-b35da6da RESET
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ResetNetworkInterfaceAttribute](#)

Related Commands

- [ec2-attach-network-interface](#) (p. 37)
- [ec2-create-network-interface](#) (p. 126)
- [ec2-delete-network-interface](#) (p. 209)
- [ec2-describe-network-interface-attribute](#) (p. 348)
- [ec2-describe-network-interfaces](#) (p. 352)
- [ec2-detach-network-interface](#) (p. 467)
- [ec2-modify-network-interface-attribute](#) (p. 541)

ec2-reset-snapshot-attribute

Description

Resets permission settings for the specified snapshot.

The short version of this command is **ec2rsnapatt**.

Syntax

```
ec2-reset-snapshot-attribute snapshot_id -c
```

Options

Name	Description
<code>--snapshot <i>snapshot</i></code>	The ID of the snapshot. Type: String Default: None Required: Yes Example: snap-1a2b3c4d
<code>-c, --create-volume-permission</code>	Resets the create volume permissions of the snapshot. Type: String Default: None Required: Yes Example: -c

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url <i>URL</i></code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The `createVolumePermission` identifier
- The ID of the snapshot
- The action identifier (`RESET`)

Amazon EC2 command line tools display errors on `stderr`.

Examples

Example Request

This example resets the permissions for `snap-1a2b3c4d`, making it a private snapshot that can only be used by the account that created it.

```
PROMPT> ec2-reset-snapshot-attribute snap-1a2b3c4d -c  
createVolumePermission snap-1a2b3c4d RESET
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [ResetSnapshotAttribute](#)

Related Commands

- [ec2-modify-snapshot-attribute](#) (p. 545)
- [ec2-describe-snapshot-attribute](#) (p. 391)

- [ec2-describe-snapshots](#) (p. 395)
- [ec2-create-snapshot](#) (p. 146)

ec2-resume-import

Description

Resumes the upload of a disk image associated with an import instance or import volume task ID. Amazon EC2 supports import of VMDK, RAW, and VHD disk images.

If the upload task stops without completing, use this command to resume this upload. The upload task will resume from where it left off. For more information, see [Using the Command Line Tools to Import Your Virtual Machine to Amazon EC2](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2rim**.

Syntax

```
ec2-resume-import -t task_id -o owner -w secret_key [-x days] [--user-threads threads] [--part-size partsize] [--dry-run] [--dont-verify-format] disk_image_filename
```

Options

Name	Description
<i>disk_image_filename</i>	The local file name of the disk image. Type: String Default: None Required: Yes Example: WinSvr8-32-disk1.vmdk
-t, --task <i>task_id</i>	The conversion task ID for the upload. Type: String Default: None Required: Yes Example: -t import-i-ffvko9js
-o, --owner-akid <i>access_key_id</i>	The access key ID of the bucket owner. Type: String Default: None Required: Yes Example: AKIAIOSFODNN7EXAMPLE
-w, --owner-sak <i>secret_access_key</i>	The secret access key of the bucket owner. Type: String Default: None Required: Yes Example: wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY

Name	Description
<code>-x, --expires <i>days</i></code>	The validity period for the signed Amazon S3 URLs that allow Amazon EC2 to access your file. Type: String Default: 30 days Required: No Example: <code>-x 10</code>
<code>--user-threads <i>threads</i></code>	The maximum number of threads to concurrently upload the file with. Type: String Default: 20 Required: No Example: <code>--user-threads 15</code>
<code>--part-size <i>partsize</i></code>	The size of each individual file part (in MB) that will be uploaded. The file will be split into multiple parts at most as large as the <i>partsize</i> parameter. Type: String Default: 8 Required: No Example: <code>--part-size 3</code>
<code>--dry-run</code>	Does not upload the file, only validates that the disk image matches a known type. Type: None Default: None Required: No Example: <code>--dry-run</code>
<code>--dont-verify-format</code>	Does not verify the file format. We don't recommend this option because it can result in a failed conversion. Type: None Default: None Required: No Example: <code>--dont-verify-format</code>

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns the following information:

- The disk image size and format
- The converted volume size
- The EBS volume size
- The percentage of the upload completed

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example uploads the corresponding disk image of the Windows Server 2008 (32-bit) VM you want to migrate.

```
PROMPT>ec2-resume-import ./WinSvr8-32-disk1.vmdk -t import-i-ffvko9js -o AKI
AIOFODNN7EXAMPLE -w wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Commands

- [ec2-cancel-conversion-task](#) (p. 64)

- [ec2-delete-disk-image](#) (p. 189)
- [ec2-describe-conversion-tasks](#) (p. 272)
- [ec2-import-instance](#) (p. 507)
- [ec2-import-volume](#) (p. 518)

ec2-revoke

Description

Removes a rule from a security group.

A security group is for use with instances either in the EC2-Classic platform or in a specific VPC. For more information, see [Amazon EC2 Security Groups](#) in the *Amazon Elastic Compute Cloud User Guide* and [Security Groups for Your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

The values that you specify in the revoke request (ports, and so on) must match the existing rule's values in order for the rule to be removed.

Each rule consists of the protocol (for example, TCP), plus either a CIDR range, or a source group (for ingress rules) or destination group (for egress rules). For TCP and UDP, you must also specify the destination port or port ranges. You can specify -1 to mean all ports (for example, port range 0-65535). For ICMP, you must also specify the ICMP type and code. You can use -1 for the type or code to mean all types or all codes.

Rule changes are propagated to affected instances as quickly as possible. However, a small delay might occur.

The short version of this command is **ec2revoke**.

Syntax

```
ec2-revoke group [--egress] [-P protocol] (-p port_range | -t icmp_type_code)
[-u source_or_dest_group_owner ...] [-o source_or_dest_group ...] [-s
source_or_dest_cidr ...]
```

Options

Name	Description
<i>group</i>	<p>EC2-Classic, default VPC: The name or ID of the security group.</p> <p>nondefault VPC: The ID of the security group.</p> <p>The group must belong to your AWS account. Type: String Default: None Required: Yes Example: webserv (name), sg-1a2b3c4d (ID)</p>
--egress	<p>[EC2-VPC] Indicates that the rule is an egress rule (applies to traffic leaving the VPC).</p> <p>Default: If this option is not specified, the rule is an ingress rule (applies to traffic entering the VPC)</p> <p>Required: No</p>

Name	Description
<p><code>-P, --protocol protocol</code></p>	<p>The name or number of the IP protocol to revoke (see Protocol Numbers). Security groups for EC2-Classic can have rules only for TCP, UDP, and ICMP, whereas security groups for EC2-VPC can have rules assigned to any protocol number.</p> <p>When you call <code>ec2-describe-group</code>, the protocol value returned is the number. Exception: For TCP, UDP, and ICMP, the value returned is the name (<code>tcp</code>, <code>udp</code>, or <code>icmp</code>).</p> <p>Type: String</p> <p>Valid values for EC2-Classic: <code>tcp</code> <code>udp</code> <code>icmp</code> or the corresponding protocol number (6 17 1).</p> <p>Default for EC2-Classic: TCP if the source CIDR is specified (or implied by default), or all three protocols (TCP, UDP, and ICMP) if the source group is specified (to ensure backwards compatibility).</p> <p>Valid values for EC2-VPC: <code>tcp</code> <code>udp</code> <code>icmp</code> or any protocol number. Use <code>all</code> to specify all protocols.</p> <p>Required: Conditional</p> <p>Condition: Required for EC2-VPC.</p> <p>Example: <code>-P udp</code></p>
<p><code>-p port_range</code></p>	<p>For TCP or UDP: The range of ports to revoke.</p> <p>Type: String</p> <p>Default: None</p> <p>Valid values: A single integer or a range (min-max). You can specify -1 to mean all ports (for example, port range 0-65535).</p> <p>Required: Conditional</p> <p>Condition: Required if specifying <code>tcp</code> or <code>udp</code> (or the equivalent number) for the protocol.</p> <p>Example: <code>-p 80-84</code></p>
<p><code>-t icmp_type_code</code></p>	<p>For ICMP: The ICMP type and code to revoke. This must be specified in the format <code>type:code</code> where both are integers. You can use -1 for the type or code to mean all types or all codes.</p> <p>Type: String</p> <p>Default: None</p> <p>Required: Conditional</p> <p>Condition: Required if specifying <code>icmp</code> (or the equivalent number) for the protocol.</p> <p>Example: <code>-t -1:-1</code></p>

Name	Description
<code>-u, source_or_dest_group_owner</code>	The ID of the AWS account that owns the source security group (for ingress rules) or destination security group (for egress rules). If the group is in your own account, set this to your own AWS account ID. Cannot be used when specifying a CIDR IP address. Type: String Default: None Required: Conditional Condition: Required when revoking a rule that gives access to one or more source security groups. Example: <code>-u 111122223333</code>
<code>-o source_or_dest_group</code>	The source security group (for ingress rules), or destination security group (for egress rules). When revoking a rule for a security group for EC-VPC, you must specify the group's ID (for example, <code>sg-9d4e5f6g</code>) instead of its name. Cannot be used when specifying a CIDR IP address with the <code>-s</code> option. Type: String Default: None Required: Conditional Condition: Required if revoking access to one or more source or destination security groups. Example: <code>-o headoffice</code>
<code>-s, --cidr source_or_dest_cidr</code>	The CIDR range. Cannot be used when specifying a source or destination security group with the <code>-o</code> option. Type: String Default: <code>0.0.0.0/0</code> Constraints: Valid CIDR IP address range. Required: Conditional Condition: Required if revoking access to one or more IP address ranges. Example: <code>-s 205.192.8.45/24</code>

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
-K, --private-key <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
-C, --cert <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

A line containing the group information. Some of these fields may be blank.

- The GROUP identifier
- The ID of the security group
- The AWS account ID of the owner of the security group
- The name of the security group
- A description of the security group
- [VPC only] The ID of the VPC the group belongs to

One of each of the following lines for each permission defined by the group:

- The PERMISSION identifier
- The AWS account ID of the owner of the group
- The name of the group granting permission
- The type of rule. Currently, only `ALLOWS` rules are supported
- The protocol to allow (for example, `tcp`, `udp`, etc)
- The start of port range
- The end of port range
- `FROM` for an ingress rule or `TO` for an egress rule
- The source type (for ingress rules) or destination type (for egress rules)
- The source (for ingress rules) or destination (for egress rules)
- [USER only] The name of the source or destination entity
- [USER only] The group ID
- Whether the rule is ingress rule or an egress rule

Amazon EC2 command line tools display errors on `stderr`.

Examples

Example Request

This example revokes TCP port 80 access from the 205.192.0.0/16 address range for the `webserv` security group.

```
PROMPT> ec2-revoke webserv -P tcp -p 80 -s 205.192.0.0/16
GROUP    webserv
PERMISSION webserv ALLOWS tcp 80 80 FROM CIDR 205.192.0.0/16 ingress
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [RevokeSecurityGroupEgress](#)
- [RevokeSecurityGroupIngress](#)

Related Commands

- [ec2-authorize](#) (p. 49)
- [ec2-create-group](#) (p. 97)
- [ec2-delete-group](#) (p. 192)
- [ec2-describe-group](#) (p. 289)

ec2-run-instances

Description

Launches a specified number of instances of an AMI for which you have permissions.

If capacity is insufficient to launch the maximum number of instances requested in one Availability Zone (the specified Availability Zone for targeted requests, or an Availability Zone chosen by EC2 for untargeted requests), Amazon EC2 launches the minimum number specified. If Amazon EC2 cannot launch the minimum number of instances requested in a single Availability Zone, no instances are launched.

Note

Every instance is launched in a security group (which you create using the `ec2-create-group` command). If you don't specify a security group at launch time, the default security group is used.

You can provide an optional key pair ID in the launch request (created using the `ec2-create-keypair` or `ec2-import-keypair` command). The instances will have access to the public key at boot. You can use this key to provide secure access to an instance of an image on a per-instance basis. Amazon EC2 public images use this feature to provide secure access without passwords.

The public key material is made available to the Linux instance at boot time by placing it in the `openssh_id.pub` file on a logical device that is exposed to the instance as `/dev/sda2` (the instance store). The format of this file is suitable for use as an entry within `~/.ssh/authorized_keys` (the OpenSSH format). This can be done at boot (for example, as part of `rc.local`) allowing for secure access without passwords.

Important

Launching public images without a key pair ID will leave them inaccessible.

You can provide optional user data in the launch request. All instances that collectively comprise the launch request have access to this data. For more information, see [Instance Metadata](#) in the *Amazon Elastic Compute Cloud User Guide*.

Note

If any of the AMIs have a product code attached for which the user has not subscribed, the `ec2-run-instances` command fails.

The short version of this command is `ec2run`.

Syntax

```
ec2-run-instances ami_id [-n instance_count] [-g group [-g group ...]] [-k keypair] [-d user_data | -f user_data_file] [--addressing addressing_type] [--instance-type instance_type] [--availability-zone zone] [--kernel kernel_id] [--ramdisk ramdisk_id] [--block-device-mapping block_device_mapping] [--monitor] [--disable-api-termination] [--instance-initiated-shutdown-behavior behavior] [--placement-group placement-group] [--tenancy tenancy] [--subnet subnet_id] [--private-ip-address ip_address] [--client-token token] [--network-interface interface_id] [--secondary-private-ip-address ip_address | --secondary-private-ip-address-count count] [-p, --iam-profile arn|name] | --ebs-optimized Boolean
```

Options

Name	Description
<code>ami_id</code>	The ID of the AMI, returned by a call to ec2-describe-images . Type: String Default: None Required: Yes Example: ami-15a4417c
<code>-n , --instance-count min[-max]</code>	The number of instances to launch. If Amazon EC2 cannot launch the specified number of instances, no instances will launch. If this is specified as a range (min-max), Amazon EC2 will try to launch the maximum number, but no fewer than the minimum number. Type: String Default: 1 Constraints: Between 1 and the maximum number allowed for your account (the default for each account is 20, but this limit can be increased). Required: No Example: -n 5-10
<code>-g, --group group</code>	The name of the security group. Type: String Default: None Required: No Example: -g webserv
<code>-k, --key keypair</code>	The name of the key pair. Type: String Default: None Required: No Example: -k webserv-keypair
<code>-d, --user-data user_data</code>	Base64-encoded MIME user data to be made available to the instances in this reservation. Type: String Default: None Required: No Example: -d s3-bucket:my-logs
<code>-f, --user-data-file filename</code>	The file name of the user data to be made available to the instances in this reservation. Type: String Default: None Required: No Example: -f user-data.txt

Name	Description
<p><code>-t, --instance-type <i>instance_type</i></code></p>	<p>The instance type. See Available Instance Types for more information.</p> <p>Type: String</p> <p>Valid values: <code>t1.micro</code> <code>m1.small</code> <code>m1.medium</code> <code>m1.large</code> <code>m1.xlarge</code> <code>m3.xlarge</code> <code>m3.2xlarge</code> <code>c1.medium</code> <code>c1.xlarge</code> <code>m2.xlarge</code> <code>m2.2xlarge</code> <code>m2.4xlarge</code> <code>cr1.8xlarge</code> <code>hi1.4xlarge</code> <code>hs1.8xlarge</code> <code>cc1.4xlarge</code> <code>cc2.8xlarge</code> <code>cg1.4xlarge</code></p> <p>Default: <code>m1.small</code></p> <p>Required: No</p> <p>Example: <code>-t m1.large</code></p>
<p><code>-z, --availability-zone <i>zone</i></code></p>	<p>The Availability Zone in which to run the instance.</p> <p>Type: String</p> <p>Default: None</p> <p>Required: No</p> <p>Example: <code>--availability-zone us-east-1a</code></p>
<p><code>--kernel <i>kernel</i></code></p>	<p>The ID of the kernel with which to launch the instance.</p> <p>Type: String</p> <p>Default: None</p> <p>Required: No</p> <p>Example: <code>--kernel aki-ba3adfd3</code></p>
<p><code>--ramdisk <i>ramdisk</i></code></p>	<p>The ID of the RAM disk to select.</p> <p>Important</p> <p>We recommend that you use PV-GRUB instead of kernels and RAM disks. For more information, see PV-GRUB: A New Amazon Kernel Image in the <i>Amazon Elastic Compute Cloud User Guide</i>.</p> <p>Type: String</p> <p>Default: None</p> <p>Required: No</p> <p>Example: <code>--ramdisk ari-abcdef01</code></p>

Name	Description
<p><code>-b, --block-device-mapping <i>mapping</i></code></p>	<p>The block device mapping for the instance. This argument is passed in the form of <code><devicename>=<blockdevice></code>. The <i>devicename</i> is the device name of the physical device on the instance to map. The <i>blockdevice</i> can be one of the following values:</p> <ul style="list-style-type: none"> • <code>none</code> - Suppresses an existing mapping of the device from the AMI used to launch the instance. For example: <code>"/dev/sdc=none"</code>. • <code>ephemeral[0..3]</code> - An instance store volume to be mapped to the device. For example: <code>"/dev/sdc=ephemeral0"</code>. • <code>[snapshot-id]:[volume-size]:[true false]:[standard io1[:iops]]</code> - An EBS volume to be mapped to the device. <i>[snapshot-id]</i> To create a volume from a snapshot, specify the snapshot ID. <i>[volume-size]</i> To create an empty EBS volume, omit the snapshot ID and specify a volume size instead. For example: <code>"/dev/sdh=:20"</code>. <i>[delete-on-termination]</i> To prevent the volume from being deleted on termination of the instance, specify <code>false</code>. The default is <code>true</code>. <i>[volume-type]</i> To create a Provisioned IOPS volume, specify <code>io1</code>. The default volume type is <code>standard</code>. If the volume type is <code>io1</code>, you can also provision the number of IOPS that the volume supports. For example, <code>"/dev/sdh=snap-7eb96d16::false:io1:500"</code>. <p>You can specify multiple <i>blockdevicemapping</i> parameters in one call.</p> <p>For more detailed information about block device mapping, see Block Device Mapping in the <i>Amazon Elastic Compute Cloud User Guide</i>.</p> <p>Type: String Default: None Required: No Example: <code>-b "/dev/sdb=snap-92d333fb::false"</code></p> <p>Note On Windows, the <i>mapping</i> argument must be enclosed in double quotes, as shown in the example.</p>
<p><code>-m, --monitor</code></p>	<p>Enables monitoring for the instance.</p> <p>Type: Boolean Default: Disabled Required: No Example: <code>--monitor</code></p>

Amazon Elastic Compute Cloud CLI Reference
Options

Name	Description
<code>--disable-api-termination</code>	<p>Whether the instance can be terminated using the EC2 API. A value of <code>true</code> means you can't terminate the instance using the API (the instance is "locked"). A value of <code>false</code> means you can terminate the instance using the API (the instance is "unlocked"). Set this attribute to <code>true</code> to prevent the instance from being terminated using the EC2 API.</p> <p>Type: Boolean Default: <code>false</code> Required: No Example: <code>--disable-api-termination true</code></p>
<code>--instance-initiated-shutdown-behavior</code> <i>behavior</i>	<p>If an instance shutdown is initiated, this determines whether the instance stops or terminates.</p> <p>Type: String Valid values: <code>stop</code> <code>terminate</code> Default: <code>stop</code> Required: No Example: <code>--instance-initiated-shutdown-behavior stop</code></p>
<code>--placement-group</code> <i>placement_group</i>	<p>The name of the placement group.</p> <p>Type: String Valid values: <code>cluster</code> Default: None Required: No Example: <code>--placement-group XYZ-cluster</code></p>
<code>--tenancy</code> <i>tenancy</i>	<p>The tenancy of the instance. An instance with a tenancy of <code>dedicated</code> runs on single-tenant hardware and can only be launched into a VPC.</p> <p>Type: String Valid values: <code>default</code> <code>dedicated</code> Default: <code>default</code> Required: No Example: <code>--tenancy dedicated</code></p>
<code>-s, --subnet</code> <i>subnet_id</i>	<p>[EC2-VPC] The ID of the subnet to launch the instance into.</p> <p>Type: String Default: None Required: No Example: <code>-s subnet-f3e6ab83</code></p>
<code>--private-ip-address</code> <i>ip_address</i>	<p>[EC2-VPC] You can optionally use this parameter to assign the instance a specific available primary private IP address from the subnet.</p> <p>Type: String Default: We select an IP address from the IP address range of the subnet for the instance Required: No Example: <code>--private-ip-address 10.0.0.25</code></p>

Name	Description
<code>--secondary-private-ip-address</code> <i>ip_address</i>	<p>[EC2-VPC] Assigns the specified IP address as a secondary private IP address to the network interface or instance. This option can be used multiple times to assign multiple secondary IP addresses.</p> <p>You can do one of the following:</p> <ul style="list-style-type: none"> • Use the <code>--secondary-private-ip-address</code> option without a value, and AWS will automatically assign a secondary private IP address within the subnet range. • Use the <code>--secondary-private-ip-address</code> option and provide a specific IP address that you want to assign. On Windows clients, you must enclose the IP addresses in quotes. <p>You cannot specify this parameter when also specifying <code>--secondary-private-ip-address-count</code>.</p> <p>Type: String Default: None Required: No Example: <code>--secondary-private-ip-address "10.0.2.18"</code> <code>--secondary-private-ip-address "10.0.2.28"</code></p>
<code>--secondary-private-ip-address-count</code> <i>count</i>	<p>[EC2-VPC] The number of secondary IP addresses to assign to the network interface or instance.</p> <p>You cannot specify this parameter when also specifying <code>--secondary-private-ip-address</code></p> <p>Type: Integer Default: None Required: No Example: <code>--secondary-private-ip-address-count 2</code></p>
<code>--client-token</code> <i>token</i>	<p>Unique, case-sensitive identifier you provide to ensure idempotency of the request. For more information, see How to Ensure Idempotency in the <i>Amazon Elastic Compute Cloud User Guide</i>.</p> <p>Type: String Default: None Constraints: Maximum 64 ASCII characters Required: No Example: <code>--client-token</code> 550e8400-e29b-41d4-a716-446655440000</p>

Name	Description
<p><code>-a, --network-interface interface_id</code></p>	<p>The network attachment for the launched instance. The format is as follows:</p> <p>For an existing network interface - <i>eni:dev index</i></p> <p>For a new network interface - <i>dev index[:subnet[:description[:priv IP[:SGs[:DOT[:SIP count [:SIPs]]]]]]]</i> where SGs is a comma separated list of security group IDs; DOT is either true or false, denoting whether to delete the interface on terminate; SIP count is the number of secondary IP addresses to assign; and SIPs is a list of secondary IP addresses. You cannot specify both SIP count and SIPs.</p> <p>Type: String Default: None Required: No Examples:</p> <ul style="list-style-type: none"> • Launch an instance with a specific interface for index 0 <pre>ec2run ami-0644f007 -a eni-d2b24dbb:0</pre> <ul style="list-style-type: none"> • Launch an instance and specify interfaces for both index 0 and index 1 <pre>ec2run ami-0644f007 -a eni-d2b24dbb:0 -a eni-12345678:1</pre> <ul style="list-style-type: none"> • Launch an instance and autcreate an interface for index 0 with details and a specific interface for index 1 <pre>ec2-run-instances ami-31814f58 -a :0:subnet-15ca247d:"My ENI" -a eni-12345678:1</pre> <ul style="list-style-type: none"> • Launch an instance with a specific interface for index 0 and autcreate an interface for index 1 with specific values <pre>ec2-run-instances ami-31814f58 -a eni-12345678:0 -a :1:subnet-15ca247d:"My ENI":"10.0.0.10":sg-123456,sg-654321:false</pre> <ul style="list-style-type: none"> • Launch an instance with a specific interface for index 0 with specific secondary IP addresses <pre>ec2-run-instances ami-31814f58 -a eni-12345678:0 -a :1:subnet-15ca247d:"My ENI":::::"10.0.0.18,10.0.0.25"</pre>

Name	Description
<code>-p, --iam-profile arn/name</code>	The IAM instance profile to associate with the launched instances. IAM instance profiles enable you to manage permissions for applications running on EC2. This is either the Amazon Resource Name (ARN) of the instance profile (for example, <code>arn:aws:iam::111111111111:instance-profile/s3access</code>) or the name of the role (for example, <code>s3access</code>). Type: String Default: None Required: No Example: <code>arn:aws:iam::111111111111:instance-profile/s3access</code>
<code>--ebs-optimized Boolean</code>	Whether the instance is optimized for EBS I/O. This optimization provides dedicated throughput to Amazon EBS and an optimized configuration stack to provide optimal EBS I/O performance. This option isn't available on all instance types. Additional usage charge apply when using this option. Type: Boolean Default: <code>false</code> Required: No Example: <code>--ebs-optimized true</code>

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key</code> <i>AWS_SECRET_KEY</i>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token</code> TOKEN <i>AWS_DELEGATION_TOKEN</i>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout</code> <i>TIMEOUT</i>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	<p>The X.509 certificate to use when constructing requests to Amazon EC2.</p> <p>Default: The value of the <code>EC2_CERT</code> environment variable.</p> <p>Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code></p>

Output

This command returns a table that contains the following rows of information for each instance. Each field is separated by a comma. Some of these values may be empty.

1. The reservation information
 - The RESERVATION identifier
 - The ID of the reservation
 - The AWS account ID of the instance owner
 - The name of each security group the instance is in
2. The instance information
 - The INSTANCE identifier
 - The ID of the instance
 - The AMI ID of the image on which the instance is based
 - The public DNS name associated with the instance. This is only present for instances in the running state.
 - The private DNS name associated with the instance. This is only present for instances in the running state.
 - The state of the instance
 - The key name. If a key was associated with the instance at launch, its name will appear.
 - The AMI launch index
 - The product codes associated with the instance
 - The instance type
 - The instance launch time
 - The Availability Zone
 - The ID of the kernel
 - The ID of the RAM disk
 - The platform (`windows` or `empty`)
 - The monitoring state
 - The public IP address
 - The private IP address
 - [EC2-VPC] The ID of the VPC
 - [EC2-VPC] The subnet ID
 - The type of root device (`ebs` or `instance-store`)
 - The instance lifecycle
 - The Spot Instance request ID
 - The instance license
 - The placement group the cluster instance is in
 - The virtualization type (`paravirtual` or `hvm`)
 - The hypervisor type (`xen` or `ovm`)

- The client token
 - The ID of each security group the instance is in
 - The tenancy of the instance (`default` or `dedicated`)
 - Whether or not the instance is EBS optimized (`true` or `false`)
 - The [Amazon Resource Name](#) (ARN) of the IAM role
3. [EC2-VPC] The network interface information. There will be a set of the following for each network interface
- a. The network interface information
 - The NIC identifier
 - The network interface ID
 - The subnet ID
 - The VPC ID
 - The owner ID
 - The network interface status
 - The private IP address of the network interface
 - The private DNS name
 - Whether or not source destination check is enabled (`true` or `false`)
 - b. The network interface attachment information
 - The NICATTACHMENT identifier
 - The attachment ID
 - The device index
 - The device status
 - The attachment timestamp
 - Whether or not the attachment is deleted on termination (`true` or `false`)
 - c. The network interface association information
 - The NICASSOCIATION identifier
 - The public IP address
 - The public IP address owner
 - The private IP address
 - d. The security group information
 - The GROUP identifier
 - The security group identifier
 - The security group name
 - e. The private IP address information
 - The PRIVATEIPADDRESS identifier
 - The private IP address

Amazon EC2 command line tools display errors on `stderr`.

Examples

Example Request

This example launches three instances of the `ami-1a2b3c4d` AMI.


```
PROMPT> ec2-run-instances ami-1a2b3c4d -n 3 --availability-zone us-east-1a  
RESERVATION r-1a2b3c4d 111122223333  
INSTANCE i-1a2b3c4d ami-1a2b3c4d pending gsg-keypair 0 m1.small YYYY-MM-  
DDTHH:MM:SS+0000 us-east-1a aki-1a2b3c4d monitoring-disabled ebs  
paravirtual xen sg-1a2b3c4d default false  
INSTANCE i-2a2b3c4d ami-1a2b3c4d pending gsg-keypair 1 m1.small YYYY-MM-  
DDTHH:MM:SS+0000 us-east-1a aki-1a2b3c4d monitoring-disabled ebs  
paravirtual xen sg-1a2b3c4d default false  
INSTANCE i-3a2b3c4d ami-1a2b3c4d pending gsg-keypair 2 m1.small YYYY-MM-  
DDTHH:MM:SS+0000 us-east-1a aki-1a2b3c4d monitoring-disabled ebs  
paravirtual xen sg-1a2b3c4d default false
```

Example Request

This example launches an Amazon EBS-based Windows image (ami-2879f118) and provides a block device mapping that mounts a public snapshot with the snap-1a2b3c4d ID.

```
PROMPT> ec2-run-instances ami-2879f118 -n 1 --b "/dev/sdb=snap-1a2b3c4d::false"  
RESERVATION r-1a2b3c4d 111122223333  
INSTANCE i-1a2b3c4d ami-84db39ed pending gsg-keypair 0 m1.small YYYY-MM-  
DDTHH:MM:SS+0000 us-east-1c windows monitoring-disabled ebs hvm xen  
sg-1a2b3c4d default false
```

Example Request

This example launches an instance with a primary IP address of 10.0.0.146 and two secondary private IP addresses of 10.0.0.148 and of 10.0.0.150 in subnet-1a2b3c4d.

```
PROMPT> ec2-run-instances ami-1a2b3c4d -k gsg-keypair -s subnet-1a2b3c4d -t  
c1.medium --private-ip-address 10.0.0.146 --secondary-private-ip-address  
10.0.0.148 --secondary-private-ip-address 10.0.0.150  
RESERVATION r-1a2b3c4d 111122223333  
INSTANCE i-1a2b3c4d ami-1a2b3c4d pending gsg-keypair 0 c1.medium YYYY-MM-  
DDTHH:MM:SS+0000 us-west-2a windows monitoring-disabled 10.0.0.146 vpc-  
1a2b3c4d subnet-1a2b3c4d ebs hvm xen sg-1a2b3c4d dedicated false  
NIC eni-1a2b3c4d subnet-1a2b3c4d vpc-1a2b3c4d 111122223333 in-use 10.0.1.146  
true  
NICATTACHMENT eni-attach-1a2b3c4d 0 attaching YYYY-MM-DDTHH:MM:SS+0000 true  
GROUP sg-1a2b3c4d default  
PRIVATEIPADDRESS 10.0.0.146  
PRIVATEIPADDRESS 10.0.0.148  
PRIVATEIPADDRESS 10.0.0.150
```

Example Request

This example launches a Dedicated Instance into a VPC.

```
PROMPT> ec2-run-instances ami-1a2b3c4d --tenancy dedicated -s subnet-1a2b3c4d
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [RunInstances](#)

Related Commands

- [ec2-describe-instances](#) (p. 320)
- [ec2-stop-instances](#) (p. 650)
- [ec2-start-instances](#) (p. 646)
- [ec2-terminate-instances](#) (p. 654)
- [ec2-authorize](#) (p. 49)
- [ec2-revoke](#) (p. 627)
- [ec2-create-keypair](#) (p. 114)
- [ec2-create-group](#) (p. 97)
- [ec2-describe-group](#) (p. 289)

ec2-start-instances

Description

Starts an instance that uses an Amazon EBS volume as its root device.

Instances that use Amazon EBS volumes as their root devices can be quickly stopped and started. When an instance is stopped, the compute resources are released and you are not billed for hourly instance usage. However, your root partition Amazon EBS volume remains, continues to persist your data, and you are charged for Amazon EBS volume usage. You can restart your instance at any time. Each time you transition an instance from stopped to started, we charge a full instance hour, even if transitions happen multiple times within a single hour.

Before stopping an instance, make sure it is in a state from which it can be restarted. Stopping an instance does not preserve data stored in RAM.

Performing this operation on an instance that uses an instance store as its root device returns an error.

You cannot start or stop Spot Instances.

For more information, see [Using Amazon EBS-Backed AMIs and Instances](#).

The short version of this command is **ec2start**.

Syntax

```
ec2-start-instances instance_id [instance_id...]
```

Options

Name	Description
<i>instance_id</i>	The instance ID. Type: String Default: None Required: Yes Example: i-43a4412a

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>

**Amazon Elastic Compute Cloud CLI Reference
Common Options**

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- INSTANCE identifier
- Instance ID
- The previous state of the instance
- The new state of the instance

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example starts the i-10a64379 instance.

```
PROMPT> ec2-start-instances i-10a64379  
INSTANCE i-10a64379 stopped pending
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [StartInstances](#)

Related Commands

- [ec2-describe-instances](#) (p. 320)
- [ec2-run-instances](#) (p. 633)
- [ec2-stop-instances](#) (p. 650)
- [ec2-terminate-instances](#) (p. 654)

ec2-stop-instances

Description

Stops an instance that uses an Amazon EBS volume as its root device. Each time you transition an instance from stopped to started, we charge a full instance hour, even if transitions happen multiple times within a single hour.

Important

Although Spot Instances can use Amazon EBS-backed AMIs, they don't support Stop/Start. In other words, you can't stop and start Spot Instances launched from an AMI with an Amazon EBS root device.

Instances that use Amazon EBS volumes as their root devices can be quickly stopped and started. When an instance is stopped, the compute resources are released and you are not billed for hourly instance usage. However, your root partition Amazon EBS volume remains, continues to persist your data, and you are charged for Amazon EBS volume usage. You can restart your instance at any time.

Before stopping an instance, make sure it is in a state from which it can be restarted. Stopping an instance does not preserve data stored in RAM.

Performing this operation on an instance that uses an instance store as its root device returns an error.

You can stop, start, and terminate EBS-backed instances. You can only terminate S3-backed instances. What happens to an instance differs if you stop it or terminate it. For example, when you stop an instance, the root device and any other devices attached to the instance persist. When you terminate an instance, the root device and any other devices attached during the instance launch are automatically deleted. For more information about the differences between stopping and terminating instances, see [Stopping Instances](#) in the *Amazon Elastic Compute Cloud User Guide*

The short version of this command is **ec2stop**.

Syntax

```
ec2-stop-instances instance_id [instance_id...] [--force]
```

Options

Name	Description
<i>instance_id</i>	The ID of the instance. Type: String Default: None Required: Yes Example: i-43a4412a

Name	Description
<code>-f, --force</code>	<p>Forces the instance to stop. The instance will not have an opportunity to flush file system caches or file system metadata. If you use this option, you must perform file system check and repair procedures. This option is not recommended for Windows instances.</p> <p>Type: Boolean Default: None Required: No Example: None</p>

Common Options

Option	Description
<code>--region REGION</code>	<p>Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option.</p> <p>Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set.</p> <p>Example: <code>--region eu-west-1</code></p>
<code>-U, --url URL</code>	<p>The uniform resource locator (URL) of the Amazon EC2 web service entry point.</p> <p>Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set.</p> <p>Example: <code>-U https://ec2.amazonaws.com</code></p>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>

Option	Description
<code>--request-timeout</code> <i>TIMEOUT</i>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The INSTANCE identifier
- The ID of the instance
- The previous state of the instance
- The new state of the instance

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example stops the i-10a64379 instance.

```
PROMPT> ec2-stop-instances i-10a64379  
INSTANCE i-10a64379 running stopping
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [StopInstances](#)

Related Commands

- [ec2-describe-instances](#) (p. 320)
- [ec2-run-instances](#) (p. 633)
- [ec2-start-instances](#) (p. 646)
- [ec2-terminate-instances](#) (p. 654)

ec2-terminate-instances

Description

Shuts down one or more instances. This operation is idempotent; if you terminate an instance more than once, each call succeeds.

Terminated instances will remain visible after termination (approximately one hour).

Note

By default, Amazon EC2 deletes all Amazon EBS volumes that were attached when the instance launched. Amazon EBS volumes attached after instance launch persist.

You can stop, start, and terminate EBS-backed instances. You can only terminate S3-backed instances. What happens to an instance differs if you stop it or terminate it. For example, when you stop an instance, the root device and any other devices attached to the instance persist. When you terminate an instance, the root device and any other devices attached during the instance launch are automatically deleted. For more information about the differences between stopping and terminating instances, see [Stopping Instances](#) in the *Amazon Elastic Compute Cloud User Guide*

The short version of this command is **ec2kill**.

Syntax

`ec2-terminate-instances instance_id [instance_id ...]`

Options

Name	Description
<i>instance_id</i>	The IDs of instances to terminate. Type: String Default: None Required: Yes Example: i-43a4412a

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url <i>URL</i></code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The INSTANCE identifier
- The instance ID of the instance being terminated
- The state of the instance prior to being terminated
- The new state of the instance

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example terminates the `i-1a2b3c4d` instance.

```
PROMPT> ec2-terminate-instances i-1a2b3c4d  
INSTANCE i-1a2b3c4d running shutting-down
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [TerminateInstances](#)

Related Commands

- [ec2-describe-instances](#) (p. 320)
- [ec2-run-instances](#) (p. 633)

ec2-unassign-private-ip-addresses

Description

Unassigns one or more secondary private IP addresses from a network interface. This command is only available in EC2-VPC.

The short version of this command is **ec2upip**.

Syntax

```
ec2-unassign-private-addresses --network-interface interface_id
--secondary-private-ip-address ip_address [--secondary-private-ip-address
ip_address ...]
```

Options

Name	Description
<code>--n, --network-interface <i>interface_id</i></code>	The network interface from which the secondary private IP address will be unassigned. Type: String Default: None Required: Yes Example: <code>-n eni-bc7299d4</code>
<code>--secondary-private-ip-address <i>ip_address</i></code>	The secondary private IP addresses that you want to unassign from the network interface. You can specify this option multiple times to unassign more than IP address. Type: String Default: None Required: Yes Example: <code>--secondary-private-ip-address 10.0.2.18</code> <code>--secondary-private-ip-address 10.0.2.28</code>

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url <i>URL</i></code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Amazon Elastic Compute Cloud CLI Reference Common Options

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`)

and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

The command returns a true value if the operation succeeds or an error if the operation fails.

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example unassigns the private IP addresses 10.0.0.118 and 10.0.0.119 from the network interface specified.

```
PROMPT> ec2-unassign-private-ip-addresses --network-interface eni-c08a35a9 -  
-secondary-private-ip-address 10.0.0.118 --secondary-private-ip-address  
10.0.0.119  
RETURN true
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [UnassignPrivateIpAddresses](#)

Related Commands

- [ec2-assign-private-ip-addresses](#) (p. 16)

ec2-unmonitor-instances

Description

Disables monitoring for a running instance. For more information, see [Monitoring Your Instances and Volumes](#) in the *Amazon Elastic Compute Cloud User Guide*.

The short version of this command is **ec2umin**.

Syntax

`ec2-unmonitor-instances instance_id [instance_id...]`

Options

Name	Description
<i>instance_id</i>	The ID of the instance. Type: String Default: None Required: Yes Example: i-43a4412a

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url <i>URL</i></code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key <i>AWS_ACCESS_KEY</i></code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns a table that contains the following information:

- The ID of the instance.
- The monitoring state

Amazon EC2 command line tools display errors on stderr.

Examples

Example Request

This example disables monitoring for `i-43a4412a` and `i-23a3397d`.

```
PROMPT> ec2-unmonitor-instances i-43a4412a i-23a3397d
i-43a4412a monitoring-disabling
i-23a3397d monitoring-disabling
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Action

- [UnmonitorInstances](#)

Related Commands

- [ec2-monitor-instances](#) (p. 556)
- [ec2-run-instances](#) (p. 633)

ec2-upload-disk-image

Description

Deprecated. Instead, use the `ec2-import-instance` and `ec2-import-volume` commands (included in the command line tools as of 2011-09-15) to create the import task and upload the image to Amazon EC2. For more information, see [Using the Command Line Tools to Import Your Virtual Machine to Amazon EC2](#) in the *Amazon Elastic Compute Cloud User Guide*.

Uploads the disk image associated with an import instance or an import volume task ID. Amazon EC2 supports import of VMDK, RAW, and VHD disk images.

If the upload task doesn't complete, use `ec2-resume-import` to resume the import from where it was interrupted.

The short version of this command is **ec2udi**.

Syntax

```
ec2-upload-disk-image -t task_id -o owner -w secret_key [-x days] [--user-threads threads] [--part-size partsize] [--dry-run] [--dont-verify-format] disk_image
```

Options

Name	Description
<i>disk_image</i>	The local file name of the disk image that you want to upload. Type: String Default: None Required: Yes Example: WinSvr8-32-disk1.vmdk
-t, --task <i>task_id</i>	The conversion task ID for the upload. Type: String Default: None Required: Yes Example: -t import-i-ffvko9js
-o, --owner-akid <i>access_key_id</i>	The access key ID of the bucket owner. Type: String Default: None Required: Yes Example: AKIAIOSFODNN7EXAMPLE
-w, --owner-sak <i>secret_access_key</i>	The secret access key of the bucket owner. Type: String Default: None Required: Yes Example: wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY

Name	Description
<code>-x, --expires <i>days</i></code>	The validity period for the signed Amazon S3 URLs that allow Amazon EC2 to access your file. Type: String Default: 30 days Required: No Example: <code>-x 10</code>
<code>--user-threads <i>threads</i></code>	The maximum number of threads to concurrently upload the file with. Type: String Default: 20 Required: No Example: <code>--user-threads 15</code>
<code>--part-size <i>partsize</i></code>	The size of each individual file part (in MB) that will be uploaded. The file will be split into multiple parts at most as large as the <i>partsize</i> parameter. Type: String Default: 8 Required: No Example: <code>--part-size 3</code>
<code>--dry-run</code>	Does not upload the file, only validates that the disk image matches a known type. Type: None Default: None Required: No Example: <code>--dry-run</code>
<code>--dont-verify-format</code>	Does not verify the file format. We don't recommend this option because it can result in a failed conversion. Type: None Default: None Required: No Example: <code>--dont-verify-format</code>

Common Options

Option	Description
<code>--region <i>REGION</i></code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>

Amazon Elastic Compute Cloud CLI Reference
Common Options

Option	Description
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN</code> <code>AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (-O, --aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command returns the following information:

- The disk image size and format
- The converted volume size
- The EBS volume size
- The percentage of the upload completed

Amazon EC2 command line tools display errors on stderr.

Example

Example Request

This example uploads the corresponding disk image of the Windows Server 2008 (32-bit) VM you want to migrate.

```
PROMPT>ec2-upload-disk-image ./WinSvr8-32-disk1.vmdk -t import-i-ffvko9js -o  
AKIAIOSFODNN7EXAMPLE -w wJalrXUtnFEMI/K7MDENG/bPxrFicYEXAMPLEKEY
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Related Commands

- [ec2-delete-disk-image](#) (p. 189)

- [ec2-import-instance](#) (p. 507)
- [ec2-import-volume](#) (p. 518)
- [ec2-resume-import](#) (p. 622)
- [ec2-cancel-conversion-task](#) (p. 64)
- [ec2-describe-conversion-tasks](#) (p. 272)

ec2-version

Description

Describes the build and API versions of the CLI tools.

The short version of this command is **ec2ver**.

Syntax

`ec2-version`

Options

This command does not have any options.

Common Options

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are . Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option. Example: <code>-O AKIAIOSFODNN7EXAMPLE</code> Note For more information, see the following section, <i>Deprecated Options</i> .

Option	Description
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	The secret access key associated with your AWS account. Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option. Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code> Note For more information, see the following section, <i>Deprecated Options</i> .
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	The AWS delegation token. Default: The value of the environment variable (if set).
<code>--connection-timeout TIMEOUT</code>	The connection timeout, in seconds. Example: <code>--connection-timeout 30</code>
<code>--request-timeout TIMEOUT</code>	The request timeout, in seconds. Example: <code>--request-timeout 45</code>
<code>-v, --verbose</code>	Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.
<code>-H, --headers</code>	Includes column headers in the command output.
<code>--show-empty-fields</code>	Shows empty columns as <code>(nil)</code> .
<code>--hide-tags</code>	Omits tags for tagged resources.
<code>--debug</code>	Displays internal debugging information. This can assist us when helping you troubleshooting problems.
<code>-?, --help, -h</code>	Displays usage information for the command.
<code>-</code>	Reads arguments from standard input. This is useful when piping the output from one command to the input of another. Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O, --aws-access-key`) and secret access key (`-W, --aws-secret-key`) now, as the private key (`-K, --private-key`) and X.509 certificate (`-C, --cert`) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key EC2-PRIVATE-KEY</code>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Option	Description
<code>-C, --cert EC2-CERT</code>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>

Output

This command displays the build and API version information.

Amazon EC2 command line tools display errors on stderr.

Example

Example Request

This example displays version information for the version of the CLI tools that you're using.

```
PROMPT> ec2-version
1.6.7.2 2013-02-01
```

Related Topics

Download

- [Getting Started with the Command Line Tools](#)

Common Options for CLI Tools

Most commands in the CLI tools accept the set of optional parameters described in the following table.

Option	Description
<code>--region REGION</code>	Overrides the region specified by the <code>EC2_URL</code> environment variable and the URL specified by the <code>-U</code> option. Default: The value of the <code>EC2_URL</code> environment variable, or <code>us-east-1</code> if <code>EC2_URL</code> isn't set. Example: <code>--region eu-west-1</code>
<code>-U, --url URL</code>	The uniform resource locator (URL) of the Amazon EC2 web service entry point. Default: The value of the <code>EC2_URL</code> environment variable, or <code>https://ec2.amazonaws.com</code> if <code>EC2_URL</code> isn't set. Example: <code>-U https://ec2.amazonaws.com</code>

Option	Description
<code>-O, --aws-access-key AWS_ACCESS_KEY</code>	<p>The access key ID associated with your AWS account. For more information, see Tell the Tools Who You Are.</p> <p>Default: The value of the <code>AWS_ACCESS_KEY</code> environment variable. If <code>AWS_ACCESS_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-O AKIAIOSFODNN7EXAMPLE</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-W, --aws-secret-key AWS_SECRET_KEY</code>	<p>The secret access key associated with your AWS account.</p> <p>Default: The value of the <code>AWS_SECRET_KEY</code> environment variable. If <code>AWS_SECRET_KEY</code> isn't set, you must specify this option.</p> <p>Example: <code>-W wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code></p> <p>Note For more information, see the following section, <i>Deprecated Options</i>.</p>
<code>-T, --security-token TOKEN AWS_DELEGATION_TOKEN</code>	<p>The AWS delegation token.</p> <p>Default: The value of the environment variable (if set).</p>
<code>--connection-timeout TIMEOUT</code>	<p>The connection timeout, in seconds.</p> <p>Example: <code>--connection-timeout 30</code></p>
<code>--request-timeout TIMEOUT</code>	<p>The request timeout, in seconds.</p> <p>Example: <code>--request-timeout 45</code></p>
<code>-v, --verbose</code>	<p>Displays verbose output, including the API request and response on the command line. This is useful if you are building tools to talk directly to our Query API.</p>
<code>-H, --headers</code>	<p>Includes column headers in the command output.</p>
<code>--show-empty-fields</code>	<p>Shows empty columns as <code>(nil)</code>.</p>
<code>--hide-tags</code>	<p>Omits tags for tagged resources.</p>
<code>--debug</code>	<p>Displays internal debugging information. This can assist us when helping you troubleshooting problems.</p>
<code>-?, --help, -h</code>	<p>Displays usage information for the command.</p>
<code>-</code>	<p>Reads arguments from standard input. This is useful when piping the output from one command to the input of another.</p> <p>Example: <code>ec2-describe-instances grep stopped cut -f 2 ec2-start-instances -</code></p>

Deprecated Options

For a limited time, you can still use the private key and X.509 certificate instead of your access key ID and secret access key. However, we recommend that you start using your access key ID (`-O`,

Amazon Elastic Compute Cloud CLI Reference Deprecated Options

--aws-access-key) and secret access key (-W, --aws-secret-key) now, as the private key (-K, --private-key) and X.509 certificate (-C, --cert) won't be supported after the transition period elapses. For more information, see [Tell the Tools Who You Are](#).

Option	Description
<code>-K, --private-key</code> <i>EC2-PRIVATE-KEY</i>	The private key to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_PRIVATE_KEY</code> environment variable. Example: <code>-K pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-C, --cert</code> <i>EC2-CERT</i>	The X.509 certificate to use when constructing requests to Amazon EC2. Default: The value of the <code>EC2_CERT</code> environment variable. Example: <code>-C cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>

Commands (AMI Tools)

You install and run the AMI tools on an Amazon EC2 instance-store backed instance to manage your instance-store backed AMIs. The AMI tools are distinct from the API tools, which are used to manage your other Amazon EC2 and Amazon VPC resources (instances, security groups, volumes, and so on). For more information, see the [API Tools Reference](#).

Note

Currently, the AMI tools are compatible only with Ruby 1.8x.

Topics

- [ec2-bundle-image](#) (p. 673)
- [ec2-bundle-vol](#) (p. 677)
- [ec2-delete-bundle](#) (p. 682)
- [ec2-download-bundle](#) (p. 685)
- [ec2-migrate-bundle](#) (p. 688)
- [ec2-migrate-manifest](#) (p. 692)
- [ec2-unbundle](#) (p. 695)
- [ec2-upload-bundle](#) (p. 697)
- [Common Options for AMI Tools](#) (p. 699)

ec2-bundle-image

Description

Creates an AMI from an operating system image created in a loopback file. For more information, see [Creating AMIs from a Loopback](#).

To get the AMI tools, go to [Amazon EC2 AMI Tools](#).

Note

Scripts that require a copy of the public key from the launch key pair must obtain the key from the instance's metadata (not the key file in the instance store) for instances bundled with the 2007-08-29 AMI tools and later. AMIs bundled before this release will continue to work normally.

Syntax

```
ec2-bundle-image -k private_key -c cert -u user_id -i image_path -r {i386 | x86_64} [-d destination] [-p ami_prefix] [--ec2cert cert_path] [--kernel kernel-id] [--ramdisk ramdisk_id] [--block-device-mapping block_device_mapping]
```

Note

When the image is for an Ubuntu Linux distribution, you must manually add the following syntax to this command:

```
--ec2cert /etc/ec2/amitools/cert-ec2.pem
```

Options

Option	Description
-k, --privatekey <i>private_key</i>	The path to the user's PEM-encoded RSA key file. Required: Yes Example: -k pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem
-c, --cert <i>cert</i>	The user's PEM encoded RSA public key certificate file. Required: Yes Example: -c cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem
-u, --user <i>user_id</i>	The user's AWS account ID without dashes. Do not use the Access Key ID. Required: Yes Example: -u 111122223333
-i, --image <i>image_path</i>	The path to the image to bundle. Required: Yes Example: -i /var/spool/my-image/version-2/debian.img

Amazon Elastic Compute Cloud CLI Reference
Options

Option	Description
<code>-r, --arch <i>architecture</i></code>	Image architecture. If you don't provide this on the command line, you'll be prompted to provide it when the bundling starts. Valid Values: <code>i386</code> <code>x86_64</code> Required: Yes Example: <code>-r x86_64</code>
<code>-d, --destination <i>destination</i></code>	The directory in which to create the bundle. Default: <code>/tmp</code> Required: No Example: <code>-d /var/run/my-bundle</code>
<code>-p, --prefix <i>ami_prefix</i></code>	The filename prefix for bundled AMI files. Default: The name of the image file. For example, if the image path is <code>/var/spool/my-image/version-2/debian.img</code> , then the default prefix is <code>debian.img</code> . Required: No Example: <code>-p my-image-is-special</code>
<code>--ec2cert <i>cert_path</i></code>	The path to the Amazon EC2 X.509 public key certificate. Default: <code>/etc/ec2/amitools/cert-ec2.pem</code> (varies, depending on tools) Required: No Example: <code>--ec2cert /etc/ec2/amiutil/cert-ec2.pem</code>
<code>--kernel <i>kernel_id</i></code>	The ID of the kernel to select. Default: <code>2.6.16-xenU</code> Required: No Example: <code>--kernel aki-ba3adfd3</code>
<code>--ramdisk <i>ramdisk_id</i></code>	The ID of the RAM disk to select. Note It is recommended that PV-GRUB be used instead of kernels and RAM disks. For more information, see PV-GRUB: A New Amazon Kernel Image in the <i>Amazon Elastic Compute Cloud User Guide</i> . Required: No Example: <code>--ramdisk ari-badbad00</code>

Option	Description
<code>--block-device-mapping <i>mappings</i></code>	<p>Default block-device-mapping scheme with which to launch the AMI. This defines how block devices are exposed to an instance of this AMI if the instance type supports the specified device.</p> <p>The scheme is a comma-separated list of key=value pairs, where each key is a virtual name and each value is the desired device name. Virtual names include:</p> <ul style="list-style-type: none"> • ami—The root file system device, as seen by the instance • root—The root file system device, as seen by the kernel • swap—The swap device, as seen by the instance • ephemeralN—The Nth ephemeral store <p>Required: No Example: <code>--block-device-mapping ami=sda1,root=/dev/sda1,ephemeral0=sda2,swap=sda3</code> Example: <code>--block-device-mapping ami=0,root=/dev/dsk/c0d0s0,ephemeral0=1</code></p>
<code>--no-filter</code>	<p>Do not use the default filtered files list.</p> <p>Required: No</p>
Common options	<p>For options common to most of the AMI Tools, go to Common Options for AMI Tools (p. 699).</p>

Output

Status messages describing the stages and status of the bundling process.

Example

This example creates a bundled AMI from an operating system image that was created in a loopback file.

```
$ ec2-bundle-image -k pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem -c cert-HKZYK
TAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem -u 111122223333 -i image.img -d bundled/ -p
fred -r x86_64
Please specify a value for arch [i386]:
Bundling image file...
Splitting bundled/fred.gz.crypt...
Created fred.part.00
Created fred.part.01
Created fred.part.02
Created fred.part.03
Created fred.part.04
Created fred.part.05
Created fred.part.06
Created fred.part.07
Created fred.part.08
Created fred.part.09
Created fred.part.10
```



```
Created fred.part.11
Created fred.part.12
Created fred.part.13
Created fred.part.14
Generating digests for each part...
Digests generated.
Creating bundle manifest...
ec2-bundle-image complete.
```

Related Topics

- [ec2-bundle-vol](#) (p. 677)
- [ec2-unbundle](#) (p. 695)
- [ec2-upload-bundle](#) (p. 697)
- [ec2-download-bundle](#) (p. 685)
- [ec2-delete-bundle](#) (p. 682)

ec2-bundle-vol

Description

Creates a bundled AMI by compressing, encrypting and signing a snapshot of the local machine's root file system.

To use `ec2-bundle-vol`, first you must install the AMI tools on the instance you are bundling, then run `ec2-bundle-vol` on that instance, not on a local system.

To get the AMI tools, go to [Amazon EC2 AMI Tools](#).

Note

Scripts that require a copy of the public key from the launch key pair must obtain the key from the instance's metadata (not the key file in the instance store) for instances bundled with the 2007-08-29 AMI tools and later. AMIs bundled before this release will continue to work normally. On a running instance, Amazon EC2 attempts to inherit product codes, kernel settings, RAM disk settings, and block device mappings with which the instance launched.

Syntax

```
ec2-bundle-vol -k private_key -u user_id -c cert -r architecture [-s size] [-d destination] [-e exclude_directory_1,exclude_directory_2,...] [-i include_file_1,include_file_2,...] [-p ami_prefix] [-v volume] [--ec2cert cert_path] [--fstab fstab_path] [--generate-fstab] [--kernel kernel-id] [--ramdisk ramdisk_id] [--block-device-mapping block_device_mapping] [--[no-]inherit] [--productcodes product_code]
```

Options

Option	Description
<code>-k, --privatekey <i>private_key</i></code>	The path to the user's PEM-encoded RSA key file. Required: Yes Example: <code>-k pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-u, --user <i>user_id</i></code>	The user's AWS account ID without dashes. Do not use the Access Key ID. Required: Yes Example: <code>-u 111122223333</code>
<code>-c, --cert <i>cert</i></code>	The user's PEM encoded RSA public key certificate file. Required: Yes Example: <code>-c cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-r, --arch <i>architecture</i></code>	Image architecture. If you don't provide this on the command line, you'll be prompted to provide it when the bundling starts. Valid Values: <code>i386 x86_64</code> Required: Yes Example: <code>-r x86_64</code>

Option	Description
<code>-s, --size size</code>	The size, in MB (1024 * 1024 bytes), of the image file to create. The maximum size is 10240 MB. Default: 10240 Required: No Example: <code>-s 2048</code>
<code>-d, --destination destination</code>	The directory in which to create the bundle. Default: <code>/tmp</code> Required: No Example: <code>-d /var/run/my-bundle</code>
<code>-e, --exclude directory_1,directory_2,...</code>	A list of absolute directory paths and files to exclude from the bundle operation. This parameter overrides the <code>--all</code> option. When exclude is specified, the directories and subdirectories listed with the parameter will not be bundled with the volume. Required: No Example: Assuming the mount point of the volume is <code>-v /foo</code> , and you want to exclude directories <code>/foo/bar</code> and <code>/foo/baz</code> , specify <code>-e /bar,/baz</code> .
<code>-i, --include file_1,file_2,...</code>	A list of files to include in the bundle operation. This option overrides the exclusion of files that are filtered out by default because they might contain sensitive information, such as your AWS credentials. Use this option to explicitly include a file that might contain sensitive data — i.e., <code>*.sw</code> , <code>*.swo</code> , <code>*.swp</code> , <code>*.pem</code> , <code>*.priv</code> , <code>*.pgp</code> , <code>*.jks</code> , <code>*/.ssh/authorized_keys</code> , <code>*/.bash_history</code> . The files listed with the parameter will be bundled with the volume. Required: No Example: Assuming the mount point of the volume is <code>-v /mnt/myvol/</code> and you want to include file <code>/mnt/myvol/foo/bar.pem</code> , specify <code>-i /foo/bar.pem</code> .
<code>-p, --prefix ami_prefix</code>	The filename prefix for bundled AMI files. Default: <code>image</code> Required: No Example: <code>-p my-image-is-special</code>
<code>-v, --volume volume</code>	The absolute path to the mounted volume from which to create the bundle. Default: The root directory (<code>/</code>) Required: No Example: <code>-v /mnt/my-customized-ami</code>
<code>-a, --all</code>	Bundle all directories, including those on remotely mounted file systems. Required: No Example: <code>-a</code>

Amazon Elastic Compute Cloud CLI Reference
Options

Option	Description
<code>--ec2cert <i>cert_path</i></code>	The path to the Amazon EC2 X.509 public key certificate. Default: <code>/etc/ec2/amitools/cert-ec2.pem</code> (varies, depending on tools) Required: No Example: <code>--ec2cert /etc/ec2/amiutil/cert-ec2.pem</code>
<code>--fstab <i>fstab_path</i></code>	The path to the fstab to bundle into the image. If this is not specified, Amazon EC2 bundles <code>/etc/fstab</code> . Required: No Example: <code>--fstab /etc/fstab</code>
<code>--generate-fstab</code>	Causes Amazon EC2 to bundle the volume using an Amazon EC2-provided fstab. Required: No Example: <code>--generate-fstab</code>
<code>--kernel <i>kernel_id</i></code>	The ID of the kernel to select. Required: No Example: <code>--kernel aki-ba3adfd3</code>
<code>--ramdisk <i>ramdisk_id</i></code>	The ID of the RAM disk to select. Note It is recommended that PV-GRUB be used instead of kernels and RAM disks. For more information, see PV-GRUB: A New Amazon Kernel Image in the <i>Amazon Elastic Compute Cloud User Guide</i> . Required: No Example: <code>--ramdisk ari-badbad00</code>
<code>--block-device-mapping <i>mappings</i></code>	Default block-device-mapping scheme with which to launch the AMI. This defines how block devices are exposed to an instance of this AMI if the instance type supports the specified device. The scheme is a comma-separated list of key=value pairs, where each key is a virtual name and each value is the desired device name. Virtual names include: <ul style="list-style-type: none">• ami—The root file system device, as seen by the instance• root—The root file system device, as seen by the kernel• swap—The swap device, as seen by the instance• ephemeralN—The Nth ephemeral store Required: No Example: <code>--block-device-mapping ami=sda1,root=/dev/sda1,ephemeral0=sda2,swap=sda3</code> Example: <code>--block-device-mapping ami=0,root=/dev/dsk/c0d0s0,ephemeral0=1</code>

Option	Description
<code>--[no-]inherit</code>	Whether the image should inherit the instance's metadata (the default is to inherit). Bundling will fail if you enable inherit but the instance metadata is not accessible. Required: No Example: <code>--inherit</code>
<code>--productcodes <i>product_code</i></code>	Product code to attach to the image at registration time. Required: No Example: <code>--productcodes 1234abcd</code>
<code>--no-filter</code>	Do not use the default filtered files list. Important The default filtered files list is used to avoid leaking of sensitive information, such as AWS credentials. Required: No
Common options	For options common to most of the AMI Tools, go to Common Options for AMI Tools (p. 699) .

Output

Status messages describing the stages and status of the bundling.

Example

This example creates a bundled AMI by compressing, encrypting and signing a snapshot of the local machine's root file system.

```
$ ec2-bundle-vol -d /mnt -k pk-HKZYKTAIG2ECMYIBH3HXV4ZBEXAMPLE.pem -c cert-
HKZYKTAIG2ECMYIBH3HXV4ZBEXAMPLE.pem -u 111122223333 -r x86_64
Copying / into the image file /mnt/image...
Excluding:
  sys
  dev/shm
  proc
  dev/pts
  proc/sys/fs/binfmt_misc
  dev
  media
  mnt
  proc
  sys
  tmp/image
  mnt/img-mnt
1+0 records in
1+0 records out
mke2fs 1.38 (30-Jun-2005)
warning: 256 blocks unused.

Splitting /mnt/image.gz.crypt...
Created image.part.00
```

```
Created image.part.01
Created image.part.02
Created image.part.03
...
Created image.part.22
Created image.part.23
Generating digests for each part...
Digests generated.
Creating bundle manifest...
Bundle Volume complete.
```

Related Topics

- [ec2-bundle-image](#) (p. 673)
- [ec2-unbundle](#) (p. 695)
- [ec2-upload-bundle](#) (p. 697)
- [ec2-download-bundle](#) (p. 685)
- [ec2-delete-bundle](#) (p. 682)

ec2-delete-bundle

Description

Deletes the specified bundle from Amazon S3 storage.

To get the AMI tools, go to [Amazon EC2 AMI Tools](#).

Syntax

```
ec2-delete-bundle -b s3_bucket -a access_key_id -s secret_key [-m manifest_path]
[-p ami_prefix] [--url url] [--retry] [-y] [--clear]
```

Options

Option	Description
<code>-b, --bucket <i>s3_bucket</i></code>	The name of the Amazon S3 bucket containing the bundled AMI, followed by an optional '/'-delimited path prefix Required: Yes Example: <code>-b myawsbucket/ami-001</code>
<code>-a, --access-key <i>access_key_id</i></code>	The AWS access key ID. Required: Yes Example: <code>-a AKIAIOSFODNN7EXAMPLE</code>
<code>-s, --secret-key <i>secret_key</i></code>	The AWS secret access key. Required: Yes Example: <code>-s wJalrXUtnFEMI/K7MDENG/bPxrFicYEXAMPLEKEY</code>
<code>-m, --manifest <i>manifest_path</i></code>	The path to the unencrypted manifest file. Required: Conditional Condition: You must specify <code>--prefix</code> or <code>--manifest</code> . Example: <code>-m /var/spool/my-first-bundle/image.manifest.xml</code>
<code>-p, --prefix <i>ami_prefix</i></code>	The bundled AMI filename prefix. Provide the entire prefix. For example, if the prefix is <code>image.img</code> , use <code>-p image.img</code> and not <code>-p image</code> . Required: Conditional Condition: You must specify <code>--prefix</code> or <code>--manifest</code> . Example: <code>-p image.img</code>
<code>--url <i>url</i></code>	The Amazon S3 service URL. Default: <code>https://s3.amazonaws.com</code> Required: No Example: <code>--url https://s3.example.com</code>

Option	Description
<code>--retry</code>	Automatically retries on all Amazon S3 errors, up to five times per operation. Required: No Example: <code>--retry</code>
<code>-y, --yes</code>	Automatically assumes the answer to all prompts is 'yes'. Required: No Example: <code>-y</code>
<code>--clear</code>	Deletes the specified bundle from the Amazon S3 bucket and deletes the bucket, if empty. Required: No Example: <code>--clear</code>
Common options	For options common to most of the AMI Tools, go to Common Options for AMI Tools (p. 699) .

Output

Amazon EC2 displays status messages indicating the stages and status of the delete process.

Example

This example deletes a bundle from Amazon S3.

```
$ ec2-delete-bundle -b myawsbucket -a AKIAIOSFODNN7EXAMPLE -s wJalrXUtn
FEMI/K7MDENG/bPxrFiCYEXAMPLEKEY -p fred
Deleting files:
myawsbucket/fred.manifest.xml
myawsbucket/fred.part.00
myawsbucket/fred.part.01
myawsbucket/fred.part.02
myawsbucket/fred.part.03
myawsbucket/fred.part.04
myawsbucket/fred.part.05
myawsbucket/fred.part.06
Continue? [y/n]
y
Deleted myawsbucket/fred.manifest.xml
Deleted myawsbucket/fred.part.00
Deleted myawsbucket/fred.part.01
Deleted myawsbucket/fred.part.02
Deleted myawsbucket/fred.part.03
Deleted myawsbucket/fred.part.04
Deleted myawsbucket/fred.part.05
Deleted myawsbucket/fred.part.06
ec2-delete-bundle complete.
```

Related Topics

- [ec2-bundle-image \(p. 673\)](#)

- [ec2-bundle-vol](#) (p. 677)
- [ec2-unbundle](#) (p. 695)
- [ec2-upload-bundle](#) (p. 697)
- [ec2-download-bundle](#) (p. 685)

ec2-download-bundle

Description

Downloads the specified bundles from S3 storage.

To get the AMI tools, go to [Amazon EC2 AMI Tools](#).

Syntax

```
ec2-download-bundle -b s3_bucket [-m manifest] -a access_key_id -s secret_key
-k private_key [-p ami_prefix] [-d directory] [--retry] [--url url]
```

Options

Option	Description
-b, --bucket <i>s3_bucket</i>	The name of the Amazon S3 bucket where the bundle is located, followed by an optional '/'-delimited path prefix. Required: Yes Example: -b myawsbucket/ami-001
-m, --manifest <i>manifest</i>	The manifest filename (without the path). We recommend you specify either the manifest (option -m), or the filename prefix (option -p). Required: No Example: -m my-image.manifest.xml
-a, --access-key <i>access_key_id</i>	Your AWS access key ID. Required: Yes Example: -a AKIAIOSFODNN7EXAMPLE
-s, --secret-key <i>secret_key</i>	Your AWS secret access key. Required: Yes Example: -s wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY
-k, --privatekey <i>private_key</i>	The private key used to decrypt the manifest. Required: Yes Example: -k pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem
-p, --prefix <i>ami_prefix</i>	The filename prefix for the bundled AMI files. Default: image Required: No Example: -p my-image

Option	Description
<code>-d, --directory <i>directory</i></code>	The directory where the downloaded bundle is saved. The directory must exist. Default: The current working directory. Required: No Example: <code>-d /tmp/my-downloaded-bundle</code>
<code>--retry</code>	Automatically retries on all Amazon S3 errors, up to five times per operation. Required: No Example: <code>--retry</code>
<code>--url <i>url</i></code>	The S3 service URL. Default: <code>https://s3.amazonaws.com</code> Required: No Example: <code>--url https://s3.example.com</code>
Common options	For options common to most of the AMI Tools, go to Common Options for AMI Tools (p. 699) .

Output

Status messages indicating the various stages of the download process are displayed.

Example

This example creates the `bundled` directory and downloads the bundle from the `myawsbucket` Amazon S3 bucket.

```
$ mkdir bundled
$ ec2-download-bundle -b myawsbucket -m fred.manifest.xml -a AKIAIOSFODNN7EXAMPLE
-s wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY -k pk-HKZYKTAIG2ECMXY
IBH3HXV4ZBEXAMPLE.pem -d bundled
downloading manifest https://s3.amazonaws.com/myawsbucket/image.manifest.xml
to bundled/image.manifest.xml ...
downloading part https://s3.amazonaws.com/myawsbucket/image.part.00 to
bundled/image.part.00 ...
Downloaded image.part.00 from https://s3.amazonaws.com/myawsbucket.
downloading part https://s3.amazonaws.com/myawsbucket/image.part.01 to
bundled/image.part.01 ...
Downloaded image.part.01 from https://s3.amazonaws.com/myawsbucket.
downloading part https://s3.amazonaws.com/myawsbucket/image.part.02 to
bundled/image.part.02 ...
Downloaded image.part.02 from https://s3.amazonaws.com/myawsbucket.
downloading part https://s3.amazonaws.com/myawsbucket/image.part.03 to
bundled/image.part.03 ...
Downloaded image.part.03 from https://s3.amazonaws.com/myawsbucket.
downloading part https://s3.amazonaws.com/myawsbucket/image.part.04 to
bundled/image.part.04 ...
Downloaded image.part.04 from https://s3.amazonaws.com/myawsbucket.
downloading part https://s3.amazonaws.com/myawsbucket/image.part.05 to
bundled/image.part.05 ...
```

```
Downloaded image.part.05 from https://s3.amazonaws.com/myawsbucket.  
downloading part https://s3.amazonaws.com/myawsbucket/image.part.06 to  
bundled/image.part.06 ...  
Downloaded image.part.06 from https://s3.amazonaws.com/myawsbucket.  
Download Bundle complete.
```

Note

This example uses the Linux and UNIX `mkdir` command.

Related Topics

- [ec2-bundle-image](#) (p. 673)
- [ec2-bundle-vol](#) (p. 677)
- [ec2-unbundle](#) (p. 695)
- [ec2-upload-bundle](#) (p. 697)
- [ec2-delete-bundle](#) (p. 682)

ec2-migrate-bundle

Description

Copies a bundled AMI from one region to another.

Note

This tool is replaced by [ec2-migrate-image](#) (p. 524).

To get the AMI tools, go to [Amazon EC2 AMI Tools](#).

Note

After copying a bundled AMI to a new region, make sure to register it as a new AMI. During migration, Amazon EC2 replaces the kernel and RAM disk in the manifest file with a kernel and RAM disk designed for the destination region. Unless the `--no-mapping` parameter is given, `ec2-migrate-bundle` might use the Amazon EC2 `DescribeRegions` and `DescribeImages` operations to perform automated mappings. It is recommended that PV-GRUB be used instead of kernels and RAM disks. For more information, see [PV-GRUB: A New Amazon Kernel Image](#) in the *Amazon Elastic Compute Cloud User Guide*.

Syntax

```
ec2-migrate-bundle -k private_key -c cert -a access_key_id -s secret_key --bucket source_s3_bucket --destination-bucket destination_s3_bucket --manifest manifest_path [--location location] [--ec2cert ec2_cert_path] [--kernel kernel-id] [--ramdisk ramdisk_id] [--no-mapping] [--region mapping_region_name]
```

Options

Option	Description
<code>-k, --privatekey <i>private_key</i></code>	The path to the user's PEM-encoded RSA key file. Required: Yes Example: <code>-k pk-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-c, --cert <i>cert</i></code>	The user's PEM encoded RSA public key certificate file. Required: Yes Example: <code>-c cert-HKZYKTAIG2ECMXIYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-a, --access-key <i>access_key_id</i></code>	The AWS access key ID. Required: Yes Example: <code>-a AKIAIOSFODNN7EXAMPLE</code>
<code>-s, --secret-key <i>secret_key</i></code>	The AWS secret access key. Required: Yes Example: <code>-s wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code>

Amazon Elastic Compute Cloud CLI Reference
Options

Option	Description
<code>-b, --bucket <i>source_s3_bucket</i></code>	The source Amazon S3 bucket where the AMI is located, followed by an optional '/'-delimited path prefix. Required: Yes Example: <code>--bucket myawsbucket</code>
<code>-d, --destination-bucket <i>destination_s3_bucket</i></code>	The destination Amazon S3 bucket, followed by an optional '/'-delimited path prefix. If the destination bucket does not exist, it is created. Required: Yes Example: <code>--destination-bucket myotherawsbucket</code>
<code>-m, --manifest <i>manifest</i></code>	The location of the Amazon S3 source manifest. Default: None Required: Yes Example: <code>--manifest my-ami.manifest.xml</code>
<code>--location <i>location</i></code>	The location of the destination Amazon S3 bucket. If the bucket exists and the location is specified, the tool exits with an error. if the specified location does not match the actual location. If the bucket exists and no location is specified, the tool uses the bucket's location. If the bucket does not exist and the location is specified, the tool creates the bucket in the specified location. If the bucket does not exist and location is not specified, the tool creates the bucket without a location constraint (in the US). Valid Values: US EU us-west-1 ap-southeast-1 Default: US Required: No Example: <code>--location EU</code>
<code>--acl {public-read aws-exec-read}</code>	The access control list policy of the bundled image. Valid Values: public-read aws-exec-read Default: aws-exec-read Required: No Example: <code>--acl public-read</code>
<code>--retry</code>	Automatically retries on all Amazon S3 errors, up to five times per operation. Required: No Example: <code>--retry</code>
<code>--kernel <i>kernel_id</i></code>	The ID of the kernel to select. Required: No Example: <code>--kernel aki-ba3adfd3</code>

Option	Description
<code>--ramdisk <i>ramdisk_id</i></code>	<p>The ID of the RAM disk to select.</p> <p>Note It is recommended that PV-GRUB be used instead of kernels and RAM disks. For more information, see PV-GRUB: A New Amazon Kernel Image in the <i>Amazon Elastic Compute Cloud User Guide</i>.</p> <p>Required: No Example: <code>--ramdisk ari-badbad00</code></p>
<code>--no-mapping</code>	<p>Disables automatic mapping of kernels and RAM disks.</p> <p>Required: No Example: <code>--no-mapping</code></p>
<code>--region</code>	<p>Region to look up in the mapping file. If no region is specified, Amazon EC2 attempts to determine the region from the location of the Amazon S3 bucket.</p> <p>Required: No Example: <code>--region eu-west-1</code></p>
Common options	<p>For options common to most of the AMI Tools, go to Common Options for AMI Tools (p. 699).</p>

Output

Status messages describing the stages and status of the bundling process.

Example

This example copies the AMI specified in the `my-ami.manifest.xml` manifest from the US to the EU.

```
$ ec2-migrate-bundle --cert cert-THUMBPRINT.pem --privatekey pk-THUMBPRINT.pem
--access-key AKIAIOSFODNN7EXAMPLE --secret-key wJalrXUtnFEMI/K7MDENG/bPxrFi
CYEXAMPLEKEY --bucket myawsbucket --destination-bucket myotherawsbucket --
manifest my-ami.manifest.xml --location EU
Downloading manifest my-ami.manifest.xml from myawsbucket to /tmp/ami-migration-
my-ami.manifest.xml/my-ami.manifest.xml ...
Copying 'my-ami.part.00'...
Copying 'my-ami.part.01'...
Copying 'my-ami.part.02'...
Copying 'my-ami.part.03'...
Copying 'my-ami.part.04'...
Copying 'my-ami.part.05'...
Copying 'my-ami.part.06'...
Copying 'my-ami.part.07'...
Copying 'my-ami.part.08'...
Copying 'my-ami.part.09'...
Copying 'my-ami.part.10'...
Your new bundle is in S3 at the following location:
myotherawsbucket/my-ami.manifest.xml
```

Related Topics

- [ec2-register](#) (p. 566)
- [ec2-run-instances](#) (p. 633)

ec2-migrate-manifest

Description

Modifies a bundled AMI to work in a new region.

You must use this command if you are bundling in one region for use in another or if you copy a bundled AMI out of band (without using `ec2-migrate-bundle`) and want to use it in a different region.

To get the AMI tools, go to [Amazon EC2 AMI Tools](#).

Note

This command replaces the kernel and RAM disk in the manifest file with a kernel and RAM disk designed for the destination region.

It is recommended that PV-GRUB be used instead of kernels and RAM disks. For more information, see [PV-GRUB: A New Amazon Kernel Image](#) in the *Amazon Elastic Compute Cloud User Guide*.

Syntax

```
ec2-migrate-manifest -k private_key -c cert -m manifest_path {(-a access_key_id
-s secret_key --region mapping_region_name) | --no-mapping} [--kernel kernel-id]
[--ramdisk ramdisk_id] [--ec2cert ec2_cert_path]
```

Options

Option	Description
<code>-k, --privatekey <i>private_key</i></code>	The path to the user's PEM-encoded RSA key file. Required: Yes Example: <code>-k pk-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-c, --cert <i>cert</i></code>	The user's PEM encoded RSA public key certificate file. Required: Yes Example: <code>-c cert-HKZYKTAIG2ECMXYIBH3HXV4ZBEXAMPLE.pem</code>
<code>-a, --access-key <i>access_key_id</i></code>	The AWS access key ID. Required: Conditional Condition: Required if using automatic mapping. Example: <code>-a AKIAIOSFODNN7EXAMPLE</code>
<code>-s, --secret-key <i>secret_key</i></code>	The AWS secret access key. Required: Conditional Condition: Required if using automatic mapping. Example: <code>-s wJalrXUtnFEMI/K7MDENG/bPxrFicYEXAMPLEKEY</code>
<code>--manifest <i>manifest_path</i></code>	The manifest file. Required: Yes Example: <code>--manifest my-ami.manifest.xml</code>

Option	Description
<code>--kernel <i>kernel_id</i></code>	The ID of the kernel to select. Required: No Example: <code>--kernel aki-ba3adfd3</code>
<code>--ramdisk <i>ramdisk_id</i></code>	The ID of the RAM disk to select. Note It is recommended that PV-GRUB be used instead of kernels and RAM disks. For more information, see PV-GRUB: A New Amazon Kernel Image in the <i>Amazon Elastic Compute Cloud User Guide</i> . Required: No Example: <code>--ramdisk ari-badbad00</code>
<code>--mapping-file <i>mapping_file</i></code>	Overrides the file containing kernel and RAM disk region mappings. Required: No Example: <code>--mapping-file eu-mappings</code>
<code>--mapping-url <i>url</i></code>	Overrides the file containing kernel and RAM disk region mappings from the specified hostname portion of a URL. Required: No Example: <code>--mapping-url mysite.com/eu-mappings</code>
<code>--no-mapping</code>	Disables automatic mapping of kernels and RAM disks. Required: Conditional Condition: Required if you're not providing the <code>-a</code> , <code>-s</code> , and <code>--region</code> options (which are used for automatic mapping).
<code>--region</code>	Region to look up in the mapping file. Condition: Required if using automatic mapping. Required: Conditional Example: <code>--region eu-west-1</code>
Common options	For options common to most of the AMI Tools, go to Common Options for AMI Tools (p. 699) .

Output

Status messages describing the stages and status of the bundling process.

Example

This example copies the AMI specified in the `my-ami.manifest.xml` manifest from the US to the EU.

```
$ ec2-migrate-manifest --manifest my-ami.manifest.xml --cert cert-HKZYKTAIG2ECMXY
IBH3HXV4ZBZQ55CLO.pem --privatekey pk-HKZYKTAIG2ECMXYIBH3HXV4ZBZQ55CLO.pem --
region eu-west-1
```

```
Backing up manifest...
```

```
Successfully migrated my-ami.manifest.xml It is now suitable for use in eu-west-1.
```

Related Topics

- [ec2-register](#) (p. 566)
- [ec2-run-instances](#) (p. 633)

ec2-unbundle

Description

Recreates the AMI from the bundled AMI parts.

To get the AMI tools, go to [Amazon EC2 AMI Tools](#).

Syntax

```
ec2-unbundle -m manifest -k private_key [-d destination_directory] [-s source_directory]
```

Options

Option	Description
-m, --manifest <i>manifest</i>	The path to the unencrypted AMI manifest file. Required: Yes Example: -m /var/spool/my-first-bundle/Manifest
-k, --privatekey <i>private_key</i>	The path to your PEM-encoded RSA key file. Required: Yes Example: -k \$HOME/pk-234242example.pem
-d, --destination <i>destination_directory</i>	The directory in which to unbundle the AMI. The destination directory must exist. Default: The current directory. Required: No Example: -d /tmp/my-image
-s, --source <i>source_directory</i>	The directory containing the bundled AMI parts. Default: The current directory. Required: No Example: -s /tmp/my-bundled-image
Common options	For options common to most of the AMI Tools, go to Common Options for AMI Tools (p. 699) .

Example

This Linux and UNIX example unbundles the AMI specified in the `fred.manifest.xml` file.

```
$ mkdir unbundled
$ ec2-unbundle -m fred.manifest.xml -s bundled -d unbundled

$ ls -l unbundled
total 1025008
```

```
-rw-r--r-- 1 root root 1048578048 Aug 25 23:46 fred.img
```

Output

Status messages indicating the various stages of the unbundling process are displayed.

Related Topics

- [ec2-bundle-image](#) (p. 673)
- [ec2-bundle-vol](#) (p. 677)
- [ec2-upload-bundle](#) (p. 697)
- [ec2-download-bundle](#) (p. 685)
- [ec2-delete-bundle](#) (p. 682)

ec2-upload-bundle

Description

Uploads a bundled AMI to Amazon S3 storage.

To get the AMI tools, go to [Amazon EC2 AMI Tools](#).

Syntax

```
ec2-upload-bundle -b s3_bucket -m manifest -a access_key_id -s secret_key [--acl acl] [-d directory] [--part part] [--location location] [--url url] [--retry] [--skipmanifest]
```

Options

Option	Description
<code>-b, --bucket <i>s3_bucket</i></code>	The name of the Amazon S3 bucket in which to store the bundle, followed by an optional '/'-delimited path prefix. If the bucket doesn't exist it will be created (if the bucket name is available). Required: Yes Example: <code>-b myawsbucket/ami-001</code>
<code>-m, --manifest <i>manifest</i></code>	The path to the manifest file. The manifest file is created during the bundling process and can be found in the directory containing the bundle. Required: Yes Example: <code>-m image.manifest.xml</code>
<code>-a, --access-key <i>access_key_id</i></code>	Your AWS access key ID. Required: Yes Example: <code>-a AKIAIOSFODNN7EXAMPLE</code>
<code>-s, --secret-key <i>secret_key</i></code>	Your AWS secret access key. Required: Yes Example: <code>-s wJalrXUtnFEMI/K7MDENG/bPxrFiCYEXAMPLEKEY</code>
<code><i>acl</i></code>	The access control list policy of the bundled image. Valid Values: <code>public-read aws-exec-read</code> Default: <code>aws-exec-read</code> Required: No Example: <code>--acl public-read</code>
<code>-d, --directory <i>directory</i></code>	The directory containing the bundled AMI parts. Default: The directory containing the manifest file (see the <code>-m</code> option). Required: No Example: <code>-d /var/run/my-bundle</code>

Option	Description
<code>--part <i>part</i></code>	Starts uploading the specified part and all subsequent parts. Required: No Example: <code>--part 04</code>
<code>--location <i>location</i></code>	The location of the destination Amazon S3 bucket. If the bucket exists and you specify a location that doesn't match the bucket's actual location, the tool exits with an error. If the bucket exists and you don't specify a location, the tool uses the bucket's location. If the bucket does not exist and you specify a location, the tool creates the bucket in the specified location. If the bucket does not exist and you don't specify a location, the tool creates the bucket without a location constraint (in the US). Valid Values: US EU us-west-1 ap-southeast-1 Default: US Required: No Example: <code>--location EU</code>
<code>--url <i>url</i></code>	The S3 service URL. Default: <code>https://s3.amazonaws.com</code> Required: No Example: <code>--url https://s3.example.com</code>
<code>--retry</code>	Automatically retries on all Amazon S3 errors, up to five times per operation. Required: No Example: <code>--retry</code>
<code>--skipmanifest</code>	Does not upload the manifest. Required: No Example: <code>--skipmanifest</code>
Common options	For options common to most of the AMI Tools, go to Common Options for AMI Tools (p. 699) .

Output

Amazon EC2 displays status messages that indicate the stages and status of the upload process.

Example

This example uploads the bundle specified by the `bundled/fred.manifest.xml` manifest.

```
$ ec2-upload-bundle -b myawsbucket -m bundled/fred.manifest.xml -a AKIAIOSFOD
NN7EXAMPLE -s wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY
Creating bucket...
Uploading bundled image parts to the S3 bucket myawsbucket ...
Uploaded fred.part.00
Uploaded fred.part.01
```

```
Uploaded fred.part.02
Uploaded fred.part.03
Uploaded fred.part.04
Uploaded fred.part.05
Uploaded fred.part.06
Uploaded fred.part.07
Uploaded fred.part.08
Uploaded fred.part.09
Uploaded fred.part.10
Uploaded fred.part.11
Uploaded fred.part.12
Uploaded fred.part.13
Uploaded fred.part.14
Uploading manifest ...
Uploaded manifest.
Bundle upload completed.
```

Related Topics

- [ec2-bundle-image](#) (p. 673)
- [ec2-bundle-vol](#) (p. 677)
- [ec2-unbundle](#) (p. 695)
- [ec2-download-bundle](#) (p. 685)
- [ec2-delete-bundle](#) (p. 682)

Common Options for AMI Tools

Most of the commands described in this section accept the set of optional parameters described in the following table.

Option	Description
<code>--help, -h</code>	Display the help message.
<code>--version</code>	Displays the version and copyright notice.
<code>--manual</code>	Displays the manual entry.
<code>--batch</code>	Runs in batch mode, suppressing user interaction and confirmation.
<code>--debug</code>	Prints internal debugging information. This is useful to assist us when troubleshooting problems.