



CELL PHONE/PORTABLE MUSIC PLAYER CASES (TO KNIT)

MEASUREMENTS

Mini case: To fit electronic device 2 ins [5 cm] wide by 3¾ ins [9.5 cm] long by ½ inch [1.5 cm] thick.

Regular case: To fit electronic device 2½ ins [6 cm] wide by 4¼ ins [11 cm] long by ¾ inch [2 cm] thick.

MATERIALS

Bernat® Satin

(Solids 100 g/3.5 oz, Ombres 80 g/2.8 oz)

Mini Case 1 ball

Regular Case 1 ball

Sizes 3.75 mm (U.S. 5) and 6 mm (U.S. 10) knitting needles **or size needed to obtain gauge**. Cable needle. Pair of D-rings ¾ inch [1.5 cm] wide. Small patch of hook and loop tape.

GAUGE

22 sts and 28 rows = 4 ins [10 cm] with smaller needles in stocking st.

ABBREVIATIONS

www.bernat.com/glossary

INSTRUCTIONS

The instructions are written for smaller size. If changes are necessary for larger size the instructions will be written thus ().

FRONT

Beg at top edge, with smaller needles cast on 13 (17) sts.

***Knit 3 rows, noting first row is WS.

***Change to larger needles and knit 1 row.

Proceed in Twist Pat as follows:

1st row: (WS). P2. *Slip next st onto cable needle and leave at back of work. P1. P1 from cable needle. Rep from * to last st. P1.

2nd row: K2. *Slip next st onto cable needle and leave at front of work. K1. K1 from cable needle. Rep from * to last st. K1.

Last 2 rows form Twist Pat.**

Cont in pat until work from beg measures 3½ (4) ins [9 (10) cm], ending with WS facing for next row.

Change to smaller needles and pat 1 row. Cast off knitwise.

BACK

Note: (yo) twice counts as 2 sts.

Beg at edge of flap, with smaller needles, cast on 13 (17) sts.

Work from ** to ** as given for Front.

Cont in pat until work from beg measures 1¾ (2) ins [4.5 (5) cm], ending with WS facing for next row.

Change to smaller needles and pat 1 row.

Next row: (RS). Knit, dec 3 sts evenly across. 10 (14) sts.

Knit 2 rows.

Opening for Jack: Next row: (WS). K1 (5). K2tog. (yo) twice. ssk. Knit to end of row.

Next row: K6. (K1. P1). Knit to end of row.

Next row: Knit, inc 3 sts evenly across. 13 (17) sts. Place marker at each end of last row.

Work from *** to ** as given for Front.

Cont in pat until work from marked row measures 3½ (4) ins [9 (10) cm], ending with WS facing for next row.


Change to smaller needles and pat 1 row. Cast off knitwise (RS).

GUSSET and STRAPS

With smaller needles, cast on 83 (88) sts. Place markers on 20th and 64th (69th) sts. Knit 4 (6) rows, noting first row is RS. Cast off loosely.

FINISHING

Beg and ending at markers on Gusset, sew side and bottom edges of Front to Gusset. Sew side and bottom edges of Back to Gusset, aligning markers. Fold end of one strap through D-rings and sew in position. Sew patch of loop tape to WS of flap. Sew patch of hook tape to RS of Front to correspond to loop tape.



P.O. Box 40, Listowel ON N4W 3H3
"home style... life style... your style."