

V-NECK BABY CARDIGAN.

3ply yarn or 2 strands of 2/30s.

Sizes 8(10)(12)(14)(16)(18)(20)(21) inch chest.

E6000 machine.

Stitch pattern A 1000, Tech 138.

Stitch size 4/4. Tension 5 sts and 16 rows to 1 inch.

Use cast on 2.

Back.

Cast on over 24(28)(32)(36)(40)(46)(50)(56) needles. S/S 2.5/2.5 for row 1 and 3/3 for CX rows.

Continue at 3/3 for 8(8)(10)(10)(12)(12)(14)(16) rows.

Stitch Patt A. RC 000. S/S 4/4.

Knit 80(84)(88)(104)(128)(140)(152)(176) rows, marking the armhole at each end of row 40(40)(40)(48)(52)(60)(76)(88).

Mark the centre 8(10)(12)(14)(16)(18)(20)(22) sts. and cast off.

Fronts.

Cast on and rib as for back using 12(14)(16)(18)(20)(22)(24)(28) needles.

Stitch Patt A. RC000. S/S 4/4.

Knit 40(40)(40)(48)(52)(60)(76)(88) rows. Mark row end at armhole edge.

Decrease 1st. at front edge every 8(8)(8)(8)(8)(10)(8)(8) rows to 8(9)(10)(11)(12)(14)(15)(17) needles. Knit to row 80(84)(88)(104)(128)(140)(152)(176). Cast off.

Sleeves.

Cast on over 20(20)(20)(22)(22)(24)(26)(30) needles. S/S 2/2 for row 1 and 2.5/2.5 for CX rows.

Continue at 2.5/2.5 for 6(6)(10)(10)(20)(20)(20)(20) rows.

Stitch Patt A. RC000. S/S 4/4.

Increase 1st at each end every 10(12)(12)(10)(8)(8)(9)(9) rows to 24(28)(30) (34)(40)(46)(50)(56) needles.

Knit to row 48(56)(64)(72)(90)(100)(116)(120). Cast off.

Neckband.

Cast on over 5(5)(7)(7)(7)(7)(7) needles, S/S 3/3. Make buttonholes after 4th and every 16(16)(16)(18)(20)(22)(18)(24) rows to 3(3)(3)(3)(3)(3)(4) (4) holes.

Knit to row 220(240)(260)(280)(300)(340)(360)(420) app. Release from machine.

Making up.

Join shoulder seams. Place sleeve top between markers and stitch in position. Join side and sleeve seams.

Attach neckband stretching slightly to fit. Unravel any extra knitting and cast off on size 14 needles (hand-knitting.)

Attach buttons to match holes.

Hat for premature babies

Fisherman's rib.

E 6000. No console required.

3ply yarn or 2 strands 2/30s.

Cast on over 40 (46) (50) needles. s/s 3.5/3.5

N/EX . Work 50 (60) (64) rows

EX/N . work 50 (60) (64) rows

N/N . 3 rows

N/N s/s 2.5/2.5 2rows

1 row 8/8.

Remove from machine on waste yarn, leaving a long thread.

Remove waste yarn.

Thread end of main yarn through the last row of knitting and pull up. Stitch seam.

Turn back lower edge to form brim.

Our website www.andycraft.co.uk

Ann Baker